

TOPS-20 Commands Reference Manual

AA-FP65A-TM

September 1985

This manual describes all operating system commands available to the nonprivileged user of TOPS-20. For easy reference, the command descriptions are arranged alphabetically.

This manual supersedes the manual of the same name and order number, AA-5115B-TM.

Change bars in the margins indicate material that has been added or changed since the previous printing of this manual. Bullets indicate that material has been deleted.

OPERATING SYSTEM: TOPS-20 (KL Model B) V6.1

SOFTWARE: TOPS-20 EXEC V6.1

Software and manuals should be ordered by title and order number. In the United States, send orders to the nearest distribution center. Outside the United States, orders should be directed to the nearest DIGITAL Field Sales Office or representative.

Northeast/Mid-Atlantic Region

Digital Equipment Corporation
PO Box CS2008
Nashua, New Hampshire 03061
Telephone:(603)884-6660

Central Region

Digital Equipment Corporation
Accessories and Supplies Center
1050 East Remington Road
Schaumburg, Illinois 60195
Telephone:(312)640-5612

Western Region

Digital Equipment Corporation
Accessories and Supplies Center
632 Caribbean Drive
Sunnyvale, California 94086
Telephone:(408)734-4915

First Printing, February 1979
Revised, January 1980
Updated, April 1982
Updated, December 1982
Revised, September 1985

© Digital Equipment Corporation 1979, 1982, 1985. All Rights Reserved.

The information in this document is subject to change without notice and should not be construed as a commitment by Digital Equipment Corporation. Digital Equipment Corporation assumes no responsibility for any errors that may appear in this document.

The software described in this document is furnished under a license and may only be used or copied in accordance with the terms of such license.

No responsibility is assumed for the use or reliability of software on equipment that is not supplied by DIGITAL or its affiliated companies.

The following are trademarks of Digital Equipment Corporation:



DEC	MASSBUS	RSX
DECmate	PDP	RT
DECsystem-10	P/OS	UNIBUS
DECSYSTEM-20	Professional	VAX
DECUS	Q-BUS	VMS
DECwriter	Rainbow	VT
DIBOL	RSTS	Work Processor

The postage-prepaid READER'S COMMENTS form on the last page of this document requests the user's critical evaluation to assist us in preparing future documentation.

CONTENTS

PREFACE		vii
INTRODUCTION		Intro-1
COMMAND DESCRIPTIONS		
ACCESS	Obtains ownership rights to a directory	1
ADVISE	Sends commands to another user's job	4
APPEND	Adds files onto end of another file	8
ARCHIVE	Makes permanent off-line copies of files	12
ASSIGN	Allocates a device for your job	15
ATTACH	Attaches a job to your terminal	16
BACKSPACE	Moves a magnetic tape or tape set backward	19
BLANK	Clears your video terminal screen	21
BREAK	Ends links made by TALK command	22
BUILD	Creates, modifies, or deletes a directory	23
CANCEL	Withdraws queue requests	37
CLOSE	Closes open files and releases JFNs	44
COMPILE	Translates source programs into object programs	46
CONNECT	Connects your job to a directory	54
CONTINUE	Continues a halted program	57
COPY	Makes copies of files	64
CREATE	Creates a file	71
CREF	Translates .CRF files into listings	77
CSAVE	Stores compressed copy of memory in a file	81
DAYTIME	Tells the date and time	83
DDT	Starts a debugging program	84

DEASSIGN	Gives up previously assigned devices	87
DEBUG	Loads your program with a debugging program; compiles your program if necessary; then starts the debugging program	89
DEFINE	Establishes or withdraws logical names	98
DELETE	Marks files for later erasure	101
DEPOSIT	Changes contents of a memory location	105
DETACH	Disengages a job from your terminal	109
DIRECTORY	Gives information about files	112
DISABLE	Deactivates capabilities	121
DISCARD	Gives up the tape copy of on-line files	122
DISMOUNT	Gives up access to a structure or tape set	124
EDIT	Creates or edits a file	130
ENABLE	Activates capabilities	137
END-ACCESS	Terminates ownership rights to a directory	139
EOF	Writes an end-of-file mark on a magnetic tape	141
ERUN	Runs a program in an ephemeral fork	143
EXAMINE	Inspects a memory location	145
EXECUTE	Compiles, loads, and starts a program	147
EXPUNGE	Erases deleted files from a directory	155
FDIRECTORY	DIRECTORY command with subcommands	158
FORK	Specifies which fork is current	159
FREEZE	Stops a running fork	162
GET	Places an executable program in memory	164
HELP	Displays information on system programs	166
INFORMATION	Gives information about such items as system, job, and directory parameters	168
KEEP	Protects a fork from being cleared from memory	189
LOAD	Places a program in memory	192
LOGIN	Validates you as a user, creates your job, and begins charging your account	201
LOGOUT	Ends your job	206
MERGE	Merges an executable program with current memory	209
MODIFY	Changes output or batch requests	211

MOUNT	Mounts a structure or tape set	222
PERUSE	Types files on your terminal using an editing program in Read-only mode	238
PLOT	Prints files on a plotter	241
POP	Returns to superior level of TOPS-20	247
PRINT	Prints files on line printer	249
PUNCH	Punches files onto cards or paper tape	257
PUSH	Begins an inferior level of TOPS-20	265
R	Runs a system program	269
RECEIVE	Allows communication with your terminal	271
REENTER	Starts the program in memory at restart address	273
REFUSE	Disallows communication with your terminal	274
REMARK	Treats subsequent input as comment only	277
RENAME	Changes the specification of files	279
RESET	Terminates current process and clears its memory	282
RETRIEVE	Returns off-line files to disk	284
REWIND	Rewinds a magnetic tape set to its load point	289
RUN	Runs an executable program	291
SAVE	Stores copy of memory in a file	293
SEND	Sends messages to terminals	295
SET	Sets various job- and directory-related parameters	298
SET HOST	Connects your terminal to another system	326
SKIP	Moves a magnetic tape or tape set forward	332
START	Starts program in memory at specified address	334
SUBMIT	Submits control files to the batch system	338
SYSTAT	Gives information about system and job status	350
TAKE	Starts processing of a command file	358
TALK	Makes communication links with another user	361
TDIRECTORY	DIRECTORY command with subcommands	365
TERMINAL	Sets various terminal characteristics	366
TRANSLATE	Gives directory names for ppn's and vice versa	379
TYPE	Prints files on your terminal	381

UNATTACH	Disengages another job from its terminal	383
UNDELETE	Restores deleted files	385
UNKEEP	Cancels the kept status of a fork	387
UNLOAD	Unloads a magnetic tape	389
VDIRECTORY	DIRECTORY command with subcommands	391
APPENDIX A	FUNCTIONAL GROUPING OF TOPS-20 COMMANDS	A-1
APPENDIX B	ALPHABETICAL SUMMARY OF TOPS-20 COMMANDS	B-1
APPENDIX C	FILE ATTRIBUTES	C-1
INDEX		Index-1

PREFACE

The TOPS-20 Commands Reference Manual is an alphabetically-arranged description of all operating system commands (EXEC commands) available to the nonprivileged timesharing user of TOPS-20.

In addition, there are two appendixes for quick reference - a list of commands grouped by function, and an alphabetical summary of commands showing what variety of argument each uses and whether it calls a program or otherwise affects memory.

To use the TOPS-20 Commands Reference Manual properly, you should first read and understand Getting Started With TOPS-20 and the TOPS-20 User's Guide. The occasional summary of information you will find here cannot substitute for the more complete presentations offered in those manuals.

INTRODUCTION

COMMANDS AND ARGUMENTS

A complete TOPS-20 command consists of the command name and usually one or more arguments. In the most general sense, arguments are any combinations of letters, numerals, punctuation marks and other characters that you type after the command name itself to complete the meaning of the command. These arguments can be file specifications, switches, subcommands, and values for switches and subcommands, as well as words and numbers (the arguments to the SET and TERMINAL commands, for example). The following pages contain general information about each variety of argument.

File Specifications

Information and programs for TOPS-20 are usually stored in uniquely labeled files. Therefore, file specifications or "filespecs" are the most common variety of argument to a command. A complete file specification is of the form

```
dev:<dir>name.typ.gen;att;...;att
```

where

dev: is a device (usually a file structure)

| <dir> is a directory name (enclosed in angle < > or square []
| brackets)

name is a filename

.typ is a file type

.gen is a generation number

;att is a file attribute

You need file attributes in only a few situations and can usually let dev:, <dir>, and .gen take default values (that is, values defined by the state of your job - see the Special Features section below), so you can give most file specifications in the shortened form, name.typ, without being unclear. In a few cases, an entire file specification is assumed if you do not supply one when you give the command (for the CREATE and EDIT commands, for example, and for LOAD-class commands - COMPILE, LOAD, EXECUTE, and DEBUG).

INTRODUCTION

Whenever you omit the dev: field of the filespec, the system assumes you mean your connected structure (DSK:). This is the public structure (usually named PS:), which all users must log in to, unless you connect to a directory on another structure by using the CONNECT command. Give the INFORMATION STRUCTURE command if you are unsure of the name for your connected structure.

Whenever you omit the <dir> field of the filespec, the system assumes you mean your connected directory. Unless you have given a CONNECT command, this is your "log-in" directory, the directory on the public structure that you must log in to and which usually has a name composed of your surname, or surname and initials, enclosed in angle or square brackets. You change your connected directory by giving a CONNECT command. Use the DIRECTORY command to see the name of your connected directory.

When you omit the .gen field of the filespec the system usually assumes you mean the highest generation (largest generation number) of the file. (A few commands, for example, DELETE, RENAME, and DIRECTORY, act on all generations of a file unless you specify a particular generation.) When you create and edit text files, compile and debug programs, or do anything else to produce another generation of a file, the system automatically works with the highest existing generation and labels the changed file with the next higher generation number. Therefore when you omit the generation number in a filespec given as argument to a TOPS-20 command, you are assured of using the most recent version of the file. Although you can override this default action by specifying particular generations of input and output files, it is simplest and most straightforward to allow the defaults to prevail.

Specification of file attributes is optional. You can assign attributes in order to have a file automatically marked for deletion when you log out; to associate a file with a valid account; and so forth. Appendix C lists the available file attributes.

Pressing the ESC key instead of typing a filespec field will usually cause any default for the remaining fields to be printed on your terminal.

There are two characters (called "wildcard" characters) that you can include in any field of a filespec to include all files matching the rest of the filespec. An asterisk (*) fills in for zero or more characters of a field, while a percent sign (%) fills in for a single character only. (However, only the complete field "DSK:" is allowed as wildcard for the device field, and only the complete field "*" is allowed as wildcard for the generation field.) Therefore you could give the command DIRECTORY *.CBL to find out what source files written in COBOL are in your connected directory, or the command DELETE *.Q* to remove the EDIT program's backup files from your directory.

Switches

Switches are arguments used with LOAD-class (COMPILE, LOAD, EXECUTE, and DEBUG) and EDIT-class (CREATE and EDIT) commands, as well as with Queue-class commands - that is, those affecting entries in processing queues (CANCEL, DISMOUNT, MODIFY, MOUNT, PLOT, PRINT, PUNCH, and SUBMIT).

Switches can also be used with the following program-control commands: DDT, GET, MERGE, R, and RUN. The REWIND command also accepts a switch.

INTRODUCTION

Switches allow you to give quickly many options chosen from a large list, and let you specify to which files they apply when you give more than one filespec in a single command.

Give switches on the same line as the command, typing a slash (/) before each switch. If your command requires more than one line, simply keep typing without giving a carriage return. The system will begin a new line automatically and will read your command as if you had typed it on a single line. Or you may end your command line at any point with a hyphen (-) and carriage return, and continue the command on the next line; the hyphen will not be considered part of your input.

Keep in mind the way each class of command considers switches. EDIT-class commands operate on only one file at a time, and the switches must be given before the input filespec - this is the simplest case.

Queue-class and LOAD-class commands treat switches according to their position in the command line. If you give them before any filespecs, they act as default switches for all filespecs in the command (they will be in effect unless you override them with later switches applying to individual files only). If you give them after the first filespec, they apply only to the preceding file. In addition, there are a few switches of a different sort for the PLOT, PRINT, and PUNCH commands - these apply to all files no matter where they appear in the command line. These are called job switches (because they affect the entire printing job) and are presented in a separate list in those command descriptions.

A switch is a default if the system assumes it in the absence of others. For LOAD-class commands, /FORTRAN is the default for all switches that specify which compiler to use (like /MACRO, /COBOL, and /PASCAL). The /NOCOMPILE switch is the default for /COMPILE, /NOCOMPILE, and /RELOCATABLE. Most defaults for these commands apply to only a pair of switches; however, the /BINARY, /NOSEARCH, and /NOOPTIMIZE switches are assumed, for example, unless you specify /NOBINARY, /SEARCH, and /OPTIMIZE.

Default switches for the other classes of command operate similarly. Some are in effect unless you specify their opposite; others are in effect with a default argument unless you specify another argument; still others must be specified to be in effect, but are supplied with a default argument. The list of switches presented with each command description distinguishes these cases. When you give two or more switches of the same kind (for example, /BINARY and /NOBINARY), the last switch given usually prevails.

Subcommands

Subcommands are a variety of argument used chiefly with DIRECTORY-class (DIRECTORY, FDIRECTORY, TDIRECTORY, and VDIRECTORY) commands and with the BUILD command. If you want to give subcommands to any of the DIRECTORY-class commands, type a comma at the end of the command line just before pressing the carriage return. After the system prompts you with a double at sign (@@) you can give subcommands, one on each line. If you give no subcommands to the DIRECTORY command, the ALPHABETICAL and HEADING subcommands will be in effect, giving an alphabetical listing of files. For a few subcommands, default arguments will be in effect if you give the subcommands without supplying any. You can give subcommands in any order, requesting or declining special categories of information and specifying the format of its presentation. If you give mutually

INTRODUCTION

exclusive subcommands (ALPHABETICAL and CHRONOLOGICAL, for example) the last-given subcommand prevails. Note that the FDIRECTORY, TDIRECTORY, and VDIRECTORY commands are equivalent to the DIRECTORY command with certain subcommands automatically included, and can be further modified with other subcommands from DIRECTORY's list. To cancel a DIRECTORY-class command while giving subcommands, type a CTRL/C.

The BUILD command operates differently from DIRECTORY-class commands in putting you automatically into subcommand mode without your typing a final comma on the command line, and in offering a special subcommand to cancel the command while you are typing subcommands.

See the individual command descriptions for more detailed information about subcommands.

Other Arguments

Some command arguments are not introduced by special characters such as slashes or double at signs, but still are particular words, or "keywords," having a special meaning to the system. Give these on the same line as the command itself, leaving at least one space before and between arguments. Certain of these (for example, the LOGICAL-NAMES argument to the INFORMATION command) are actually composed of more than one word, joined by hyphens so that the system will not interpret them as more than one argument. If the complete command will not all fit onto one line, simply keep typing: the system automatically begins a new line when necessary, but interprets the typing as if it had all appeared on one line. Or you may end a command line at any point with a hyphen (-) and a carriage return, and continue the command on the next line; the hyphen will not be considered part of your input.

A few command arguments must be accompanied by special symbols to be interpreted correctly. Enclose directory names in angle brackets when using them with the CONNECT or names (for DEFINE), device names (used with ASSIGN), and structures and tape sets (used with MOUNT or DISMOUNT) all require a colon at the end. (But note that when supplying what look like structure and tape set names to the related CANCEL command, you are supplying jobnames, and must not include the colon.) If you punctuate a command argument incorrectly, the system will usually print a message reminding you of this.

SPECIAL FEATURES

Defaults

The concept of "defaults," or command arguments assumed when you do not specify a choice, is important for understanding TOPS-20. To speed processing of commands and to help inexperienced users, the system uses defaults when necessary for completing commands that you give. By taking advantage of this defaulting action, you can make the system work faster and more efficiently for you. This manual displays prominently the available choices of command arguments and the established defaults for these.

There are different kinds of default. When you give file specifications as arguments to, say, the PRINT command, the system assumes that you are referring to the highest (most recent) generation of these files in your connected structure and connected directory. By specifying a different structure, directory, or generation you can override this default, but only if you already have the right

INTRODUCTION

(established by user membership in a group, perhaps, or by a prior ACCESS command) to do so.

When you give the INFORMATION BATCH-REQUESTS command without further arguments, you are presented with a listing of all requests in the batch input queue. The /USER switch allows you to limit this display to the jobs of the user named. If you give the switch without supplying a user name, your own user name is used as default. (But the /USER switch to the related SUBMIT command has meaning for privileged users only, who can use it to run batch jobs under other user names; for non-privileged users this switch effectively defaults to your own user name.) Only a few command arguments behave like the /USER switch. The /TIME switch to the SUBMIT command is worth noting: by not giving the switch, you set a time limit of 5 minutes; by giving the switch without specifying a time limit, you are setting a 1-hour limit; and you can set any other time limit by supplying it as argument to the switch.

Note that none of the three switches to INFORMATION BATCH-REQUESTS and INFORMATION OUTPUT-REQUESTS (/ALL, /FAST, and /USER) is used as a default: each calls for a listing that differs in some respects from that yielded by the unmodified command. However, the INFORMATION LOGICAL-NAMES command, which allows keywords ALL, JOB, and SYSTEM, has JOB as default for these. The list of arguments associated with each command makes these choices clear.

To discover what default argument (if any) is established for a switch, subcommand, or other argument, press the ESC key instead of giving the argument: the default will be printed on your terminal.

"Recognition" input is another feature of the TOPS-20 operating system that speeds up your input, by finishing the typing of a command or command argument for you when you have given only part of it and then prompting your next response.

As soon as you have typed enough of a command or argument to distinguish it from others, press the ESC key: the system will finish the word, if possible, and prompt your next input with guidewords enclosed in parentheses. (Note that this manual does not show guidewords except in the Format section of each command description.) By pressing the ESC key without beginning an argument you make the system print the default argument, if there is one. If the system cannot help you, either because you have not typed enough characters to make your intentions clear or because there is no default, your terminal makes a warning noise - either a ringing bell or high-pitched beep.

Because the ESC key does not produce a printed character, you may be unable to remember exactly where you pressed it when later examining the output from a hard-copy terminal. If you want to avoid this possibility, use the TERMINAL NO RAISE command to make your terminal produce lowercase input, to distinguish it from the uppercase printing of the system.

You cannot use recognition for device names (including file structures), jobnames (for example, with the MODIFY or CANCEL command) or logical names.

Abbreviation

By abbreviating commands and command arguments, you can further increase the speed with which you give instructions to TOPS-20. The smallest unique abbreviation for a command or argument will stand for

INTRODUCTION

the entire word; if there is a default choice for further arguments, the system will assume you want this too. (You can determine sufficient abbreviations by using the ESC key: any correctly recognized abbreviation will stand for the word.) For example, the abbreviated command FD stands for the FDIRECTORY command; I L stands for INFORMATION LOGICAL-NAMES JOB.

There are a few cases where non-unique abbreviations stand for a frequently used command. For example, DIS is the abbreviation for DISABLE even though two other commands begin with the letters DIS - DISCARD and DISMOUNT.

Special Abbreviation	Command
C	CONTINUE
D	DEPOSIT
DIS	DISABLE
E	EXAMINE
EX	EXECUTE
INFORMATION F	INFORMATION FILE-STATUS
LOG (When not logged in)	LOGIN
LOG (When logged in)	LOGOUT

You cannot use abbreviation (or recognition) in a few cases. The names of devices (including file structures), and jobnames (given, for example, as arguments to the MODIFY or CANCEL command) must be typed in full; and of course passwords cannot be abbreviated or recognized.

Question Marks

Whenever you type a question mark (?) instead of (or even in the middle of) a TOPS-20 command or command argument, the system responds with instructions or a list of possible completions. By using question marks and recognition when you are unsure of the proper command or argument, you can have the system help you during your terminal session.

These features, together with the HELP command, which provides information on various system programs, are valuable supplements to the written documentation for TOPS-20.

INTRODUCTION

DATE-TIME ARGUMENTS

You can specify date and time arguments to many of the TOPS-20 commands. The following sections describe the formats for these arguments.

Date

The examples below show the various formats that are acceptable for the date argument:

Jun 30 1981	30 Jun 1981
May 1, 82	1/May/1982
January 000005 75	0005-January-000075
F/13-83	5/17/83

If the month and day are both numeric, the first number of the two, if less than 13, is considered to be the month. Otherwise, the second number is considered to be the month. For example:

2/15/83	is February 15th
15/2/83	is February 15th

You can abbreviate the month to as few characters as possible without causing it to be confused with another month. Thus,

O
Jun
Jul
Ja

are acceptable abbreviations for October, June, July, and January.

Many commands allow you to give the day of the week or "today" for the date.

If you specify the time along with the date, you must separate the two arguments by at least one space and/or no more than one tab.

For the time argument you can specify:

- time according to a 24-hour clock:

/AFTER:17:00:00

- AM and PM:

@SET ALERT 5:00PM

INTRODUCTION

- the following time zones:

Arguments	Zone	Hour Offset from Greenwich
GST, GDT, GMT	Greenwich	0
AST, ADT	Atlantic	4
EST, EDT	Eastern	5
CST, CDT	Central	6
MST, MDT	Mountain	7
PST, PDT	Pacific	8
YST, YDT	Yukon	9
HST, HDT	Hawaii/Alaska	10
BST, BDT	Bering	11
DAYLIGHT	Daylight time for your zone	
STANDARD	Standard time for your zone	

Examples

```
6:00PM-EDT      is 5:00PM EST
6:00PM-PST      is 9:00PM EST
6:00PM-GMT      is 1:00PM EST
```

Note that a hyphen (-) is required before the zone.

The basic time format is:

hh:mm:ss

where:

```
hh      is hours, must be less than 24, and is optional
mm      is minutes, must be less than 60, and is required
ss      is seconds, must be less than 60, and is optional
```

The colon between hours and minutes is optional.

Examples (based on a 24-hour clock):

```
3        is 00:03:00AM
125      is 1:25AM
14:30    is 2:30PM
25:33    is 00:25:33AM
```

Relative Date-Time Arguments

Many commands accept relative dates and times. You can specify that an event is to occur at a certain amount of time from the current time, from today, or from a certain day of the week. Likewise, you can specify relative times in the past.

Examples

```
@SET ALERT +30      sets an alert for 30 minutes from now

@DIRECTORY,         produces a listing of files that
@@BEFORE TODAY      were created before today's date
```

INTRODUCTION

EXEC MESSAGES

The TOPS-20 Command Processor, or EXEC, displays messages in response to errors or other conditions that arise when using the TOPS-20 Command Language. There are three kinds of EXEC messages: error, warning, and information.

Error messages begin with a question mark (?). An error message indicates that a failure has occurred and execution of the command or program has stopped. If, for example, you type the wrong password in a LOGIN or CONNECT command, you receive the message ?Incorrect password, and the command is not executed.

Warning messages begin with percent sign (%). A warning message also indicates that a failure has occurred, but execution of the command or program usually continues. For example, suppose you type the command DIRECTORY *.PAS, *.REL to list all the files with the extensions .PAS and .REL, and, your connected directory does not contain any .REL files. The EXEC lists all the files with the .PAS extensions and then prints the warning message, %No such file type *.REL.

The third type of message you can get from the EXEC (and sometimes from the system) is an information message. Information messages are enclosed in square brackets [] and inform you about the status of the system or the result of an EXEC command. For example, the message [DECSYSTEM-20 continued] indicates that a temporary pause in service has ended. The message [n pages freed] indicates that your EXPUNGE command freed n disk pages. Usually information messages require no response from you.

When you need more information than is provided by an EXEC message, refer to the EXEC Message Manual. This manual contains detailed descriptions of all EXEC messages, plus actions to take for correcting errors.

NEW AND CHANGED FEATURES

The TOPS-20 has been enhanced considerably for TOPS-20 Version 6.1. The following is a list of new commands, and new arguments, subcommands and switches to previously existing commands. Changes affecting the command are shown as bulleted items.

New commands and arguments related to the multiforking feature are listed separately.

New Commands (excluding multiforking-related commands)

- ERUN
- PERUSE
- SEND
- SET HOST (considered separate from the SET command)

ACCESS

Obtains ownership rights to a directory and the group rights of its user-group list.

Format

```
@ACCESS (TO DIRECTORY) dev:<directory>  
Password:password
```

where

dev:<directory> is the directory that you want to access
 Default dev: - your connected structure

 Default <directory> - the directory (on
 the specified
 structure) of the
 same name as your
 connected
 directory

password is the password of the directory (not
 requested for your log-in directory or a
 directory of the same name as your log-in
 directory on a domestic structure)

Characteristics

Capabilities

Your capabilities (such as Wheel, Operator, Confidential) are associated with your log-in user name only. If you give the ACCESS command for a directory whose owner has Wheel capabilities, say, you do not gain these capabilities.

Restrictions

One Directory Per Structure

You can access only one directory at a time on each mounted structure. Each ACCESS command ends any previous ACCESS command (including the implicit access obtained by the LOGIN command) for that structure. If you access another directory on the public structure you give up your own group rights on the public structure. These are restored when you give an ACCESS command for your log-in directory.

Not For Files-only Directories

Because a files-only directory does not have an owner or user group rights, you cannot give an ACCESS command for it. Use CONNECT instead.

INTRODUCTION

Changes to Commands and New Arguments, Subcommands, and Switches

BUILD

PRESERVE
TOPS10-PROJECT-PROGRAMMER-NUMBER n,n
PERMANENT
INFINITY
WORKING
INFINITY

- Square brackets legal for directory names
- Forty directory group numbers allowed in a directory

PUSH

- Refers to EXEC defined by DEFAULT-EXEC:
- Runs SYSTEM:COMAND.COMD

CANCEL

* (wildcard)

COPY,

SUPERSEDE

DEFINE

- File recognition in the logical name definition

LOAD-class commands (COMPILE, DEBUG, EXECUTE, and LOAD)

/10-BLISS
/36-BLISS
/ABORT
/[NO]CROSS-REFERENCE (same as [NO]CREF)
/FAIL
/[NO]FLAG-NON-STANDARD,
/MAC new special abbreviation for /MACRO
/[NO]MACHINE-CODE
/NOSTAY
/PASCAL
/SAIL
/SIMULA
/SNOBOL
/[NO]WARNINGS

- Default switches no longer passed to the compiler. It is assumed that the compiler's defaults are the same as the LOAD-class commands.

DDT and MERGE

/OVERLAY

DIRECTORY,

COMPLETE

INTRODUCTION

INFORMATION

CLUSTER
SUPERIOR

INFORMATION ARPANET

- Displays several new fields

INFORMATION DECNET

node-name

INFORMATION DEFAULTS

PROGRAM

INFORMATION DIRECTORY

- Password not displayed
- Displays TOPS-10 project-programmer number
- Displays INFINITY argument to PERMANENT and WORKING parameters

INFORMATION JOB

- Displays name of host node

INFORMATION LOGICAL-NAME logical-name

- Accepts wildcards in logical names

INFORMATION MAIL

SYSTEM

INFORMATION SYSTEM

- Indicates whether DECnet terminals allowed to log in
- Indicates whether operator messages are sent to the console terminal
- Indicates whether level zero and one messages are sent to all users

VERSION

- Displays version numbers in decimal

LOGIN

/FAST

- Runs SYSTEM:LOGIN.CMD and SYSTEM:COMAND.CMD
- Displays date and time of last LOGIN

INTRODUCTION

LOGOUT

/FAST n

- Runs PS:LOGOUT.CMD and SYSTEM:LOGOUT.CMD

RECEIVE and REFUSE

USER-MESSAGES

SET

[NO]STATUS-WATCH
TERMINAL (same as TERMINAL command)

SET [NO] DEFAULT

PROGRAM [NO-]EPHEMERAL

SET FILE

[NO] EPHEMERAL

SET MAIL-WATCH

notification-count

SET [NO] TRAP JSYS

/DEFINED
/UNDEFINED

SUBMIT

- Runs SYS:BATCH.CMD file.

SYSTAT

- Displays job's originating host in "Origin" column

SYSTEM-STATUS

- Indicates whether the sending of level zero and level one messages to all users is enabled

TERMINAL

[NO]INHIBIT
[NO]RECEIVE (same as REFUSE and RECEIVE)
H19
VT102
VT200-SERIES

TYPE,

UNFORMATTED

INTRODUCTION

New Multiforking-class Commands

The most significant addition to the EXEC is the multiforking feature. Commands which accept a fork name or number as an argument or display information about forks are considered multiforking-class commands.

FREEZE
KEEP
UNKEEP

New Multiforking-class Arguments and Switches

CONTINUE

fork-name
fork-number
/BACKGROUND
/NORMALLY (formerly a subcommand)
/STAY (formerly a subcommand)

FORK

fork-name (interchangeable with existing fork-number)

INFORMATION

FORK-STATUS
DEFAULT PROGRAM

INFORMATION PROGRAM-STATUS

- Displays SET PROGRAM and SET DEFAULT PROGRAM settings.

RESET

* (wildcard)
.(period)
fork-name
fork-number

SET

NAME fork-name
PROGRAM KEEP
PROGRAM NONE

SET [NO] DEFAULT

PROGRAM KEEP
PROGRAM NONE

START

/BACKGROUND
/NORMALLY
/STAY

Deleted subcommands and arguments

These components have been removed from the EXEC.

INTRODUCTION

APPEND and COPY

Arguments to the ASCII subcommand: NOPARITY and PARITY.
(NOPARITY was never implemented and PARITY is now the default.)

TAKE

- Second filespec field deleted. Replaced in Release 5 by LOG-FILE subcommand.

General Notes

- A colon after a device name is now optional in these commands:

ASSIGN, BACKSPACE, DEASSIGN, DEFINE, DISMOUNT, EOF,
INFORMATION LOGICAL-NAMES, INFORMATION STRUCTURE, INFORMATION
VOLUMES, MOUNT, REWIND, and SKIP
- On autobaud lines, any character typed on the terminal gets the attention of system.
- In an effort to reduce the number of top level EXEC commands in future releases of TOPS-20, the REFUSE and RECEIVE commands have been placed under the TERMINAL command in the format TERMINAL [NO] RECEIVE. The TERMINAL command has been placed under the SET command.

Commands that were modified in this release, also remain available in their old format. For example the TERMINAL command is available as TERMINAL or SET TERMINAL.

ACCESS (Cont.)

Related Commands

CONNECT	for making a directory your connected directory
END-ACCESS	for surrendering rights to an accessed directory
MOUNT STRUCTURE	for making a structure available for access, and ensuring the continued availability of an accessed structure

Examples

1. Access another user's directory.

```
@ACCESS <HOLLAND>  
Password: _____
```

2. Access another user's directory so you can copy a file from it to your connected directory.

```
@ACCESS <HOLLAND>  
Password: _____  
@COPY <HOLLAND>MAX.MEM HOLMAX.MEM  
      <HOLLAND>MAX.MEM.1 => HOLMAX.MEM.1 [OK]  
@END-ACCESS <HOLLAND>
```

3. Access the login directory of a user whose group rights you want to borrow.

```
@COPY <MANUALS>CHKCRF.MAC CHKCRF.MAC  
?Directory access privileges required - "<MANUALS>CHKCRF.MAC"  
@ACCESS <HOLLAND>  
Password: _____  
@COPY <MANUALS>CHKCRF.MAC CHKCRF.MAC  
      <MANUALS>CHKCRF.MAC.4 => CHKCRF.MAC.1 [OK]  
@END-ACCESS <HOLLAND>
```

ACCESS (Cont.)

4. Access the directory of a user on another structure. Then examine his directory and copy a file from it.

```
@MOUNT STRUCTURE SNARK:
Structure SNARK: Mounted
@ACCESS SNARK:<HOLLAND>
Password:
@DIRECTORY SNARK:<HOLLAND>

    SNARK:<HOLLAND>
    ACCT.MEM.1
    ACTGEN..1
    COMP.FOR.1
    COMPUT.CBL.1
    .REL.1
    DIFFER.FOR.1
    .QOR.1
    MAIL.TXT.2
    OVERVIEW.MEM.1

    Total of 9 files
@COPY SNARK:<HOLLAND>COMP.FOR
    SNARK:<HOLLAND>COMP.FOR.1 => COMP.FOR.1 [OK]
@END-ACCESS SNARK:<HOLLAND>
@DISMOUNT STRUCTURE SNARK:
Structure SNARK: Dismounted
```

ADVISE

Links your terminal with another user's terminal so that you can give commands to his job. The advisee can still give commands to his job.

Format

@ADVISE (USER) argument

where

argument is either a user name or terminal line number.

Characteristics

Input to Other Job

For as long as the ADVISE command is in effect, the commands you give affect the advisee's job instead of your own.

Ending Advice

To end an advising link that you have formed between terminals, you must type CTRL/E. This CTRL/E is not echoed on either terminal.

Refused Advice

Ordinarily, you cannot advise a job unless its terminal is set to receive advice. However, if you have Wheel or Operator capabilities enabled, you can ADVISE any job, providing the user has not given the TERMINAL INHIBIT command.

Special ADVISE Commands

Once you are advising another job, you can give special commands to send comments or control characters, or to relink to a terminal that has broken links with yours. These commands are:

CTRL/E	End an ADVISE link
CTRL/~ +	Restart an ADVISE link after a BREAK command is typed at the advised terminal
CTRL/~ (Start a comment (or use the REMARK command)
CTRL/~)	End a comment (or use the REMARK command)
CTRL/~ ?	Display the list of ADVISE control characters

ADVISE (Cont.)

CTRL/~<CHAR> Send CTRL/CHAR

Note that the tilde character (~) can have different meanings with various terminal models. Consult your terminal's manual for the character equivalent to 36 octal in ASCII code.

Special Cases

Advisee Has More Than One Job

If more than one job is logged in under the user name you specify, the system gives you a list of that user's terminal numbers and associated programs to choose from, then prints TTY: to prompt your response. Type your choice of terminal number after the prompt.

Advising a Pseudoterminal (PTY:)

If you try to advise a PTY: the system informs you of this and asks you to confirm with a carriage return.

Restrictions

Compatible Terminals

Unless the terminals involved in an advising link have compatible characteristics (e.g., terminal width, ability to handle tabs and lowercase letters), some information can be lost or overprinted. To avoid this problem, the user of the faster or more capable terminal should adjust his terminal's characteristics, if possible before the ADVISE command is given.

Detached Jobs

You cannot advise detached jobs.

Warning

Talking Between a VT100 and a VT52

If links between VT100 and VT52 terminals are established using an ADVISE (or TALK) command, the VT52 may function improperly during or after the linked interval (e.g., by requiring frequent CTRL/Q commands to print multiple lines of output). Turning the terminal off and then on again (after the linked interval) will correct this problem.

ADVISE (Cont.)

Effect on Terminal

| The ADVISE command leaves your terminal at the advisee's
terminal's command level, controlling his job.

Related Commands

RECEIVE ADVICE	for allowing other users to advise you
REFUSE ADVICE	for preventing other users from advising you
REMARK	for sending comments only
TALK	for linking terminals so that your commands affect only your own job
TERMINAL INHIBIT	for refusing all types of terminal communication including advice, links, system messages, user messages, and notices of new mail.

Examples

1. Advise a user, then immediately type CTRL/E to end advice.

```
@ADVISE D.CROWLEY
Escape character is <CTRL>E, type <CTRL>^? for help
D.CROWLEY JOB 51 EXEC

LINK FROM LATTA, TTY 226
[Advising]

^E !Not displayed on terminal
[Advice terminated]
```

2. Advise a user's job and access a directory for him.

```
@ADVISE BONSAVAGE
Escape character is <CTRL>E, type <CTRL>^? for help
BONSAVAGE JOB 48 EXEC

LINK FROM LATTA, TTY 226
[Advising]
!I'LL ACCESS THE DIRECTORY FOR YOU, THEN YOU CAN USE IT.
@ACCESS <SARTINI>
Password:
@!OKAY, NOW YOU CAN USE IT.
@!Thank you.
^E
[Advice terminated]
```


ADVISE (Cont.)

3. Advise another user, demonstrating how to use the FILCOM program.

@ADVISE D.CROWLEY

Escape character is <CTRL>E, type <CTRL>^? for help
D.CROWLEY JOB 51 EXEC

LINK FROM LATTA, TTY 226

[Advising]

!HERE'S HOW TO COMPARE FILES USING THE FILCOM PROGRAM.

@FILCOM

*=VERCBL.TXT, BAKVER.TXT/A

No differences encountered

*^C

@!SEE? THE SWITCH AT THE END (/A) MEANS TO COMPARE THEM IN ASCII

@IMODE. DON'T FORGET THE CTRL/C WHEN YOU'RE DONE.

@!THANKS.

^E

--[Advice terminated]

4. Advise a user who is logged in at more than one terminal. Choose one of them.

@ADVISE LATTA

TTY25, EXEC

TTY41, EXEC

TTY27, EXEC

TTY: 27

Escape character is <CTRL>E, type <CTRL>^? for help

LATTA Job 22 EXEC

LINK FROM D.CROWLEY, TTY 225

[Advising]

.

.

.

^E

--[Advice terminated]

APPEND

Adds the contents of one or more source files to the end of a new or existing destination file on disk, leaving the original source files unchanged.

Format

@APPEND (SOURCE FILE) source filespec(s) (TO) destination filespec,
@@subcommand

where

source filespec(s) is a single file specification, or a series of them separated by commas.

destination filespec is the specification of the destination file on disk; this can be a new file.

@@subcommand means that after a final comma you can type an optional keyword, modifying the mode or format of information transfer.

APPEND Command Subcommands (when used with the paper tape reader - PTR:)

- ASCII specifies that the files being appended are written in ASCII mode, with 36-bit words each consisting of five 7-bit bytes and a parity bit; the parity bit means that the eighth hole of the paper tape is never punched.
- |
- BINARY specifies that the files being appended are composed of 36-bit words, each consisting of six 6-bit bytes, with the seventh hole of the paper tape set always to 0 and the eighth hole set always to 1; causes a checksum calculation.
- BYTE n specifies that the byte size of the destination file is to be n (any decimal number). If you do not give the BYTE subcommand, the destination file will have the same byte size as the source file.
- IMAGE specifies that the files being appended are composed of 36-bit words, each consisting of one 8-bit byte; the 28 most significant bits are lost on output.
- IMAGE BINARY same as BINARY, but lacking the checksum

APPEND (Cont.)

APPEND Command Subcommands
(when used with devices other than the paper tape reader)

ASCII	specifies that the files being appended are written in ASCII mode, with 36-bit words each consisting of five 7-bit bytes and a parity bit; the parity bit means that the least significant bit is set to 0 on input and is lost on output.
BINARY	calls for a direct transfer of data in 36-bit bytes
BYTE n	specifies that the byte size of the destination file is to be n (any decimal number). If you do not give the BYTE subcommand, the destination file will have the same byte size as the source file.
IMAGE	same as BINARY
IMAGE BINARY	same as BINARY

Output

As each file is appended, the system prints its specification and the word [OK]. Also, if recognition is used on the destination file specification, the system prints its status (Old generation, New generation, New file, or Superseding, for disk files; or OK, if the files are appended to a non-disk device).

Characteristics

Files Appended in Order Specified

The APPEND command attaches source files to the destination file in the order you specify them; the contents of the last specified source will appear at the end of the destination file when APPEND is finished.

Subcommands Optional

For most purposes you do not need to use subcommands when transferring information with the APPEND command. These subcommands, specifying the format of the appended files, are required only when using certain devices (for example, devices of the form MTn: (tape drives) using labeled tapes, or PTR: (paper tape reader)) or under particular conditions (for example, when transferring files over network facilities). If you are appending information from disk files or from your terminal and you do not use any subcommands, the data will be appended as written, whether in a standard format (usually ASCII or binary) or not.

APPEND (Cont.)

Special Cases

Wildcard Characters

Wildcard characters (* and %) can be used in source file specifications only. The files are then appended in alphabetical order.

Appending Information from your Terminal

If you type TTY: in place of source file specifications, the system appends any characters you then type (after completing the command itself), until you give a CTRL/Z to return your terminal to TOPS-20 command level. CTRL/U, CTRL/R, CTRL/W, and the Delete key can be used to edit the current line of terminal input.

Restrictions

Source Files With Differing Formats

You can use the APPEND command to transfer data from a magnetic tape, terminal, card reader, paper tape reader, or other device to disk files, but if source files written in differing formats are specified within the same command, some data can be lost in the transfer.

Mixing Sequenced and Unsequenced Files

Source files created by the EDIT program should not contain sequence numbers when they are appended. Mixing files that contain sequence numbers with files that do not will cause EDIT to function improperly if used on the resulting file.

Appending to Archived Files

You can append the contents of an archived file to another file, by specifying it as the first (or source) argument of an APPEND command. You can then edit the resulting file, because it does not gain archive status although part of its contents are the same as those of the archived file; the archived file remains unchanged. However, you cannot give the specification of an archived file as the second (or destination) argument of an APPEND command, as this would change the file's contents.

Related Commands

COPY for making copies of files

APPEND (Cont.)

Examples

1. Use the APPEND command to join two files.

```
@APPEND FORT.FOR FIL.FOR  
FORT.FOR.8 [OK]
```

2. Append two files to the end of a third file.

```
@APPEND FORT.FOR, GORT.FOR GIL.FOR  
FORT.FOR.8 [OK]  
GORT.FOR.6 [OK]
```

3. Access a directory and append a file from it to a file in your connected directory.

```
@ACCESS <MANUALS>  
Password:  
@APPEND <MANUALS>REL3A.MEM REL3A.MEM  
<MANUALS>REL3A.MEM.4 [OK]  
@END-ACCESS <MANUALS>
```

4. Use a wildcard character (%) to append several files to the end of another file.

```
@APPEND %ORT.FOR HIL.FOR  
FORT.FOR.8 [OK]  
GORT.FOR.6 [OK]  
HORT.FOR.3 [OK]  
MORT.FOR.2 [OK]
```

5. Use a wildcard character with the APPEND command to create a new file.

```
@APPEND *.TXT BACKUP.TXT  
MAIL.TXT.1 [OK]  
NEWRUN.TXT.1 [OK]  
NX.TXT.1 [OK]
```

6. Append a message from your terminal to the beginning of the file created in Example 5. Use the symbolic generation number -1 to specify this action.

```
@APPEND TTY: ,BACKUP.TXT BACKUP.TXT.-1  
TTY:  
  
!THIS IS A BACKUP FILE FOR ALL TEXT FILES.  
^Z  
  
BACKUP.TXT.1 [OK]
```

ARCHIVE

Asks that a permanent off-line copy of specified files be made on magnetic tape, and prevents the disk copy (if retained) from being modified.

Format

```
@ARCHIVE (FILES) filespec,...,  
@@subcommand
```

where

filespec is the specification of a file of which you want a permanent copy

,... means that, after commas, you can give more arguments of the form already shown

@@subcommand means that after a final comma you can type the following optional subcommand:

RETAIN which causes the disk copies of the files being archived to be retained in your directory, rather than deleted and expunged

Output

Notice of Archive Sent to Requestor

Whenever a file is taken off line as a result of your ARCHIVE command (for example, when you do not also give the RETAIN subcommand), the operator sends a mail message notifying you that the file has been archived.

Characteristics

Archived Files Unalterable

You cannot change the contents of files specified in an ARCHIVE command once the command is given, even if the files are not immediately copied to tape. This means that you cannot alter or add to them by using the EDIT or APPEND command, or overwrite them by using the COPY or RENAME command. In general, files for which you have requested archival must not be given as the second filespec argument of these commands.

ARCHIVE (Cont.)

Archived Files Invisible

The files you specify in an ARCHIVE command ordinarily become invisible to most TOPS-20 commands as soon as the ARCHIVE command is given. However, if you include the RETAIN subcommand when giving the ARCHIVE command, the files remain visible. See Related Commands, below, for a list of commands you can use with invisible files.

Related Commands

CANCEL ARCHIVE	for canceling archival requests
DELETE, with the ARCHIVE subcommand	for deleting archived files
with the CONTENTS-ONLY subcommand	for deleting only the disk copy of files that also have a tape copy
DIRECTORY, with the ARCHIVE subcommand	for requesting information on archived files (visible and invisible) only
DIRECTORY, with the INVISIBLE subcommand	for requesting information on invisible files only
DISCARD	for giving up the tape copy of on-line files
INFORMATION ARCHIVE-STATUS	for determining if archival for the specified files (visible and invisible) has been accomplished
RETRIEVE	for restoring off-line files (visible and invisible) to on-line status
SET FILE INVISIBLE	for making visible files invisible
SET FILE VISIBLE	for making invisible files visible

ARCHIVE (Cont.)

Examples

1. Archive a file.

```
@ARCHIVE ARTEST.FIL  
  ARTEST.FIL.1 [Requested]
```

2. Archive a file, but keep a copy on disk. Check the archive status of files.

```
@ARCHIVE ARCHEK.FIL,  
@RETAIN  
@  
  ARCHEK.FIL.1 [Requested]  
@INFORMATION ARCHIVE-STATUS  
  ARCHEK.FIL.1 Archive requested, Retain contents  
  ARTEST.FIL.1 Archive requested
```

3. Attempt to use the EDIT editor to edit an archived file (first you must make it visible). Note that, afterwards, the unedited backup copy is the archived file, and that the edited file has no archive status.

```
@INFORMATION ARCHIVE-STATUS ARTEST.FIL  
  ARTEST.FIL.1 Archive requested  
@EDIT ARTEST.FIL
```

```
%No such filename, Creating New file  
Input: ARTEST.FIL.2
```

```
00100  $  
*EQ  
@SET FILE VISIBLE ARTEST.FIL  
  ARTEST.FIL.1 [OK]  
@EDIT ARTEST.FIL  
Edit: ARTEST.FIL.1  
*P  
00100  !TEST FILE FOR ARCHIVING  
*I200  
00200  !FIRST MODIFICATION  
00300  $  
*P^:*  
00100  !TEST FILE FOR ARCHIVING  
00200  !FIRST MODIFICATION  
*EU
```

```
[ARTEST.FIL.2]  
@INFORMATION ARCHIVE-STATUS ARTEST.*  
  ARTEST.QIL.1 Archive requested  
@TYPE ARTEST.QIL  
  !TEST FILE FOR ARCHIVING  
@TYPE ARTEST.FIL  
  !TEST FILE FOR ARCHIVING  
  !FIRST MODIFICATION  
@DIRECTORY ARTEST.*
```

```
MISC:<LATTA>  
ARTEST.FIL.2  
  .QIL.1
```

```
Total of 2 files
```


ASSIGN

Reserves a specific input-output device for your job.

Format

@ASSIGN (DEVICE) dev:

where

| dev: is the name of the device you want to assign. The
| colon after the device name is optional.

Restrictions

Assigning Magnetic Tape Drives

You can use the ASSIGN command to assign tape drives only if they are of the form MTn:. Tape device names of the form MTn: are logical device names only, and are assigned automatically at the time of MOUNT TAPE commands.

Related Commands

DEASSIGN	for releasing a previously assigned device
MOUNT	for mounting a structure or magnetic tape set without assigning a specific drive
INFORMATION AVAILABLE DEVICES	for finding out which devices can be assigned or have been assigned to your job

Examples

1. Assign a tape drive to your job.

@ASSIGN MTA0:

2. Find out which devices are available for timesharing use, then assign one to your job.

@INFORMATION AVAILABLE DEVICES

Devices available to this job:

DSK, PS, SNARK, MISC, LANG, MTA1, LPT, LPT0, LPT1
CDR, PCDR0, CDP FE1-15, PTY20-61, NUL, PLT, PLT0
DCN, SRV

Devices assigned to/opened by this job: TTY41

@ASSIGN PCDR0:

ATTACH

Attaches a job to your terminal.

Format

```
@ATTACH (USER) name (JOB #) number  
PASSWORD: password
```

where

name is the user name of the job's owner

number is the job number
Default the only job, or only detached job, or only job other than your current job, logged in under the user name you give

password is the associated password (not requested if you are currently logged in under the same user name as the job that you are attaching)

Characteristics

Current Job Detached

If you give the ATTACH command while logged in, your current job is detached. You can use the LOGOUT n command to log out this detached job.

Hint

Using ATTACH to Restore Phoned-in Jobs

If you log in to the system by telephone lines and service is interrupted for any reason, use the ATTACH command to restore the connection. If you do not do this within the time limit set by the system manager (usually five minutes), your job will be logged out automatically and you will have to log in again.

ATTACH (Cont.)

Warning

Attaching Attached Jobs

The system will ask you to confirm your choice with a carriage return before attaching to your terminal a job that is attached elsewhere. If you attach an attached job that is running a program, that program may be sent one or more CTRL/Cs, which can affect programs that handle CTRL/C themselves. To avoid this possibility you must give a DETACH command from the terminal to which the program's job is attached, then attach this job to your terminal with an ATTACH command.

Effect on Memory, Terminal, and Job

The ATTACH command affects neither memory nor the job that you are attaching (but see Warning, above), and leaves your terminal at TOPS-20 command level unless a program is being run by the job. If a program is being run, your terminal is left at command level, if any, in the job. Your terminal's characteristics will be those established in the job from which you gave the ATTACH command; if you were not logged in, they will be reset to system default characteristics.

Related Commands

SYSTAT	for finding out the user name and job number associated with any job
DETACH	for disengaging a job from your own terminal
UNATTACH	for disengaging a job from any other terminal

Examples

1. Attach your only job, which is presently detached.

```
@ATTACH LATTA
Password:_____
```

2. Attach one of several detached jobs.

```
@ATTACH LATTA
?Job # required - LATTA has more than one detached job
@SYSTAT LATTA
  37  DET  EXEC    LATTA
  54  DET  NRRY    LATTA
@ATTACH LATTA 37
Password:_____
```

ATTACH (Cont.)

3. Check your jobs (your current job is marked with an asterisk [*]), then attach the only detached job. Verify the system's action.

```
@SYSTAT LATTA
 37      26 NEWRUN  LATTA
 58      DET EXEC   LATTA
 59*    231 EXEC    LATTA
@ATTACH LATTA
Detaching job # 59
@INFORMATION JOB-STATUS
Host AURORA
Job 58, User LATTA, PS:<LATTA>, TTY231
Account 341
```

4. Start a program in one job. Then detach and continue it, and attach another of your jobs.

```
@INFORMATION JOB-STATUS
Host AURORA
Job 9, User LATTA, PS:<LATTA>,
Account 341 TTY26
@RUN FFACTOR

^C
@DETACH CONTINUE
Detaching job # 9
^C !Not displayed on terminal
TEDDY, Controller Dept. TOPS-20 Monitor 6.1(7)
@SYSTAT LATTA
 9      DET FFACTO  LATTA
45*     41 SYSTAT   LATTA
@ATTACH LATTA 45
[Attached to TTY41, confirm]
Password:_____
```

BACKSPACE

Moves a magnetic tape set backward over a specified number of files or records.

Format

@BACKSPACE (DEVICE) dev: n units

where

dev: is the name of the tape set or magnetic tape drive that you want to move backward. The colon after the device name is optional.

n is the number of files or records over which you want to backspace
Default n - 1

units is either FILES or RECORDS
Default units - FILES

Restrictions

BACKSPACE with Open Files

If you have given a CTRL/C to exit from a program that has opened a magnetic tape drive and you then give the BACKSPACE command for that tape drive, the system will first ask if you want to close the associated file. You must do so for BACKSPACE to succeed, but you will probably be unable to continue the program from that point because the file will now be closed.

RECORDS Argument Used for Unlabeled Tapes Only

You cannot give the RECORDS argument to the BACKSPACE command when using a labeled tape, because read and write operations for labeled tapes always move the tape to the beginning of a file first.

BACKSPACE (Cont.)

Related Commands

SKIP	for moving a magnetic tape set forward
REWIND	for backspacing a tape volume or tape set to its logical beginning (the beginning of the first file)
UNLOAD	for completely rewinding a magnetic tape onto the source reel

Examples

1. Backspace your magnetic tape one file.

@BACKSPACE MTA0: 1 FILE

BLANK

Clears your video terminal screen.

Format

@BLANK (SCREEN)

Characteristics

This command moves the cursor to line 1 of the screen, providing you with a clean area for typing commands and receiving system output.

Restriction

The BLANK command functions only if you have set your terminal type with the TERMINAL command or the unsupported TTYINI program.

BREAK

Breaks the communication link made between terminals with the TALK command.

Format

`@BREAK (LINKS WITH) argument`

where

argument is a user name or line number.
Default - all communication links

Restrictions

Does Not End Advice

The BREAK command, given at either of two terminals joined by the ADVISE command, does not end advice. To end an ADVISE link, type CTRL/E.

Related Commands

TALK	for establishing communication links with another terminal
REFUSE LINKS	for preventing future communication links with your terminal

Examples

1. Use the BREAK command to end a TALK session with another user.

@BREAK

2. Use the TALK command to speak to another user, then use BREAK to end the conversation.

@TALK PORADA

LINK FROM LATTA, TTY 41

@!HI. CAN YOU TELL ME WHERE THE PROJECT ESTIMATES ARE STORED?

@!SURE: THEY'RE ON TAPE LS2.0 IN THE LIBRARY.

@!THANKS. BYE

@BREAK

BUILD

Creates, modifies, or deletes a subdirectory to a directory to which you have write access.

Format

@BUILD (DIRECTORY NAME) **str:**<directory>
@@subcommand

where

str: is the name of the (mounted) structure containing the directory you are building.

directory is the name of the directory you are building. The directory name can contain 39 or fewer alphanumeric characters, including the following special characters: **-** and **\$**. The name must be enclosed in angle brackets **<>** or square brackets **[]**.

@@subcommand indicates that you automatically enter subcommand mode after completing the BUILD command line

Summary of BUILD Command Subcommands (defaults in boldface)

ABORT

ABSOLUTE-ARPANET-SOCKETS

ACCOUNT-DEFAULT account

ARCHIVE-ONLINE-EXPIRED-FILES

ARPANET-ACCESS

ARPANET-WIZARD

CONFIDENTIAL

DECNET-ACCESS

DEFAULT-FILE-PROTECTION octal protection code Default n - 777700

DIRECTORY-GROUP group number

DISABLE

ENABLE

ENQ-DEQ

FILES-ONLY

GENERATIONS n Default n - 1

IPCF

KILL

LIST [NAME-ONLY
FAST
 VERBOSE
 MAINTENANCE

MAXIMUM-SUBDIRECTORIES n Default n - 0

NOT [ABSOLUTE-ARPANET-SOCKETS
 ARCHIVE-ONLINE-EXPIRED-FILES
 ARPANET-ACCESS
 ARPANET-WIZARD
 CONFIDENTIAL

BUILD (Cont.)

NOT (Cont.)	[<ul style="list-style-type: none"> DECNET-ACCESS DIRECTORY-GROUP group number ENQ-DEQ FILES-ONLY IPCF KILL MAINTENANCE OPERATOR REPEAT-LOGIN-MESSAGES SUBDIRECTORY-USER-GROUP group number USER-OF-GROUP group number WHEEL]	
	NUMBER octal directory number	
	OFFLINE-EXPIRATION-DEFAULT date or +n	Default n - 90
	ONLINE-EXPIRATION-DEFAULT date or +n	Default n - 60
	OPERATOR	
	PASSWORD 1- to 39-character word	
	PERMANENT [<ul style="list-style-type: none"> pages INFINITY 	Default n - 250
	PRESERVE	
	PROTECTION octal protection code	Default n - 777700
	PUSH	
	REPEAT-LOGIN-MESSAGES	
	SUBDIRECTORY-USER-GROUP group number	
	TOPS10-PROJECT-PROGRAMMER-NUMBER n,n	
	USER-OF-GROUP group number	
	WHEEL	
	WORKING [<ul style="list-style-type: none"> pages INFINITY 	Default n - 250

BUILD Command Subcommands

ABORT cancels all work done during current BUILD command. If directory was new, it does not exist; if old, it remains unchanged.

ABSOLUTE-ARPANET-SOCKETS allows the directory owner to establish ARPANET network connections using 32-bit absolute socket numbers; users with Wheel or Operator capabilities can also perform this function. For use only with systems that are members of the ARPA network. See the TOPS-20AN User's Guide for more information. Requires WHEEL or OPERATOR capabilities.

ACCOUNT-DEFAULT account causes the specified account to be charged for a terminal session whenever the user does not include an account in his LOGIN command.

BUILD (Cont.)

ARCHIVE-ONLINE-EXPIRED-FILES	causes on-line files that have expired to be marked for archiving.
ARPANET-ACCESS	allows the directory owner to establish ARPANET network connections. This subcommand works in conjunction with pre-established system manager controls. Requires WHEEL or OPERATOR capabilities.
ARPANET-WIZARD	allows the directory owner to use special queues for sending and receiving information on the ARPANET network. For use only with systems that are members of the ARPA network. See the <u>TOPS-20AN User's Guide</u> for more information. Requires WHEEL or OPERATOR capabilities.
CONFIDENTIAL	grants the directory owner confidential information access capabilities, allowing him to obtain confidential information within the system via certain monitor calls. See the <u>TOPS-20 Monitor Calls Reference Manual</u> for details. Requires WHEEL or OPERATOR capabilities.
DECNET-ACCESS	allows the directory owner to establish DECNET network connections. This subcommand works in conjunction with pre-established system manager controls. Requires WHEEL or OPERATOR capabilities.
DEFAULT-FILE-PROTECTION	octal protection code assigns this number as default for the protection code of each file subsequently placed in the directory.

The protection code is constructed (by addition) from the octal values shown below:

77	full access to the file
40	read the file
20	write and delete the file
10	execute the program contained in the file
04	append to the file
02	list the files specification using DIRECTORY-class commands
00	no access to the file
Default code - 777700	

See the TOPS-20 User's Guide for more information about protection codes.

BUILD (Cont.)

DIRECTORY-GROUP group number

places the directory in a group, thereby allowing users in the same group access to it according to the middle two digits of the protection code, and access to files in the directory according to the middle two digits of each file's protection code. You can assign up to 40 directory group numbers to each directory, with values ranging from 1 through 262143 ($2^{18} - 1$). See the TOPS-20 System Manager's Guide for a discussion of groups.

DISABLE

suspends any special capabilities that you may have activated with the ENABLE subcommand or the ENABLE TOPS-20 command.

ENABLE

allows you to activate any privileged capabilities that the system manager has given you and that you may need during the BUILD session.

ENQ-DEQ

grants the directory owner the ability to perform global Enqueue and Dequeue functions; these are discussed in the TOPS-20 Monitor Calls Reference Manual. Requires WHEEL or OPERATOR capabilities.

FILES-ONLY

declares the directory to be a files-only directory, i.e., one not associated with a user. See Restrictions - Files-only Directories, below.

GENERATIONS n

specifies a default for the number of successive generations of files to be retained in the directory. This number must be from 0 to 15, with 0 meaning an infinite number.

Default n - 1

IPCF

allows the directory owner to execute all privileged IPCF functions; these are discussed in the TOPS-20 Monitor Calls Reference Manual. Requires WHEEL or OPERATOR capabilities.

KILL

eliminates the directory and any files it contains from the system; you must confirm this subcommand with an extra RETURN.

BUILD (Cont.)

LIST [NAME-ONLY
FAST
VERBOSE

provides a listing at your terminal of parameter values set for the directory by TOPS-20 commands, BUILD subcommands, or by default. The FAST listing always includes the subdirectory's name, working and permanent storage limits, and, if they have been set, directory number, account default, maximum number of subdirectories allowed to this directory, the date and time of last log-in, group memberships, and user group numbers assignable by this directory. The VERBOSE listing adds the other values that can be assigned by BUILD subcommands, while NAME-ONLY restricts output to the directory name.

Default - FAST

MAINTENANCE

allows the directory owner to execute certain system maintenance functions or monitor calls; discussed in the TOPS-20 Monitor Calls Reference Manual. Requires WHEEL or OPERATOR capabilities.

MAXIMUM-SUBDIRECTORIES n

allows the owner of this directory to build up to n subdirectories of his own, and subtracts an equal number from the value of this parameter for the superior directory

NOT

ABSOLUTE-ARPANET-SOCKETS
ARCHIVE-ONLINE-EXPIRED-FILES
ARPANET-ACCESS
ARPANET-WIZARD
CONFIDENTIAL
DECNET-ACCESS
DIRECTORY-GROUP group number
ENQ-DEQ
FILES-ONLY
IPCF
KILL
MAINTENANCE
OPERATOR
REPEAT-LOGIN-MESSAGES
SUBDIRECTORY-USER-GROUP group number
USER-OF-GROUP group number
WHEEL

withdraws the specified subcommand

BUILD (Cont.)

NUMBER octal directory number

assigns a specific directory number to a new directory (note: usually the default is adequate). Directory numbers 1 through 17 must never be assigned by users, as they are reserved for system use.

Default directory number - assigned by system

OFFLINE-EXPIRATION-DEFAULT date or +n

establishes the tape expiration date for files that are to go off line because of migration or archiving. If you specify "+n", the expiration date will be n days from the date the files are moved off line.

The default date cannot exceed the system maximum. Check the system maximum with the command INFORMATION (ABOUT) SYSTEM-STATUS.

ONLINE-EXPIRATION-DEFAULT date or +n

establishes the disk expiration date for files that are to be created in the directory. If you specify "+n", the expiration date will be n days from the creation date.

OPERATOR

grants Operator capabilities to the owner of the directory; these are discussed further in the TOPS-20 Operator's Guide. Requires WHEEL or OPERATOR capabilities.

PASSWORD 1- to 39-character word

assigns a password, consisting of alphanumeric characters and hyphens (-), to the directory. You can include any special characters except @ ; ! and ? in a password by typing CTRL/V before each special character. Unlike special characters in file specifications, CTRL/V is required only when creating the password, not when using it.

BUILD (Cont.)

PERMANENT [pages
INFINITY

allocates permanent disk storage capacity (in pages) to the directory, and subtracts an equal number from the permanent disk storage capacity of the superior directory. INFINITY allows users with Wheel or Operator capabilities to allocate an unlimited number of pages to the directory. The permanent disk storage of the superior directory must also be INFINITY. The number of pages that can be used is limited to the number of free pages on the structure.

The INFINITY argument is intended for special system directories; it is not intended for general users.

Default pages - 250

PRESERVE

preserves the values of the superior directory's PERMANENT, WORKING and MAXIMUM-SUBDIRECTORIES parameters. PRESERVE stops the PERMANENT, WORKING, and MAXIMUM-SUBDIRECTORIES subcommands from subtracting the values from the quotas in the superior directory. Requires WHEEL or OPERATOR capabilities.

PROTECTION octal protection code

assigns the given directory protection code to the directory. The protection code is constructed (by addition) from the octal values shown below:

- 77 full access to the directory
 - 40 access to files in the directory (including expunging individual files), consistent with the file protection of the files
 - 10 connect to the directory without giving a password, undelete files, expunge the entire directory, and change times, dates, and accounting information for files. All other access is governed by the file protection of each file.
 - 04 create files in the directory
 - 00 no access to the directory
- Default code - 777700

See the TOPS-20 User's Guide for more information about protection codes.

BUILD (Cont.)

PUSH	creates an EXEC level inferior to the one from which you issued the BUILD command and leaves your terminal at this new level. You can then issue TOPS-20 commands to create conditions or obtain information that you may need during the BUILD session. Give the POP command to return to BUILD. See Example 6.
	This subcommand refers to the EXEC defined by the logical name DEFAULT-EXEC:. You can use the DEFINE command to define the job logical name, DEFAULT-EXEC:, with the name of the EXEC you want to create each time you PUSH.
REPEAT-LOGIN-MESSAGES	causes all system messages (mail sent by privileged users to all users, contained in the file, PS:<SYSTEM>MAIL.TXT) to be printed on the user's terminal each time he logs in to this directory. If this subcommand is not given, only those system messages created since the last time he logged in are printed.
SUBDIRECTORY-USER-GROUP	group number allows propagation of any or all of the group numbers in a directory's user group list to the subdirectories of that directory. Issuing this subcommand is the first step required in establishing subdirectory group rights. You complete the process by issuing the USER-OF-GROUP subcommand for each subdirectory. You can assign up to 40 subdirectory user group numbers to each directory, with values ranging from 1 to 262143 ($2^{18} - 1$).
TOPS10-PROJECT-PROGRAMMER-NUMBER	project number, programmer number allows TOPS-10 programs that require a project-programmer number (PPN) to create subjobs to be compatible with TOPS-20. The project number is an octal number in the range 10-377777. The programmer number is a six-digit octal number. Separate the project number from the programmer number with a comma, for example 17,76.
USER-OF-GROUP	number assigns the directory owner to the given group. You can assign up to 40 group numbers to each directory, with values ranging from 1 to 262143 ($2^{18} - 1$). See the <u>TOPS-20 System Manager's Guide</u> for a discussion of groups.

BUILD (Cont.)

WHEEL

grants Wheel capabilities to the owner of the directory, allowing him to perform all the privileged functions available on the system; these are discussed further in the TOPS-20 Operator's Guide. Requires WHEEL or OPERATOR capabilities.

WORKING [pages INFINITY

allocates working disk storage capacity (in pages) to the directory, and subtracts an equal number from the working disk storage capacity of the superior directory. This working space is temporary and is allocated to the directory only while the user is logged in. Ordinarily, working and permanent storage limits are equal.

INFINITY allows users with Wheel or Operator capabilities to allocate an unlimited number of pages to the directory. The working disk storage of the superior directory must also be INFINITY. The number of pages that can be used is limited to the number of free pages on the structure.

The INFINITY argument is intended for special system directories; it is not intended for general users.

Default pages - 250

Characteristics

BUILD and ^ECREATE

The BUILD command is identical in format to the privileged ^ECREATE command. If you use BUILD with Wheel or Operator capabilities enabled, it has the same power as ^ECREATE, namely, to create directories and modify the parameters of any directory on the system. Without these capabilities, you can use BUILD to modify a more restricted set of directories: you can modify a directory if you have write access to the immediately superior directory. The LOGIN, CONNECT, or ACCESS command obtains write access to the superior directory; or, if you have sufficient group rights to the superior directory, you can use BUILD to modify its subdirectories.

More Information

For a description of using ^ECREATE to create directories, see the TOPS-20 Operator's Command Language Reference Manual.

BUILD (Cont.)

Quotas Subtracted from the Superior Directory's Allotments

Working and permanent disk storage page limits, and the maximum number of subdirectories allowed to a subdirectory are subtracted from the quotas allocated to the immediately superior directory. This subtraction occurs at the time of their allotment to a subdirectory. If the superior directory's quota is not sufficient, the BUILD command will fail. (Note that if you have enabled Wheel or Operator capabilities, you can stop the subtraction of quotas from the superior directory with the PRESERVE subcommand.)

To increase the superior directory's quota or any of these quantities you must either kill some of its subdirectories or reduce their allotments of the quantity. Or you can ask the system manager to increase the allotment of the superior directory. Remember that unless you specify working and permanent page limits, they will assume a default value of 250 pages. The BUILD command will fail in this case if there are not at least 250 pages free in the immediately superior directory.

Assigning Infinite Quotas

If you have Wheel or Operator capabilities enabled, you can assign the maximum storage limit of 34359738367 (i.e., $2^{35}-1$) to a directory. This will appear in the response to an INFORMATION DIRECTORY command as +INF, denoting infinite storage capacity. If you then use the BUILD command to construct subdirectories to this directory, any disk storage capacity assigned, even the maximum, will not be subtracted from the superior directory. You can use this feature to assign infinite storage capacity to a number of users sharing a private structure. Then these users may use storage space on the structure without limit until the disk pack fills up.

Hints

Keeping Track of Subdirectories

Subdirectories appear as files of type .DIRECTORY in the immediately superior directory, so the DIRECTORY *.DIRECTORY command for the superior directory will indicate any existing subdirectories. To suppress the listing of these files you can use the SET FILE PROTECTION command to give them a protection of 000000, but then you must specify the files completely (including generation number) to access them in the future.

BUILD (Cont.)

If there are two or more levels of subdirectories below a superior directory, you can do something else to allow a listing of them: put each subdirectory into a group of which the owner of the highest-level superior directory is a member. Then, if you obtain the group rights of this owner (e.g., by using the LOGIN or ACCESS command if the superior directory is on the public structure, or ACCESS if it is on another structure), the INFORMATION DIRECTORY <directory.*> command with the NAME-ONLY subcommand will produce a listing of subdirectories at every level beneath the superior directory. For this feature to operate properly the group field of each subdirectory's protection code must be at least 40.

Modifying Subdirectories Easily

By following the above procedure, that is, by making subdirectories at every level members of groups of which the owner of the highest-level superior directory is also a member, you make the modification of these subdirectories much easier. You can use the BUILD command to modify these subdirectories or read and write to them, as long as you have the group memberships of this owner. You need not connect to each subdirectory's immediate superior to make modifications.

Restrictions

Giving Capabilities to Subdirectory Owners

In order to give capabilities (Wheel, Operator, Absolute-Arpanet-Sockets, Arpanet-Wizard, Confidential, Enq-Deq, IPCF, or Maintenance) to a subdirectory owner, you must have these capabilities yourself, and they must be enabled at the time of the BUILD command. Wheel and Operator capabilities allow you to assign any capabilities. The INFORMATION DIRECTORY command for your log-in directory tells you which capabilities you have, if any.

Modifying Other Directories

Unless you have Wheel or Operator capabilities enabled, you can use the BUILD command to modify the parameters of only those directories subordinate to a directory to which you have write access. (See Characteristics - BUILD and ^ECREATE, and Hints - Modifying Subdirectories Easily, above.) If your installation allows it, you can use the SET DIRECTORY command to change some parameters of these directories.

Files-only Directories

By giving the FILES-ONLY subcommand you make the directory a files-only directory (see Figure 1). A files-only directory is not associated with a user and so should not be given capabilities or user group memberships. Although a files-only directory can have subdirectories, none of these can be a user directory. You cannot give the ACCESS or LOGIN command for a files-only directory.

BUILD (Cont.)

Killing Directories


You cannot kill a directory that has subdirectories; first you must kill those subdirectories one by one. (When you kill a directory, the files it contains are deleted and expunged.) Also, you cannot kill a directory if you are logged into it or connected to it, or there are open files on it.

Restricted Use of BUILD Command

Your system manager may make the BUILD and SET DIRECTORY commands available only to users with enabled Wheel or Operator capabilities.

Related Commands

INFORMATION DIRECTORY	for examining the parameters established for a directory
INFORMATION DISK-USAGE	for determining how much of a directory's disk space is already assigned to files
SET DIRECTORY	for changing certain directory parameters



MR-S-3904-85

Figure 1: Directories and Subdirectories

BUILD (Cont.)

Examples

The examples show how a user with a directory named <CHEM> builds subdirectories in the pattern shown in Figure 1.

1. Build directories for two of your students or employees, assigning disk space and passwords and placing them in one of your directory groups; check their parameters.

```
@BUILD <CHEM.ALLEN>
[New]
@@WORKING 50
@@PERMANENT 50
@@PASSWORD 619JIM
@@DIRECTORY-GROUP 2391
@@LIST
NAME <CHEM.ALLEN>
Working disk storage page limit 50
Permanent disk storage page limit 50
Account default for LOGIN - none set
Directory groups 2391
```

```
@@
@BUILD <CHEM.BLAKE>
[New]
@@WORKING 50
@@PERMANENT 50
@@PASSWORD 127BIL
@@DIRECTORY-GROUP 2391
@@LIST
Name <CHEM.BLAKE>
Working disk storage page limit 50
Permanent disk storage page limit 50
Account default for LOGIN - none set
Directory groups 2391
```

@@

2. Modify Blake's directory to allow him to create 2 subdirectories.

```
@BUILD <CHEM.BLAKE>
[Old]
@@MAXIMUM-SUBDIRECTORIES 2
@@
```

3. Build a files-only directory to store examination questions.

```
@BUILD <CHEM.TESTS>
[New]
@@FILES-ONLY
@@WORKING 10
@@PERMANENT 10
@@PASSWORD MINERVA
@@DIRECTORY-GROUP 2391
@@
```

BUILD (Cont.)

4. Build a files-only directory as a library directory for your subdirectory owners. Place the directory and these users in the same group.

```
@BUILD <CHEM.LAB-NOTES>
[New]
@@FILES-ONLY
@@WORKING 25
@@PERMANENT 25
@@PROTECTION 774000
@@DEFAULT-FILE-PROTECTION 775200
@@DIRECTORY-GROUP 2392
@@
@BUILD <CHEM.ALLEN>
[Old]
@@USER-GROUP 2392
@@
@BUILD <CHEM.BLAKE>
[Old]
@@USER-GROUP 2392
@@
```

5. User Blake quits. Delete his directory.

```
@BUILD <CHEM.BLAKE>
[Old]
@@KILL
[Confirm]
@@
```

6. Modify a subdirectory so that the subdirectory's owner will have 350 disk pages available.

```
@BUILD <TUCKER.TEST>
[Old]
@@PERMANENT 350
@@
?Request exceeds superior directory permanent quota.
Please fix incorrect subcommands.
```

The action above produced an error message. To correct the error, PUSH out of the BUILD session to learn what the superior directory's permanent quota is.

```
@@PUSH

TOPS-20 Command processor 5(702)
@INFORMATION DISK-USAGE
PS:<TUCKER>
70 Pages assigned
261 Working pages, 261 Permanent pages allowed
7546 Pages free on PS:, 144454 pages used.
```

Then return to the BUILD session, and specify a permanent quota that is less than the superior directory's quota of 261 disk pages.

```
@POP
[Continuing BUILD of directory PS:<TUCKER.TEST>]
@@PERMANENT 170
@@
```

CANCEL

CANCEL

Cancels requests made with a queue-class command.

Format

@CANCEL (REQUEST TYPE) queue (ID) identifier/switch(es)

where

queue is the name of the queue, chosen from the following list:

ARCHIVE	for requests made using the ARCHIVE command
BATCH	for requests made using the SUBMIT command
CARDS	for requests made using the PUNCH CARDS command
MOUNT	for requests made using the MOUNT STRUCTURE or MOUNT TAPE command
PAPER-TAPE	for requests made using the PUNCH PAPER-TAPE command
PLOT	for requests made using the PLOT command
PRINT	for requests made using the PRINT command
RETRIEVE	for requests made using the RETRIEVE command

request ID number

the unique identifier assigned by the system to your request. This is the number appearing under the heading "Req#" in the list of requests shown by the appropriate INFORMATION command (see Related Commands, below). To cancel archival requests, use "filespec" argument instead.

CANCEL (Cont.)

jobname the jobname of the request, either the first six characters of the first filename in the request or the argument you supplied to a /JOBNAME switch when making the request (for output and batch requests), or the first six characters of each filename in the request (for retrieval requests), or the first six characters of the structure alias or tape set n. This is the name appearing under the heading "Name", "Req Name", or "Job Name" in the list of requests shown by the appropriate INFORMATION command (see Related Commands, below).

filespec the specification of a file. Use this argument to cancel archival requests.

***** the asterisk identifier cancels all your requests in the specified queue.

/switch is one or more of the following switches:

/JOBNAME:jobname which gives the jobname of the request you want to cancel. See Special Cases - /JOBNAME Switch, below.

/SEQUENCE:n which gives the sequence number of the batch or output request you want to cancel. The INFORMATION BATCH-REQUESTS or INFORMATION OUTPUT-REQUESTS command with the /ALL switch gives the sequence number assigned to these requests. Use this switch in CANCEL commands placed within batch jobs: then you can cancel requests made earlier in the batch job even though you do not know the request ID number.

CANCEL (Cont.)

/USER:user name

which cancels the specified request entered under the given user name. Use an asterisk (*) both for request ID number and as argument to this switch to cancel all requests of all users in the specified queue. For privileged users only.

Output

When you complete a CANCEL command removing a request, the system responds with "[1 Job Canceled]" and makes the appropriate deletion from the indicated queue. If the job is being processed, the response is "[1 Job Canceled (1 was in progress)]", but if the job is already finished, it is simply "[No Jobs Killed]".

Characteristics

Request ID or Jobname as Argument to CANCEL

You can cancel a single queue request (those made with Queue-class commands - MOUNT, PLOT, PRINT, PUNCH, RETRIEVE, or SUBMIT) by giving either its request ID number or its jobname as the second argument of a CANCEL command. This argument is interpreted as a request ID number unless it includes one or more non-numeric characters. If the argument includes non-numeric characters it is interpreted as a jobname. By giving a jobname as the second argument of a CANCEL command, you cancel all your requests of that jobname in the specified queue. But see also Special Cases - /JOBNAME Switch, below.

Special Cases

/SPOOLED-OUTPUT Switch

You can give the special switch, /SPOOLED-OUTPUT, after the CARDS, PAPER-TAPE, PLOT, or PRINT argument to the CANCEL command. By doing so you cause any accumulated requests in the spooler queue for the appropriate output device (CDP:, PTP:, PLT:, or LPT:, respectively) to be canceled, rather than filled when you log out. Do not give any further arguments to a "CANCEL queue /SPOOLED-OUTPUT" command.

CANCEL (Cont.)

/JOBNAME Switch

In the singular case when you want to cancel several queue requests of the same jobname using a single command, and that jobname is purely numerical (for example, 5045), you must use the /JOBNAME:jobname switch as the second argument to the CANCEL command. Do not also give the request ID or jobname as a command argument if you give the /JOBNAME:jobname switch.

Restrictions

Cannot Cancel Filled Tape-mount Requests

You cannot use the CANCEL command to withdraw a MOUNT TAPE request once the first volume of tape has been mounted (i.e., once you have received a message of the form, [setname defined as MTn:]). Use the DISMOUNT command to give up your tape resource in this case. Note that the DEASSIGN or LOGOUT command will also dismount the tape set.

Cannot Cancel Certain Archival Requests

You cannot use the CANCEL command to withdraw an archival request once the operator has initiated archival procedures. Thus, even though files remain on disk between the operator's first and second archive runs, you cannot cancel a request during this time. If you try to cancel a request after archiving has begun, you receive the error message:

?File has archive status: filename

Note that this error does not terminate a multifile CANCEL ARCHIVE command (for example, CANCEL ARCHIVE *.*); the TOPS-20 command processor continues processing each remaining filename in the request. Cancel requests for these remaining files are judged individually.

Related Commands

ARCHIVE	for requesting archival of a file
INFORMATION ARCHIVE-STATUS	for finding out the archival status of files
INFORMATION BATCH-REQUESTS	for examining requests in the batch input queue
INFORMATION MOUNT-REQUESTS	for examining requests in the structure- and tape-mount queue
INFORMATION OUTPUT-REQUESTS	for examining requests in the line printer, plotter, card punch, and paper tape punch queues

CANCEL (Cont.)

INFORMATION RETRIEVAL-REQUESTS	for examining requests in the retrieval queue
MODIFY	for changing requests without removing them
MOUNT	for placing requests in the structure- or tape-mount queue
PLOT	for placing requests in a plotter queue
PRINT	for placing requests in a line printer queue
PUNCH	for placing requests in the card- or paper-tape-punch queue
RETRIEVE	for placing requests in the retrieval queue
SUBMIT	for placing requests in the batch input queue

Examples

1. Cancel a specific print request.

```
@CANCEL PRINT REMAX
[1 Job canceled]
```

2. Cancel all your batch requests.

```
@CANCEL BATCH *
[3 Jobs canceled]
```

3. Find out what line printer requests you have made, then cancel one of two jobs bearing the same jobname.

```
@INFORMATION OUTPUT-REQUESTS /USER
```

Printer Queue:

Job Name	Req#	Limit	User
MYCOPY	142	81	LATTA /Lower /After: 8-Nov-79 18:00
MYCOPY	143	81	LATTA /After: 8-Nov-79 18:00
MYCOPY	144	81	LATTA /After: 8-Nov-79 18:00
HOLMAX	141	200	LATTA /After: 8-Nov-79 17:00
HOLMAX	140	200	LATTA /After: 8-Nov-79 18:00

There are 5 Jobs in the Queue (None in Progress)

```
@CANCEL PRINT 141
[1 Job Canceled]
```

CANCEL (Cont.)

4. Get a list of your printing jobs (and some of the switches you gave), then cancel three of them.

@INFORMATION OUTPUT-REQUESTS /ALL/USER

Printer Queue:

Job Name	Req#	Limit	User
MYCOPY	142	81	LATTA /Lower /After: 8-Nov-79 18:00
	/Prio:20	/Seq:1728	
MYCOPY	143	81	LATTA /After: 8-Nov-79 18:00
		/Seq:1729	
MYCOPY	144	81	LATTA /After: 8-Nov-79 18:00
		/Seq:1730	
HOLMAX	140	200	LATTA /After: 8-Nov-79 18:00
		/Seq:1726	

There are 4 Jobs in the Queue (None in Progress)

@CANCEL PRINT MYCOPY
[3 Jobs Canceled]

5. Cancel a plotter request.

@CANCEL PLOT 94
[1 Job Canceled]

6. Cancel a mount request for a structure or a tape set.

@CANCEL MOUNT 24
[1 mount request canceled]

7. Find out what requests are in the mount queue. Cancel your structure mount request.

@INFORMATION MOUNT-REQUESTS

Tape/Disk Mount Queue:

Volume	Status	Type	Write	Req Name	Req#	Job#	User
MARK	MTA1	Tape	Enabled	MARK	126	60	HOVSEPIAN
TAPE	MTA3	Tape	Enabled	TAPE	148	13	WALLACE
LATB	Waiting	Disk		LATB	157	65	LATTA

There are 3 Requests in the Queue

@CANCEL MOUNT 157
[1 mount request canceled]

CANCEL (Cont.)

8. Find out what requests are in the mount queue. Cancel a mount request that has not yet been filled, and dismount a tape that has been mounted.

@INFORMATION MOUNT-REQUESTS

Tape/Disk Mount Queue:

Volume	Status	Type	Write	Req Name	Req#	Job#	User
MARK	MTA1	Tape	Enabled	MARK	29	15	HOVSEPIAN
DBL02	MTA0	Tape	Enabled	LAT	31	24	LATTA
NCV19	Waiting	Tape	Enabled	NCV	32	24	LATTA

There are 3 Requests in the Queue

@CANCEL MOUNT 32

[1 mount request canceled]

@DISMOUNT TAPE LAT:

[Tape dismounted, logical name LAT: deleted]

CLOSE

Closes open files in your job and releases their JFNs.

Format

@CLOSE (JFN) n

where

n is the JFN (Job File Number) of a file
 Default n - all JFNs for open and closed files

Output

When the CLOSE command is completed, the system prints a message on your terminal for each JFN that it has closed or attempted to close.

Characteristics

CLOSE Usually Unnecessary

The CLOSE command is used to preserve the contents of a file after the abnormal termination of the program that opened it. Under ordinary conditions you do not need to use the CLOSE command.

Special Cases

CLOSE For Closed Files

If you give the CLOSE command for an existing but closed JFN, the JFN is released.

Restrictions

Closing Mapped Files

You cannot close files that are mapped into memory; in this case you may give the RESET command, which clears memory. (Note, however, that RESET will delete and expunge a mapped file if the file is new, rather than save it as CLOSE would. To save a new mapped file, give the SET PAGE-ACCESS 0:777 NONEXISTENT command, and follow this with CLOSE.) If RESET by itself does not close the file, you may first have to give the POP command to return to a higher level of the TOPS-20 command processor; then give the RESET command.

Once memory has been cleared, all files are closed for processes at the current and lower levels of TOPS-20.

CLOSE (Cont.)

Related Commands

INFORMATION FILE-STATUS	for determining which files are open in your job
INFORMATION MEMORY-USAGE	for determining which files are mapped
RESET	for closing mapped files and clearing memory

Examples

1. Close an open file.

```
@CLOSE 4
4 EDIT-BUFFER.OUT.100036 [OK]
```

2. Try to close all your open files. Give the RESET command to close those that are mapped. (Note that the file EXEC.EXE, containing the TOPS-20 command processor, cannot be closed.)

```
@CLOSE
3 TEST1.CBL.1 [OK]
2 PS:<TEST>EDIT.EXE.4 Can't close file - File still mapped
1 PS:<SYSTEM>EXEC.EXE.3 Can't close file - File still mapped
@RESET
@CLOSE
1 PS:<SYSTEM>EXEC.EXE.3 Can't close file - File still mapped
```

COMPILE

Translates source files into object (relocatable binary) files.

Format

```
@COMPILE (FROM) /switch(es) source/switch(es) object,...
```

where

switches are keywords chosen from the list below, indicating your choice of COMPILE command options. They have different effects depending on their position in the command line: placed before all files in the command, they act as defaults for all; otherwise, they affect only the nearest preceding file.

Defaults are shown in the list of switches

source is the file specification of a source program. The filename must be of 6 or fewer characters, and the file type of 3 or fewer characters; you cannot use a generation number.

Default - arguments you gave in your last LOAD-class command

object is the filename you choose for the object file; it must be of 6 or fewer characters.

Default - filename of the source file (file type is .REL)

,... means that, after commas, you can give more arguments of the form already shown

Summary of COMPILE Command Switches (defaults in boldface)

```
|      /10-BLISS
|      /36-BLISS
|      /68-COBOL
|      /74-COBOL
|      /ABORT
|      /ALGOL
|      /BINARY
|      /COBOL
|      /COMPILE
|      /CREF
|      /CROSS-REFERENCE
|      /DEBUG
|      /FAIL
|      /FLAG-NON-STANDARD
|      /FORTRAN
|      /LANGUAGE-SWITCHES:"/switch(es)"
|      /LIST
|      /MAC
|      /MACHINE-CODE
|      /MACRO
|      /NOBINARY
|      /NOCOMPILE
|      /NOCREF
|      /NOCROSS-REFERENCE
```


COMPILE (Cont.)

```
| /NODBUG  
| /NOFLAG--NON-STANDARD  
| /NOLIST  
| /NOMACHINE-CODE  
| /NOOPTIMIZE  
| /NOSTAY  
| /NOWARNINGS  
| /OPTIMIZE  
| /PASCAL  
| /SAIL  
| /SIMULA  
| /SNOBOL  
| /STAY  
| /WARNINGS
```

Descriptions of these switches are given below. Although the system will not reject switches described under any of the LOAD-class commands, only those switches commonly associated with COMPILE are described here.

COMPILE Command Switches

```
| /10-BLISS      compiles the file using the BLISS-10 compiler.  
|                Default for files of type .B10 and .BLI  
|  
| /36-BLISS      compiles the file using the BLISS-36 compiler.  
|                Default for files of type .B36  
|  
| /68-COBOL      compiles the file using the COBOL-68 compiler.  
|                Default for files of type .C68 or .68C  
|  
| /74-COBOL      compiles the file using the COBOL-74 compiler.  
|                Default for files of type .C74 or .74C  
|  
| /ABORT         stops a compile if a fatal error is detected and  
|                returns your terminal to TOPS-20 command level.  
|  
| /ALGOL         compiles the file using the ALGOL compiler.  
|                Default for files of type .ALG  
|  
| /BINARY        allows generation of an object (binary) file for  
|                each source file given. Use this switch to cancel  
|                a /NOBINARY switch.  
|                Default  
|  
| /COBOL         compiles the file using the COBOL compiler, either  
|                COBOL-68 or COBOL-74, that your installation has  
|                stored in the file SYS:COBOL.EXE.  
|                Default for files of type .CBL  
|  
| /COMPILE       forces compilation of the source file even if a  
|                current object file already exists. Use this  
|                switch along with the /LIST or /CREF switch to  
|                obtain listings when you have current object  
|                files. (See also the /NOBINARY switch.)  
|  
| /CREF          same as /CROSS-REFERENCE
```

COMPILE (Cont.)

/CROSS-REFERENCE creates a file containing cross-reference information for each compilation. The filename is that of the object file; the file type is .CRF. Use the CREF command to obtain a listing of the file. (For COBOL files, this switch automatically produces a cross-reference listing.) See the TOPS-20 User Utilities Guide for information about the CREF program.

/DEBUG produces an object file containing debugging information beyond what is usually inserted during a compilation. (For FORTRAN programs only, and only if you have not given the /OPTIMIZE switch.)

/FAIL compiles the file using the FAIL compiler.
Default for files of type .FAI

/FLAG-NON-STANDARD indicates non-standard syntax in file.

/FORTRAN compiles the file using the FORTRAN compiler
Default in the absence of a standard source file type and a language switch
Default for files of type .FOR

/LANGUAGE-SWITCHES:"/switch(es)" passes the specified switches to the compiler that will process the file(s) to which this switch applies. You must include the switches in double quotation marks (" ").

/LIST prints a listing of the program in ASCII format; the name of this listing is the filename of the object file. The /CREF switch overrides /LIST when they both apply to the same file.

/MAC same as /MACRO

/MACHINE-CODE produces a file containing the generated machine code. The filename is that of the object file; the file type is .LST. For high-level languages.
Default

/MACRO assembles the file using the MACRO assembler.
Default for files of type .MAC

/NOBINARY prevents generation of an object (binary) file. Use this switch along with /LIST or /CREF to allow these switches to take effect without producing a new object file.

/NOCREF same as /NOCROSS-REFERENCE.

COMPILE (Cont.)

`/NOCOMPILE` prevents compilation if the associated object file is current; otherwise it forces compilation. Cancels `/COMPILE` or `/RELOCATABLE`. See Characteristics - Compiling New Sources Only, below.
Default

`/NOCROSS-REFERENCE` prevents the creation of a cross-reference file.
Default

`/NODEBUG` excludes special debugging information from your object file. (For FORTRAN programs only.)
Default

`/NOFLAG-NON-STANDARD` prevents the flagging of nonstandard syntax in the file.
Default

`/NOLIST` prevents a line printer listing of the program.
Default

`/NOMACHINE-CODE` prevents generation of a file containing machine code.
Default

`/NOOPTIMIZE` prevents the generation of a globally optimized object file. (For FORTRAN programs only.)
Default

`/NOSTAY` stops the compiler from being placed in a background fork. Use when `/STAY` is set as a default for the compiler.

`/NOWARNINGS` prevents display of warnings for nonfatal errors.

`/OPTIMIZE` calls for generation of a globally optimized object file, that is, one that runs as quickly as possible. (For FORTRAN programs only, and only if you have not given the `/DEBUG` switch.)

`/PASCAL` compiles the file using the PASCAL compiler.
Default for files of type `.PAS`

`/SAIL` compiles the file using the SAIL compiler.
Default for files of type `.SAI`

`/SIMULA` compiles the file using the SIMULA compiler.
Default for files of type `.SIM`

`/SNOBOL` compiles the file using the SNOBOL compiler
Default for files of type `.SNO`

COMPILE (Cont.)

| /STAY returns your terminal to TOPS-20 command level so
| that you can perform other work while the system
| continues to compile your program. You
| immediately receive the TOPS-20 prompt (@ or \$),
| and can then issue any user command. Be careful
| not to send incorrect data to programs expecting
| terminal input. (Refer to the CONTINUE command,
| Restrictions: Programs Competing for Terminal
| Input.)

| This switch saves you from having to: issue a ^T
| to make sure the compiler has begun; give a ^C to
| halt compilation; and issue a CONTINUE /STAY
| command to remain at command level during
| compilation.

| /WARNINGS displays warnings for nonfatal errors.
| Default

Characteristics

Compiling New Sources Only

The system usually compiles only those sources for which there are no current object files, that is, sources whose write dates are more recent than those of the object files of the same name.

However, sources for which you supply a new object filename are compiled even if there are current object files. You can always force compilation with the /COMPILE switch.

Default Switches Not Passed to Compiler

| Only switches specified in a LOAD-class command are passed
| to the compiler; default switches are not passed. Instead,
| the system assumes that the defaults for the compiler are
| the same as the defaults for the LOAD-class command.

Using Standard File Types

If you specify source files with standard types (.FOR, .MAC, .CBL, or .ALG) in a COMPILE command, the system automatically calls the appropriate compiler when compilation is necessary. If you specify source files by filename only, the system searches your connected directory in the above order for a file of this name and a standard type. To compile programs from sources that have nonstandard file types, give a switch to indicate the proper compiler (/FORTRAN, /MACRO, /COBOL, or /ALGOL). A switch will take precedence over a standard file type if they indicate different languages. If no compiler is indicated with either a switch or a standard file type, the FORTRAN compiler is used.

COMPILE (Cont.)

Hints

Plus Signs Between Filespecs

If you give two or more filespecs separated by plus signs (+) as arguments to COMPILE, they are compiled together as if they were a single file. Their object module is stored under any filename given as the "object" argument of the command, or (if none) under the last filename in the group and file type .REL.

Indirect Files as Arguments

You can store the arguments (source and object filespecs, switches) of a COMPILE command in an indirect file, and specify them by typing an at sign (@) and its filespec as a COMPILE command argument.

Establishing Default Arguments with the SET Command

You can issue the SET DEFAULT COMPILE-SWITCHES command to set up default global arguments to the COMPILE command. Insert this SET command in your COMAND.CMD file to change your own defaults permanently.

Wildcards Illegal with COMPILE

The COMPILE command does not accept wildcard characters (* and %) in a file specification.

Effect on Memory

The COMPILE command clears any unkept forks from memory and loads the appropriate compiler.

Related Commands

LOAD, EXECUTE, and DEBUG	other LOAD-class commands for performing related functions
--------------------------	--

COMPILE (Cont.)

Examples

1. Compile a FORTRAN program.

```
@COMPILE RSD2.FOR  
FORTRAN: RSD2  
MAIN.
```

2. Do the same thing, using a switch to indicate the proper compiler. Use the /STAY switch to return immediately to TOPS-20 command level.

```
@COMPILE RSD2/FORTRAN/STAY  
@PUSH
```

```
TOPS-20 Command processor 6(1015)  
@EDIT LOGIN.CMD
```

3. Create an indirect file using the EDIT editor. Use it to compile several programs, forcing a compilation of the last one and storing its object file under a new name.

```
@CREATE UPDATE.CMD  
Input: UPDATE.CMD.1  
00100 /COBOL FSTQ, SNDQ, THDQ, FTHQ/COMPILE ANNUAL  
00200 $  
*E  
E
```

```
[UPDATE.CMD.1]  
@COMPILE @UPDATE.CMD  
COBOL: DMN [FSTQ.CBL]  
COBOL: DMN [SNDQ.CBL]  
COBOL: DMN [THDQ.CBL]  
COBOL: DMN [FTHQ.CBL]
```

```
EXIT  
@DIRECTORY,  
@@CHRONOLOGICAL WRITE  
@@REVERSE  
@@
```

```
PS:<LATTA>  
ANNUAL.REL.1  
THDQ.REL.1  
SNDQ.REL.1  
SNDQ.CBL  
FSTQ.CBL
```

Total of 5 files

COMPILE (Cont.)

4. Produce a cross-reference (.CRF) file for a FORTRAN program although you already have a current object file; prevent the generation of a new object program. Check for the output file.

```
@COMPILE /CREF/FORTRAN/COMPILE/NOBINARY RSD2
FORTRAN: RSD2
MAIN.
@DIRECTORY,
@@CHRONOLOGICAL WRITE
@@REVERSE
@@
```

```
PS:<LATTA>
RSD2.CRF.1
017CRE.TMP.100017;T
RSD2.REL.1
RSD2.FOR
```

Total of 4 files

CONNECT

Connects your job to a directory.

Format

```
@CONNECT (TO DIRECTORY) dev:<directory>  
PASSWORD:password
```

where

dev:<directory> is the directory to which you want to connect
 Default dev: - your connected structure

 Default <directory> - the directory (on
 the specified structure) of the
 same name as your connected
 directory

 Default (if no arguments are given) -
 your log-in directory on the
 public structure

password is the password of the directory (not
 requested for your log-in directory or a
 directory to which you already have ownership
 or sufficient group rights)

Characteristics

Capabilities

Your capabilities (Wheel, Operator, Confidential, etc.) are associated with your log-in user name only. If you connect to a directory whose owner has Wheel capabilities, you do not gain these capabilities.

Hints

Obtaining Group Rights

You can obtain group rights equal to those of the owner of a directory by giving the ACCESS command instead of, or in addition to, CONNECT for that directory.

CONNECT (Cont.)

Restrictions

Features Not Affected

For some system features, CONNECT does not affect the directory used:

System Accounting

The SET ACCOUNT command allows arguments valid for your log-in user name only. Generally, charges for system use are made to your log-in user name.

Queue-class Commands

The Queue-class commands charge processing requests to your log-in user name only.

Related Commands

ACCESS	for obtaining group as well as ownership rights equal to those of the owner of a directory
MOUNT	for making a structure available for connecting and ensuring the continued availability of the structure

Examples

1. Connect to another user's directory.

```
@CONNECT <HOLLAND>  
Password:____
```

2. Try to access a directory. Discovering that it is a files-only directory, connect to it instead.

```
@ACCESS <MANUALS>  
?Directory is "files-only" and cannot be accessed  
@CONNECT <MANUALS>  
Password:____
```

CONNECT (Cont.)

3. Connect to another user's directory on a different file structure and then to your directory on that structure; then return to your log-in directory on PS:. Give INFORMATION JOB-STATUS commands as you go along to check which is your connected directory.

```
@INFORMATION JOB-STATUS
Host AURORA
Job 36, TTY207, User LATTA
Account 341
@MOUNT STRUCTURE SNARK:
Structure SNARK: mounted
@CONNECT SNARK:<HOLLAND>
Password:
@INFORMATION JOB-STATUS
Host AURORA
Job 36, TTY207, User LATTA, SNARK:<HOLLAND>
Account 341
@CONNECT <LATTA>
@INFORMATION JOB
Host AURORA
Job 36, TTY207, User LATTA, SNARK:<LATTA>
Account 341
@CONNECT
@INFORMATION JOB-STATUS
Host AURORA
Job 36, TTY207, User LATTA
Account 341
@DISMOUNT STRUCTURE SNARK:
Structure SNARK: dismantled
```

4. Connect to your directory on another structure and obtain your full rights to it. After giving an INFORMATION JOB-STATUS command to verify your connected directory, give a command that depends on these rights. Then return to your log-in directory on PS:.

```
@MOUNT STRUCTURE SNARK:
Structure SNARK: mounted
@ACCESS SNARK:
@CONNECT SNARK:
@INFORMATION JOB
Host AURORA
Job 36, TTY207, User LATTA, SNARK:<LATTA>
Account 341
@INFORMATION DIRECTORY <LATTA.*>,
@@NAME-ONLY
@@
Name SNARK:<LATTA.ALLEN>
Name SNARK:<LATTA.BLAKE>
Name SNARK:<LATTA.LAB-NOTES>
Name SNARK:<LATTA.TESTS>
@END-ACCESS SNARK:<LATTA>
@CONNECT
@DISMOUNT STRUCTURE SNARK:
Structure SNARK: dismantled
```

CONTINUE

Continues execution of a fork that was halted.

Format

@CONTINUE (FORK) argument /switch

where

argument is the fork name or fork number
 Default - the current fork

/switch is a keyword, chosen from the list below,
 indicating your choice of CONTINUE command options

CONTINUE Command Switches

/BACKGROUND keeps your terminal at TOPS-20 command level and
 continues execution of the program in a
 "background" fork. When the program attempts to
 do terminal input or output, it halts and displays
 the message [FORK-NAME wants the TTY].

/NORMALLY restores your terminal to command level (if any)
 within the program.
 Default

/STAY keeps your terminal at TOPS-20 command level and
 continues execution of the program in a
 "background" fork. Output from the program is
 sent to the terminal and is intermixed with
 whatever output is currently displayed. When the
 program attempts to read from the terminal, it can
 randomly intercept input intended for the EXEC or
 another program. Therefore, use this switch with
 programs that, once started, do not request
 further terminal input.

Characteristics

Continuing a Noncurrent Fork

When you continue a noncurrent fork, by including the
fork-name argument in a CONTINUE command, the specified fork
becomes your current fork.

Hints

Stopping a Background Program

To stop a background program, give the FREEZE command.

CONTINUE (Cont.)

Providing Input to a Background Program

A background program, continued with `CONTINUE /BACKGROUND`, sends the message `[FORK-NAME wants the TTY]` when it wants input. A background program, continued with `CONTINUE /STAY`, prints the program prompt, for example `PASCAL>`, when it wants input. To provide input to a program that is running in a background fork, return to program command level with `CONTINUE /NORMALLY`. (Some programs require you to type an extra `RETURN` after `CONTINUE /NORMALLY` to display the program prompt). Then, type the required program input. (See below, Restrictions, Programs Competing for Terminal Input.)

Monitoring your Program

`CONTINUE /STAY` and `CONTINUE /BACKGROUND`, by keeping your terminal at TOPS-20 command level (EXEC), let you use TOPS-20 commands to monitor the progress of your program while it is running. Use the `INFORMATION FORK-STATUS` command to display the CPU time used and the kept and RUN status of each fork belonging to the current EXEC level. More commands for monitoring your programs are listed below in Related Commands.

Running Multiple Programs Simultaneously

To simultaneously run multiple programs in background forks or use commands that affect memory, use one or a combination of the following methods after placing a fork in the background with `CONTINUE /STAY` or `CONTINUE /BACKGROUND`:

PUSHing to an Inferior EXEC Level

Type the `PUSH` command to create an inferior EXEC level and a fresh copy of memory (address space). Then run another program and return to EXEC command level with `CONTINUE /STAY` or `CONTINUE /BACKGROUND`. The new program does not affect the background program since both programs are at a different EXEC level. However, see Restrictions below. `PUSH` to a new EXEC before running each new program.

KEEPing the Fork

Type the `KEEP` command to give the background fork a "kept" status. (A kept fork is not cleared from memory when another program is loaded.) Then run another program and return to EXEC command level with `CONTINUE /STAY` or `CONTINUE /BACKGROUND`. `KEEP` each background fork before running another program. Check the status of your forks with `INFORMATION FORK-STATUS`.

Continuing Forks Using the Fork Name

You can continue a fork by typing the fork name as if it were the `CONTINUE` command. To function as the `CONTINUE` command, the fork must be "kept" with the `KEEP` or the `SET PROGRAM KEEP` command. For more information, refer to the descriptions of these commands.

CONTINUE (Cont.)

More Information

The CONTINUE command is one of the TOPS-20 multiforking-class commands. For more information about multiforking, see the section named Running Multiple Programs in the TOPS-20 User's Guide.

Restrictions

Similar Programs Competing for Files

If you have two similar programs running simultaneously, they may try to access the same files at the same time (for example, temporary files labeled by job number, used by compilers). This may cause unpredictable situations to develop. To avoid the possibility, run different kinds of programs.

Programs Competing for Terminal Input

If you use CONTINUE /STAY to run a program in a background fork, the program can request input from the terminal while you are giving input to the EXEC or another program. This input can be randomly intercepted by the background program when it requests terminal input. Usually though, the EXEC or the current program receives the input.

When terminal input is intercepted by the background program, the program will usually type input error messages. To give input to the program, stop the program by typing two CTRL/Cs or the program's exit command. Then, if the background program is at a higher EXEC command level, give POP commands to return to the EXEC level that holds the background program. (POP terminates the current EXEC and erases programs in its memory.) Finally, give the CONTINUE /NORMALLY command; this puts you at program command level so that you can give the requested input.

Remember, input is intercepted by the background program randomly. Therefore, you may have to type extra CTRL/Cs, program exit commands, and POPs. To reduce confusion about the direction of terminal input, it is recommended that you use CONTINUE /STAY only when you plan to work at the current EXEC level while a program runs in a background fork. You should also CONTINUE /STAY programs that simply end without requesting terminal input. Use CONTINUE /BACKGROUND when you plan to work at a lower EXEC level or at another program command level.

When a program started with CONTINUE /BACKGROUND requests terminal input, it sends the message, [FORK-NAME wants the TTY]. No input is taken by the background program until you return to program command level with CONTINUE /NORMALLY. You should CONTINUE /BACKGROUND programs that request terminal input.

CONTINUE (Cont.)

Maintaining Access to Directories

While a fork is running in the background, use caution in using the CONNECT, ACCESS and END-ACCESS commands. Changing your directory access could leave the fork unable to reference certain files.

No I/O Control with Some Programs

Most programs read and write data to the terminal through standard input and output designators. Some programs however, use different methods of communicating with the terminal. Therefore, when you use /BACKGROUND and /STAY to control terminal input and output from a background fork, the input and output behavior of programs with nonstandard designators can be unpredictable.

Continued Programs Do Not Prompt for input

When you continue a program, the program continues from exactly where it was interrupted. If the program was waiting for input, it will simply continue to wait for input; it won't prompt you again. For example, assume you are running the DECmail/MS program and you press CTRL/C at the MS> prompt. Next, you CONTINUE MS. The cursor moves to the next line but no MS> prompt appears. This is because MS has continued to do the last thing it was doing when you interrupted it with CTRL/C - waiting for a command at the MS> prompt. MS does not know that its prompt is no longer displayed before the cursor.

So, when you continue a program and nothing happens, consider what you were doing when you CTRL/C'd the program. If you were at the MS> prompt, type an MS command or, press RETURN again to redisplay the MS> prompt. If you had typed a portion of an MS command, press CTRL/R to redisplay the command. If you had typed a portion of a mail message, press CTRL/K to redisplay the message.

Effect on Memory and Terminal

The CONTINUE /NORMALLY command resumes processing the program in memory, and leaves your terminal at program command level (if any). The CONTINUE /BACKGROUND and CONTINUE /STAY commands resume processing the program in memory, but leave your terminal at TOPS-20 command level.

Related Commands

DETACH CONTINUE

for disengaging your current job from your terminal and continuing the program that the job is running

FORK

for changing the current fork

CONTINUE (Cont.)

FREEZE	for halting a program in a background fork
INFORMATION FILE-STATUS	for monitoring files being written by your program
INFORMATION FORK-STATUS	for displaying the number and the status of each fork in your job
INFORMATION MEMORY-USAGE	for monitoring your program's use of memory
INFORMATION PROGRAM-STATUS	for monitoring your program's use of CPU time
KEEP	for giving a fork a kept status
PUSH	for obtaining a lower TOPS-20 command level (and a fresh copy of memory)
REENTER	for starting your current program at its alternate entry point (if any)
START	for starting your current program at the beginning
RESET, SET NAME, SET PROGRAM, UNKEEP	other multiforking-class commands for performing related functions

Examples

1. Display the fork status with the INFORMATION FORK-STATUS command. Notice that the arrow points to the current fork. Then, give the CONTINUE command to continue the program in the current, halted fork.

```
@INFORMATION FORK-STATUS
  EDIT (1): Kept, HALT at 6253, 0:02:54.4
=> DUMPER (2): HALT at 700304, 0:01:19.3
@CONTINUE
DUMPER>
```

2. Run the DSR program and then halt it by typing two CTRL/Cs. Give the CONTINUE /BACKGROUND command to continue DSR in a background fork and return to EXEC command level. Then, give the KEEP command so that you can load another program without clearing the running, background, DSR fork. Check the status of DSR with the INFORMATION FORK-STATUS command.

```
@RUN DSR
DSR>TEST.RNO
^C
@CONTINUE /BACKGROUND
@KEEP
[Keeping DSR]
@INFORMATION FORK-STATUS
=> DSR (1): Kept, Background, Running at 413160, 0:00:00.8
```

CONTINUE (Cont.)

Now begin editing a file with the EDIT program. During your editing session the system notifies you that the background fork wants input. To return to DSR command level, first exit the edit program. Then check the fork status with the INFORMATION FORK-STATUS command. Notice that DSR is in a terminal I/O wait state and that EDIT is now the current fork. Since the fork you want to continue is not the current fork, you must specify the fork name with the CONTINUE command. Now type CONTINUE DSR.

```
@EDIT COMAND.CMD
Edit: COMAND.CMD.2
*p
00100    SET DEFAULT PRINT /NOHEADER /NOTIFY:YES
00200    SET PROGRAM MS KEEP START
00300    SET PROGRAM HOST KEEP CONTINUE
00400    SET DEFAULT COMPILE-SWITCHES PAS /NOFLAG-NON-STANDARD
00500    INFO MAIL
00600    TAKE
*I350
00350    SET PROGRAM DUMPER KEEP CONTINUE
DSR>[DSR: wants the TTY]
*_E
[COMAND.CMD.3]
@INFORMATION FORK-STATUS
=> EDIT (1): Kept, HALT at 6253, 0:00:51.4
    DSR (1): Kept, Background, TTY I/O wait at 4404426,
    0:00:00.8
@CONTINUE DSR

DSR>
```

3. Begin editing a long file, giving the F (find) command to EDIT. Give a CTRL/C and then the M command to return to TOPS-20 command level. Give the CONTINUE /STAY command and then INFORMATION FILE-STATUS commands to check the progress of EDIT as it searches through the file. (Notice that the byte position shown in response to successive INFORMATION FILE-STATUS commands grows larger.) Finally, give the CONTINUE command to return to EDIT so you can give more EDIT program commands.

```
@EDIT DOC-PLAN.MEM
Edit: DOC-PLAN.MEM.1
*FABCD$
Yes? (Type H for help): M
@CONTINUE /STAY
@INFORMATION FILE-STATUS
Connected to PS:<LATTA>, JFNS:
 4 <LOADTEST>EDIT.EXE.4      Read, Execute
 3 EDIT-BUFFER.OUT.100046    Read, Write, 0.(7)
 2 DOC-PLAN.MEM.1           Read, 43520.(7)
 1 <SYSTEM>EXEC.EXE.153      Read, Execute

Device assigned to/opened by this job: TTY222
```


CONTINUE (Cont.)

```
@INFORMATION FILE-STATUS 2
 2 DOC-PLAN.MEM.1 Read, 112640.(7)
@INFORMATION FILE-STATUS 2
 2 DOC-PLAN.MEM.1 Read, 130560.(7)
@CONTINUE
```

*

4. Start compiling a long file. After compilation has begun, type two CTRL/Cs to stop the compilation and return to the EXEC command level. Use the CONTINUE /STAY command to resume compilation, and then PUSH to a new EXEC command level. Edit a text file at this lower level, then give the POP and CONTINUE commands to return to the compilation in progress. The compiler finishes, in this case, after you have done so.

```
@COMPILE DUMPER.MAC
MACRO: DUMPER
^C
@CONTINUE /STAY
@PUSH
```

```
TOPS-20 Command processor 4(555)
@EDIT PROFIL.TXT
Edit: PROFIL.TXT.2
*SAPRIL$JUNE$^:*
00100 JUNE 19, 1978
00500 JUNE 12
00750 JUNE 5
00900 JUNE 18
01400 JUNE 21
*E
```

```
[PROFIL.TXT.3}
@POP
@CONTINUE
```

```
EXIT
```

COPY

Creates a copy of a file.

Format

@COPY (FROM) source filespec (TO) destination filespec,
@@subcommand

where

source filespec is the specification of the file or
device whose contents you want to copy

destination filespec is the specification of the file or
device in which you want to store a copy
of the file

Default - same as source filespec
but in your connected
directory, if necessary
using the next higher
generation number

@@subcommand means that after a final comma you can
specify the mode and format of the
transfer with one of the following
subcommands:

COPY Command Subcommands

(when used with the paper tape reader
or paper tape punch - PTR: or PTP:)

ASCII specifies that the file being copied is
written in ASCII mode, with 36-bit words each
consisting of five 7-bit bytes and a parity
bit; the parity bit means that the eighth
hole of the paper tape is never punched.

BINARY specifies that the file being copied is
composed of 36-bit words, each consisting of
six 6-bit bytes with the seventh hole of the
paper tape set always to 0 and the eighth
hole set always to 1; causes a checksum
calculation.

BYTE n specifies that the byte size of the
destination file is to be n (any decimal
number). If you do not give the BYTE
subcommand, the destination file will have
the same byte size as the source file. See
also Hints - Viewing Display Screen Data
below.

IMAGE specifies that the file being copied is
composed of 36-bit words, each consisting of
one 8-bit byte; the 28 most significant bits
are set to 0 on input and are lost on output.

COPY (Cont.)

IMAGE BINARY same as BINARY, but lacking the checksum calculation

COPY Command Subcommands

(when used with devices other than the paper tape reader or paper tape punch)

•	ASCII	specifies that the file being copied is written in ASCII mode, with 36-bit words each consisting of five 7-bit bytes and a parity bit; the parity bit means that the least significant bit is set to 0 on input and is lost on output.
	BINARY	calls for a direct transfer of data in 36-bit bytes
	BYTE n	specifies that the byte size of the destination file is to be n (any decimal number). If you do not give the BYTE subcommand, the destination file will have the same byte size as the source file. See also Hints - Viewing Display Screen Data, below.
	IMAGE	same as BINARY
	IMAGE BINARY	same as BINARY
	SUPERSEDE	sets the condition under which COPY overwrites the destination file of the same name.
	ALWAYS	allows the source file to be copied to the destination file. Default for COPY command
	NEVER	does not copy the file if the destination file already exists.
	OLDER	allows the source file to be copied to the destination file if <ul style="list-style-type: none"> • no version of the destination file exists, or • the generation number is less than or equal to the generation number specified in the destination file and the file's write date is older than the source file.
	NEWER	same as OLDER except allows the copy if the file's write date is "newer" than the source file.

COPY (Cont.)

Output

As each file is copied, the system prints the specifications of the source and destination files and the word [OK]. The delay before you see this [OK] indicates how long it took to copy the file. If you use recognition on the destination file specification, the system prints, !New Generation!, !New File!, or !Superseding!, to indicate the status of disk files, or !OK!, if the file is copied to a non-disk device.

Characteristics

Optional Subcommands With Paper Tape

Each subcommand, when used to copy information from the paper tape reader (PTR:), specifies an interpretation of eight-bit bytes, represented as eight-hole lines on paper tape. When used with the paper tape punch (PTP:), each subcommand specifies a mapping of information to the eight-bit bytes of paper tape.

Optional Subcommands With Other Devices

Each subcommand can be used under particular conditions, for example, when transferring files over network facilities (using DCN: and SRV:), to specify the byte size of information being copied. In general, you can use COPY command subcommands whenever you need to specify the byte size of information being copied.

Hints

RENAME Faster Than COPY for Transferring Files

For moving a set of files from one directory to another on the same structure, the RENAME command is a faster and more efficient means than COPY. This is because RENAME only changes the file specifications; it does not copy the contents of the files. Also, a file transfer with the RENAME command leaves only one set of files, while a transfer with the COPY command leaves two sets: the original copies and the destination copies. The original copies are often unnecessary and must be deleted.

Using Devices as Source and/or Destination Filespecs

By specifying a device as the source and/or destination filespec, you can use the COPY command to transfer information between card- or paper-tape-handling devices, magnetic tape drives, line printers, terminals, or other output devices. However, the PLOT, PRINT, PUNCH and TYPE commands, and appropriate utility programs (e.g., DUMPER and EDIT), offer more flexibility for most applications.

COPY (Cont.)

Copying To or From TTY:

You can simulate the action of the CREATE command for creating files by copying from device TTY: to a new filespec, ending your input with a CTRL/Z; use CTRL/U, CTRL/R, CTRL/W, and the DELETE key to edit the current line of terminal input. You can simulate the action of the TYPE command for displaying files by copying from an existing filespec to device TTY:.

Viewing Display Screen Data

If you specify TTY: as the destination filespec and then give the BYTE 8 subcommand, characters in the source file will be sent literally to your terminal. Do this to examine special display screen data (for 8-bit ASCII files only).

Erasing the Contents of a File While Keeping the Filespec

You can erase the contents of a file by copying from device NUL: to the file. NUL: is a receptacle for unwanted program output and a supplier of null input.

Spooled Output Action

If you send information to output devices using the COPY command, your request is processed according to the status of the SPOOLED-OUTPUT-ACTION parameter, which you set with the SET SPOOLED-OUTPUT-ACTION command.

Using Wildcards in Source and/or Destination Filespecs

You can use wildcard characters (* and %) in source and/or destination filespecs to copy many files at a time. Default values will be assumed for filespec fields you do not specify. Note that if you use wildcard characters to copy more than one source file into a single destination file on disk, the contents of each source file will appear in a different generation of the destination file; the highest generation will contain a copy of the last source file only. Use the APPEND command to put the contents of several files into a single file.

COPY (Cont.)

Specifying a New Account or Protection Number

The COPY command lets you specify the new file's protection number, and the account to which storage fees for it will be charged. Follow the new file specification with a semicolon (;) and the letter P before giving a new 6-digit protection number, and with a semicolon and the letter A before giving a new account (which must be valid for your user name). If you do not specify an account for a new file, it will take as a default the account you gave in your most recent LOGIN or SET ACCOUNT command. However, non-default protection numbers will be maintained for higher generations of existing files, unless you specify otherwise in the COPY command that creates that higher generation.

Restrictions

Copying Archived Files

| You can make a copy of an archived file by specifying it as the first (or source) argument in a COPY command, and specifying a file of different name or type as destination. You can edit the new file, because it does not have archive status although it has the same contents as the original file. However, you cannot give the specification of an archived file as the second (or destination) argument of a COPY command, as this would replace the file's contents. If you attempt to do so, whatever source argument you supply will be copied into the next higher generation of the archived file, leaving the archived file intact. And, if
| you include the generation number when specifying an archived file as the second argument of a COPY command, the
| command will fail.

Warning

Destroying the Previous Contents of Files

If you give a destination file specification that includes a generation number, the source file will be copied into that file, replacing any previous contents if that generation of the file already exists. Those contents cannot be recovered. But see Restrictions - Copying Archived Files, above.

COPY (Cont.)

Related Commands

APPEND	for adding information to a file or putting the contents of many files into a single file
RENAME	for changing only the specification of a file
SET SPOOLED-OUTPUT-ACTION	for changing the setting of the SPOOLED-OUTPUT-ACTION parameter, which determines when files copied to output devices are processed
DIRECTORY with the TIMES WRITE subcommand and VD	for displaying the date and time that the file was written

Examples

1. Make an extra copy of a file in your connected directory.

```
@COPY FORT.TXT BACKUP.TXT  
FORT.TXT.1 => BACKUP.TXT.3 [OK]
```

2. Copy a file from your directory into another user's directory, allowing the destination file to be labeled with default file specification (the source file specification).

```
@ACCESS <SARTINI>  
Password:  
@COPY TEST1.CBL <SARTINI>  
TEST1.CBL.2 => <SARTINI>TEST1.CBL.2 [OK]  
@END-ACCESS <SARTINI>
```

3. Use a wildcard character to copy several files from your directory on another structure to magnetic tape.

```
@ACCESS SNARK:  
@COPY SNARK:NA*.TST MT2:  
SNARK:NACCESS.TST.2 => MT2:NACCESS.TST [OK]  
SNARK:NADVISE.TST.2 => MT2:NADVISE.TST [OK]  
SNARK:NAPPEND.TST.2 => MT2:NAPPEND.TST [OK]  
SNARK:NASSIGN.TST.2 => MT2:NASSIGN.TST [OK]  
SNARK:NATTACH.TST.2 => MT2:NATTACH.TST [OK]  
@END-ACCESS SNARK:
```

4. Use the COPY command to create a short text file.

```
@COPY TTY: NEW-FILE.TXT  
TTY: => NEW-FILE.TXT.2  
  
THIS FILE WAS CREATED USING THE COPY COMMAND.  
^Z  
@  
@TYPE NEW-FILE.TXT  
THIS FILE WAS CREATED USING THE COPY COMMAND.
```

COPY (Cont.)

5. Copy a file from your directory into another user's directory. Give the SUPERSEDE NEVER subcommand to cancel the COPY command if the other user already has a copy of the file.

```
@ACCESS <STEVENS>  
Password:_____  
@COPY STATS.TXT <STEVENS> ,  
@@SUPERSEDE NEVER  
@@  
  STATS.TXT.1 => <STEVENS>STATS.TXT.3  
%Not superseding current file
```


CREATE

Invokes your defined editor to create a file.

Format

@CREATE (FILE) /switch(es) filespec

where

switches are keywords, chosen from the list below, indicating your choice of CREATE command options
Defaults are shown in the list of switches

filespec is a specification for the file you want to create
Default - the last file specification and associated switches you gave in a CREATE or EDIT command during the current terminal session

Summary of CREATE Command Switches (defaults in boldface)

NOTE

These switches are valid only if you have defined logical name EDITOR: to be the EDIT program.

/BAK	
/C128	
/C64	
/DECIDE	
/DPY	
/EXPERT	
/INCREMENT:n	Default n - 100
/ISAVE:n	
/LOWER	
/M33	
/M37	
/NOBAK	
/NODECIDE	
/NONSEPARATORS	
/NONNUMBER	
/NOVICE	
/NUMBER	
/OLD	
/OPTION:name	
/PLINES:n	Default n - 16
/R	
/READONLY	
/RONLY	
/RUN:filespec	Default file type - .EXE
/SAVE:n	
/SEPARATORS	
/SEQUENCE	
/START:n	Default n - argument of /INCREMENT switch
/STEP:n	Default n - 100
/UNSEQUENCE	
/UPPER	
/WINDOW:n	Default n - 10

CREATE (Cont.)

CREATE Command Switches

/BAK	causes an unedited copy of the file to be saved at the end of an editing session under specification name.Qyp, where name.typ is the file's original specification Default
/C128	calls for a 128-character alphabet, allowing insertion of control characters in an alternate format. See the <u>TOPS-20 EDIT Reference Manual</u> for details.
/C64	calls for a 64-character alphabet, disallowing use of an alternate format for insertion of control characters Default
/DECIDE	lets you decide whether to accept or reject each change caused by the operation of the S (substitute) command of the EDIT program
/DPY	has no effect in the current monitor
/EXPERT	tells the EDIT program that you need only abbreviated error messages, and fewer warnings and reminders
/INCREMENT:n	specifies the value to add to each line number of the file to obtain the next line number Default n - 100
/ISAVE:n	instructs the EDIT program to update the backup file of specification name.Qyp after every n lines you insert
/LOWER	specifies that all alphabetic characters you type should be considered lowercase characters; give uppercase characters by preceding the corresponding lowercase character with a single quotation mark (').
/M33	has no effect in the current monitor
/M37	has no effect in the current monitor
/NOBAK	prevents an unedited copy of the file from being saved at the end of an editing session under specification name.Qyp, where name.typ is the file's original specification

CREATE (Cont.)

/NODECODE	ensures the automatic operation of the S (substitute) command of the EDIT program Default
/NONSEPARATORS	specifies that the characters . (period), \$ (dollar sign), and % (percent sign) are ordinary textual characters and not field delimiters (separators) in the accompanying file Default
/NONUMBER	suppresses the printing of line numbers with each line of a file
/NOVICE	tells the EDIT program that you want to see complete error messages and all appropriate warnings; opposite of /EXPERT switch Default
/NUMBER	prints a line number for each line of the file Default
/OLD	causes the first backup file to be saved under the specification name.Zyp, where name.typ is the file's original specification
/OPTION:name	sets any EDIT switches contained in lines of the SWITCH.INI file in your log-in directory labeled with name (of 6 or fewer characters). See the <u>TOPS-20 EDIT Reference Manual</u> for more information about SWITCH.INI files.
/PLINES:n	specifies how many lines to print in response to each P (print) command of the EDIT program Default n - 16
/R	same as /READONLY
/READONLY	prevents any changes to the file during the current session of the EDIT program, i.e., makes it a read-only session. This switch cannot be given in the SWITCH.INI file.
/RONLY	same as /READONLY
/RUN:filespec	specifies an executable program to be run when you end the current session of the EDIT program with the G command Default file type - .EXE
/SAVE:n	instructs the EDIT program to update the backup file (of specification name.Qyp) after every n EDIT program commands that modify the file
/SEPARATORS	notifies the EDIT program that the characters . (period), \$ (dollar sign), and % (percent sign), are not ordinary textual characters but are field separators in the accompanying file

CREATE (Cont.)

/SEQUENCE	tells the EDIT program not to strip the line numbers from the file when the EDIT session ends Default
/START:n	specifies the first line number for the EDIT program to use when numbering the file Default n - argument of /INCREMENT switch
/STEP:n	same as /INCREMENT
/UNSEQUENCE	tells the EDIT program to strip the line numbers from the file when the EDIT session ends
/UPPER	specifies that all alphabetic characters you type should be considered uppercase characters; give lowercase characters by preceding the corresponding uppercase character with a single quotation mark ('). Default
/WINDOW:n	specifies the number n (between 10 and 99) of pages to be held in memory during the EDIT session Default n - 10

Characteristics

Input Mode and Edit Mode

The CREATE command runs the EDIT system program, first in Input mode and then in Edit mode. (However, see also Special Cases, below.) Input mode automatically begins each line with a line number (unless you have given the /NONUMBER switch), and allows you to put any alphabetic or numeric information into the file. When you have finished doing this and press the ESCAPE key, the EDIT program puts you into Edit mode and prompts you with an asterisk (*), just as if you had typed the EDIT command with the specifications of the newly-created file as argument. If you want to save the file in its present state, give the E (for end) command to the EDIT program. Otherwise you can give any other EDIT command to change or add to the file before saving it.

Hints

Saving Backup Files Periodically

Give the /ISAVE:n switch to save an updated copy of the file you are creating after every n lines inserted. Then you will lose only a few lines of input in the event of a system failure. The similar /SAVE:n switch is useful for the CREATE command only in Edit mode, where it saves an updated copy of the file after every n EDIT program commands that modify the file.

CREATE (Cont.)

SWITCH.INI File

If there is a group of CREATE command switches that you always or often use with CREATE or EDIT commands, put them into a file of specification SWITCH.INI in your log-in directory, in a line of that file beginning with EDIT:abc, where abc is any set of characters you choose to identify the line. Then if you include the single switch /OPTION:abc when you give a CREATE or EDIT command, all these switches will be in effect.

Further Information

For more information about the EDIT program, see the TOPS-20 EDIT Reference Manual.

Special Cases

Using an Editor Other than EDIT

| The CREATE, EDIT, and PERUSE command descriptions in this
| manual assume that these commands call on the EDIT program
| for their action. If your job uses another editing program,
| for example EDT, the switches and examples shown here will
| not be applicable.

| The editor used by CREATE, EDIT, and PERUSE is specified by
| logical name EDITOR:, so you can find out the name of this
| program by giving the command, INFORMATION LOGICAL-NAMES
| EDITOR:. The job-wide definition (if any) will be given
| first, followed by the system-wide definition; the job-wide
| definition prevails if both exist. If the definition of
| EDITOR: is SYS:EDIT.EXE, the CREATE, EDIT and PERUSE
| commands will function as described in this manual.
| Otherwise, you must consult the appropriate manual (for
| example, the EDT-20 Reference Manual) for information.

You can use the DEFINE command to define logical name EDITOR: to be any editing program available at your installation. Then this editor will be in effect when you give the CREATE or EDIT command.

Effect on Memory

| The CREATE command clears any unkept forks from memory, then
| loads the editor program defined by the logical name EDITOR.

Related Commands

DIRECTORY-class commands	for getting lists of existing files
EDIT	for modifying existing files
PERUSE	for reading existing files (same as EDIT/READONLY)

CREATE (Cont.)

Examples

1. Create a file.

```
@CREATE FILE1.TXT
Input: FILE1.TXT.1
00100  !THIS IS A SHORT TEXT FILE.
00200  $
*E
[FILE.TXT.1]
```

2. Create and edit (using the P and R commands to the EDIT system program) another file.

```
@CREATE FILEB.TXT
Input: FILEB.TXT.1
00100  !THIS IS ANOTHER SHORT TEXT FILE.
00200  $
*p
00100  !THIS IS ANOTHER SHORT TEXT FILE.
*R100
00100  !THIS IS A SECOND TEXT FILE.
00200  $
1 Lines (00100/1) deleted
*p
00100  !THIS IS A SECOND TEXT FILE.
*E
[FILEB.TXT.1]
```

3. Create, then execute, a FORTRAN program.

```
@CREATE FILEE.FOR
Input: FILEE.FOR.1
00100  C      THIS IS A SHORT TEST PROGRAM.
00200      TYPE 101
00300  101    FORMAT ( ' THIS IS ONLY A FORTRAN TEST.' )
00400      END
00500
*E

[FILEE.FOR.1]
@EXECUTE FILEE.FOR
FORTRAN: FILEE
MAIN.
LINK:   Loading
[LNKXCT FILEE Execution]

THIS IS ONLY A FORTRAN TEST.

END OF EXECUTION.
CPU TIME: 0.04  ELAPSED TIME: 0.44
EXIT
```

CREF

Runs the CREF program, which produces cross-reference listings from files of type .CRF.

Format

@CREF destination-filespec=source-filespec /switch

where

destination-filespec is the name of the file or device to which you want to send the processed contents of the .CRF file
 Default - LPT:

source-filespec is the name of the .CRF file you want to process
 Default - the names of all files of type .CRF produced during the current terminal session

/switch is one or more keywords from the following list.

CREF Program Switches

/A Advances magnetic tape reel by one file. You can type this switch more than once in the command string.

/B Backspaces magnetic tape reel by one file. You can type this switch more than once in the command string.

/C Cancels the processing of any switches in your SWITCH.INI file.

/D Restores the processing of any default switches in your SWITCH.INI file.

/H Types the CREF help file. /H is illegal in a SWITCH.INI file.

/K Suppresses Regular Symbol Table in the CREF listing.

/M Suppresses OPDEF/Macro Table in the CREF listing.

/O Includes the Op Code Table in the CREF listing.

/P Preserves an input file with the file type .CRF or .LST. These types of input files are normally deleted.

CREF (Cont.)

	/R	Requests the line number at which the CREF listing is to start. CREF types out "RESTART LISTING AT LINE:", after which you type the line number and press RETURN. If you use an indirect file, CREF looks for the number in the indirect file. /R is most useful for physical (non-spooled) line printers, and is illegal in a SWITCH.INI file.
	/S	Suppresses the program listing and lists only the tables you select.
	/T	Skips to the logical end of the magnetic tape.
	/W	Rewinds the magnetic tape.
	/Z	Zeroes the DECTape directory. This is a historical switch, and is illegal.

Characteristics

Current .CRF Files

If you have files of type .CRF produced by LOAD-class commands during the current terminal session, the unmodified command CREF produces listings of them and deletes the files. By supplying an argument of the form shown in the Format section above, you can copy the listing for a current .CRF file to another file or device. To run the CREF program yourself when you have current .CRF files, give the command R CREF instead.

.CRF Files From a Previous Session

If your only files of type .CRF (created by the CREF program or one of the LOAD-class commands) were produced during a previous terminal session, the command CREF puts your terminal at command level in the CREF program, symbolized by an asterisk (*). Thus it is equivalent to the command R CREF in this case. See Hints - Further Information, below, for advice on how to proceed.

Hints

Producing .CRF Files

You can produce cross-reference files by including the /CREF switch in any LOAD-class command that actually causes a compilation (i.e., is not prevented from doing so by a /RELOCATABLE switch or by the existence of current object files).

Preserving .CRF Files After Processing

Give the /P switch immediately after the CREF command to preserve .CRF files. Ordinarily they are deleted after being sent to an output device or copied into another file.

CREF (Cont.)

Further Information

For a brief on-line description of the CREF program, give the `HELP CREF` command. For more detailed information, see the TOPS-20 User Utilities Guide.

Effect on Memory and Terminal

The CREF command replaces the contents of any unkept forks in memory with the CREF program and leaves your terminal at TOPS-20 command level, or at command level within CREF (denoted by an asterisk prompt [*]).

Related Commands

LOAD-class commands for producing .CRF files

Examples

1. Give the CREF command to obtain a listing of your .CRF file.

```
@CREF
CREF:  TESTF1
```

2. Compile two FORTRAN programs, using the `/CREF` switch to produce .CRF files. Then give the CREF command to obtain listings of these, and use the `/P` switch to preserve the .CRF files.

```
@COMPILE /CREF TESTF1.FOR, TESTF2.FOR
FORTRAN: TESTF1
MAIN.
FORTRAN: TESTF2
MAIN.
@CREF/P
CREF:  TESTF1
CREF:  TESTF2
```

CREF (Cont.)

3. Determine what .CRF files you have, then mount a tape. Give the CREF command, and once within the CREF program, have the cross-reference listing produced from one of these files copied onto tape. (The .CRF files are not processed automatically when you give the CREF command because they were produced during a previous terminal session.)

```
@DIRECTORY *.CRF
```

```
PS:<LATTA>  
TESTM1.CRF.2  
TESTM2.CRF.1
```

```
Total of 2 files
```

```
@MOUNT TAPE CRFMAC:/WRITE-ENABLED
```

```
[Mount Request CRFMAC Queued, Request-ID 128]
```

```
[Tape set CRFMAC, volume CRFMAC mounted]
```

```
[CRFMAC defined as MT3:]
```

```
@CREF
```

```
*MT3:=TESTM2
```

```
[CRFXKC 4K core]
```

```
*^C
```

```
@DISMOUNT TAPE CRFMAC:
```

```
[Tape dismounted, logical name CRFMAC: deleted]
```

CSAVE

Makes a non-sharable copy of the program in memory and stores it in a file, in compressed executable format.

Format

@CSAVE (ON FILE) filespec (WORDS FROM) loc1 (TO) loc2, loc3 loc4,...

where

filespec is the file specification under which you
 want to store the program
 Default filespec - program name.EXE

loc1 loc2,
loc3 loc4,
... are pairs of octal numbers or symbolic
 expressions that specify the span(s) of
 memory locations you want to save

 Default loc1 loc2 - 20 to last location
 occupied by program

Caution

Inefficiency of CSAVE Compared to SAVE

The CSAVE command saves in a compressed-formatted file whatever program the system finds in memory. When the file is returned to memory, this format prevents other users from sharing the in-memory copy of the file. Therefore you should ordinarily use the SAVE command instead for storing programs in executable format.

Related Commands

GET	for putting a saved file into memory
LOAD	for putting source or output files into memory
RUN	for running executable programs
SAVE	usual command for saving programs in executable format

CSAVE (Cont.)

Examples

1. Save your currently loaded program in compressed executable format.

```
@CSAVE
DMN.EXE.1 SAVED
```

2. Mount a magnetic tape set. Then load an ALGOL program and save it in three places in executable format: once in a disk file under the same filename, again in a disk file under a new filename, and once on magnetic tape.

```
@MOUNT TAPE TAPBAK: /WRITE-ENABLED
[Mount Request TAPBAK Queued, Request-ID 140]
[Tape set TAPBAK, volume TAPBAK mounted]
[TAPBAK defined as MT2:]
@LOAD TESTAL
LINK: Loading

EXIT
@CSAVE
TESTAL.EXE.1 Saved
@CSAVE BAK
BAK.EXE.1 Saved
@CSAVE MT2:
MT2:BAK Saved
@DISMOUNT TAPE TAPBAK:
[Tape dismounted, logical name TAPBAK: deleted]
```

DAYTIME

Displays the current day, date, and time on your terminal.

Format

@DAYTIME

Hints

Using DAYTIME

The DAYTIME command, which does not require you to be logged in, lets you check the system's clock against your own. If you are saving the output from a hard-copy terminal, use this command to make a record of the date and time.

Examples

1. Give the DAYTIME command.

```
@DAYTIME
Friday, April 20, 1984 09:21:19
```

DDT

Loads or merges a debugging program into memory (unless one is already there), then starts it.

Format

@DDT/switch(es)

where

/switch is one or more of the following:

/OVERLAY allows pages of the DDT program to be loaded over pages occupied by the existing program in memory

/USE-SECTION:n specifies the memory section (from 0 to 37 octal) into which the debugging program is to be loaded, run, or merged

Characteristics

If a Debugging Program is Already Loaded

If you have already loaded a debugging program into memory along with your program, the DDT command starts the debugging program.

If Your Program, But Not a Debugging Program, is Already Loaded

If a program containing symbols is in memory without a debugging program, the DDT command merges SYS:XDDT.EXE into memory, then starts this debugging program. However, if some of XDDT's pages include some of the same pages as the existing program in memory, then the DDT program is not placed into memory, and you receive the error message, "?Illegal to overlay existing pages." To force the pages to be overlaid, reissue the DDT command using the /OVERLAY switch.

If There is No Current Program

If you do not have a program in memory, or if no program in memory is in the current fork, or if your program does not contain symbols, the DDT command puts SYS:XDDT.EXE into memory and starts it.

Compatibility with Previous DDT Versions

The UDDT program run by the DDT command has been replaced by the XDDT program. For compatibility with programs that reference UDDT, a stub program named UDDT references the XDDT program.

DDT (Cont.)

Hints

Using DDT to Create a Program

You can use DDT to begin typing instructions directly into memory, without first putting the instructions into a file for later compilation and loading. Give a RESET . (period) command to clear the current fork, then the DDT command. This will load the SYS:XDDT.EXE program. Then you can give commands within XDDT to create your own program. When using the XDDT program, you can use all the symbols in the system parameter file MONSYM.MAC. See the TOPS-20 Monitor Calls Reference Manual for more information about MONSYM.MAC. This method of writing a program is most useful for testing special cases, or for learning to use TOPS-20 monitor calls.

Special Cases

Using COBDDT

If you put COBDDT into memory along with a COBOL program, the DDT command starts the UDDT program, not COBDDT. Use the REENTER command to start COBDDT in this case.

Effect on Memory and Terminal

The DDT command merges the SYS:UDDT.EXE program into the current fork and starts it, or loads and starts SYS:XDDT.EXE. If you have already loaded a debugging program, the DDT command starts this program.

Related Commands

DEBUG	for loading your program along with a particular debugging program (e.g., FORDDT or COBDDT).
FORK	for selecting the current fork.
INFORMATION MEMORY-USAGE	for displaying the numbers of pages occupied by the program in memory.

Examples

1. Give the DDT command to begin debugging a program in the current fork in memory.

@DDT
DDT

DDT (Cont.)

2. Give the DEBUG command to debug a FORTRAN program; type a CTRL/C to return to TOPS-20 command level so you can find out the current load averages and number of jobs for the system. Return to your debugging program (FORDDT in this case) by giving the DDT command.

```
@DEBUG TESTF1
LINK: Loading
[LNKDEB FORDDT Execution]

STARTING FORTRAN DDT

>> ^C
@SYSTAT SYSTEM
Fri 20-Apr-79 13:50:01 Up 36:47:55
35+14 Jobs Load av (class 0) 0.72 0.81 1.33

@DDT

STARTING FORTRAN DDT

>> START

THIS IS A TEST.

END OF EXECUTION
CPU TIME: 0.04 ELAPSED TIME: 0.33
EXIT
@INFORMATION MEMORY-USAGE

66. pages, Entry vector loc 0 len 254000
0-12 Private R, W, E
400 Private R, W, E
401-466 <SUBSYS>FOROTS.EXE.3 3-70 R, CW, E

3. Display the programs in memory with the INFORMATION
   FORK-STATUS command. Then use the FORK command to make
   the CLIP program the new current fork. Verify this with
   INFORMATION FORK-STATUS and then merge the UDDT program
   with the CLIP program.

@INFORMATION FORK-STATUS
EMACS (1): Kept, HALT at 50340, 0:00:03.6
CLIP (2): Kept, HALT at 70363, 0:00:00.2
=> UNITS (3): HALT at 162, 0:00:00.9
@FORK CLIP
@INFORMATION FORK-STATUS
EMACS (1): Kept, HALT at 50340, 0:00:03.6
=> CLIP (2): Kept, HALT at 70363, 0:00:00.2
UNITS (3): HALT at 162, 0:00:00.9
@DDT
DDT
```


DEASSIGN

Releases a device from your job and places the device back in the pool of available devices.

Format

@DEASSIGN (DEVICE) dev:

where

dev: is the name of the device you want to deassign; an asterisk (*) deassigns all devices (except your log-in terminal) assigned to your job. The colon after the device name is optional.

Restrictions

Open Files

The DEASSIGN command will not deassign a device that is accessing an open file. An error is generated, and the device is not deassigned until that file is closed or until you log out. When you log out, all devices are deassigned.

Related Commands

ASSIGN	for assigning a particular device to your job
INFORMATION AVAILABLE DEVICES	for finding out which devices are available, and which ones have already been assigned to your job
MOUNT	for mounting a structure or magnetic tape and assigning the first available disk drive or tape drive to your job

DEASSIGN (Cont.)

Examples

1. Deassign a device (in this case a card reader).

@DEASSIGN PCDR0:

2. Find out which devices are assigned to your job, then deassign all of these. Verify that this was done. (Note that your terminal, in this case TTY222:, is never deassigned.)

@INFORMATION AVAILABLE DEVICES

Devices available to this job:

DSK, PS, SNARK, PACK, FTN20, MTA2, MT0, LPT, LPT0, LPT1
CDR, PCDR0, CDP, FE1-15, PTY15-61, NUL, PLT, PLT0, DCN
SRV

Devices assigned to/opened by this job: MTA2, MT0, PCDR0
TTY222, PTY15

@DEASSIGN *

@INFORMATION AVAILABLE DEVICES

Devices available to this job:

DSK, PS, SNARK, PACK, FNT20, MTA2, LPT, LPT0, LPT1
CDR, PCDR0, CDP, FE1-15, PTY15-61, NUL, PLT, PLT0
DCN, SRV

Devices assigned to/opened by this job: TTY222

DEBUG

Loads your program into memory along with a debugging program, compiling the source file first if necessary. Then it starts the debugging program.

Format

@DEBUG (FROM) /switch(es) source/switch(es) object,...

where

switches are keywords chosen from the list below, indicating your choice of DEBUG command options. They have different effects depending on their position in the command line: placed before all files in the command, they act as defaults for all; otherwise, they affect only the nearest preceding file.

Defaults are shown in the list of switches

source is the file specification of the source program. The filename must be of 6 or fewer characters, and the file type of 3 or fewer characters; you cannot use a generation number. This argument is not necessary if you supply an object filespec.

object is the file specification of the object program. The filename must be of six or fewer characters, and the file type must be .REL; you cannot use a generation number. This argument is not necessary if you supply a source filespec.

Default (if you give neither source nor object filespecs) - last filespecs and associated switches you gave in a LOAD-class command

,... means that, after commas, you can give more arguments (source, switches, and object) of the form already shown

Summary of DEBUG Command Switches (defaults in boldface)

	/10-BLISS
	/36-BLISS
	/68-COBOL
	/74-COBOL
	/ABORT
	/ALGOL
	/BINARY
	/COBOL
	/COMPILE
	/CREF
	/CROSS-REFERENCE
	/DDT

DEBUG (Cont.)

```
| /DEBUG
| /FAIL
| /FLAG-NON-STANDARD
| /FORTRAN
| /LANGUAGE-SWITCHES:"/switch(es) "
| /LIBRARY
| /LIST
| /MAC
| /MACHINE-CODE
| /MACRO
| /MAP
| /NOBINARY
| /NOCOMPILE
| /NOCREF
| /NOCROSS-REFERENCE
| /NODEBUG
| /NOFLAG-NON-STANDARD
| /NOLIBRARY
| /NOLIST
| /NOMACHINE-CODE
| /NOOPTIMIZE
| /NOSEARCH
| /NOSTAY
| /NOSYMBOLS
| /NOWARNINGS
| /OPTIMIZE
| /PASCAL
| /RELOCATABLE
| /SAIL
| /SEARCH
| /SIMULA
| /SNOBOL
| /STAY
| /SYMBOLS
| /WARNINGS
```

DEBUG Command Switches

```
| /10-BLISS      compiles the file using the BLISS-10 compiler.
|                Default for files of type .B10 and .BLI
|
| /36-BLISS      compiles the file using the BLISS-36 compiler.
|                Default for files of type .B36
|
| /68-COBOL      compiles the file using the COBOL-68 compiler.
|                Default for files of type .C68
|
| /74-COBOL      compiles the file using the COBOL-74 compiler.
|                Default for files of type .C74
|
| /ABORT         stops a compile if a fatal error is detected and
|                returns your terminal to TOPS-20 command level.
|
| /ALGOL         compiles the file using the ALGOL compiler.
|                Default for files of type .ALG
```

DEBUG (Cont.)

| /BINARY allows generation of an object (binary) file for
| each source file given.
| Default

| /COBOL compiles the file using the COBOL compiler,
| either COBOL-68 or COBOL-74, that your
| installation has stored in the file
| SYS:COBOL.EXE.
| Default for files of type .CBL

| /COMPILE forces compilation of the source file even if a
| current object file already exists. Use this
| switch along with a /LIST or /CREF switch to
| obtain listings when you have current object
| files.

| /CREF same as /CROSS-REFERENCE.

| /CROSS-REFERENCE creates a file containing cross-reference
| information for each compilation. The filename
| is that of the object file; the file type is
| .CRF. Use the CREF command to obtain a listing
| of the file. (For COBOL files, this switch
| automatically produces a cross-reference
| listing.) See the TOPS-20 User Utilities Guide
| for more information about the CREF program.

| /DDT loads the DDT debugging program along with your
| object file.

| /DEBUG produces an object file containing debugging
| information beyond what is usually inserted
| during compilation. (For FORTRAN programs only,
| and only if you have not given the /OPTIMIZE
| switch).

| /FAIL compiles the file using the FAIL compiler.
| Default for files of type .FAI

| /FLAG-NON-STANDARD indicates nonstandard syntax in file.

| /FORTRAN compiles the file using the FORTRAN compiler .
| Default in the absence of a standard source
| file type and a language switch
| Default for files of type .FOR

| /LANGUAGE-SWITCHES:"/switch(es)"
| passes the specified switches to the compiler
| that will process the file(s) to which this
| switch applies. You must include the switches
| in double quotation marks (" ").

| /LIBRARY same as /SEARCH.

DEBUG (Cont.)

/LIST	prints a line printer listing of the program in ASCII format; the name of this listing is the filename of the object file. The /CREF switch overrides /LIST when they both apply to the same file.
/MAC	same as /MACRO.
/MACHINE-CODE	produces a file containing the generated machine code. The filename is that of the object file; the file type is .LST. For high level languages. Default
/MACRO	assembles the files using the MACRO assembler. Default for files of type .MAC
/MAP	produces a loader map and stores it in the file object.MAP, where object is the name of the module containing the start address; or (if no start address) nnnLNK.MAP, where nnn is your job number.
/NOBINARY	prevents generation of an object (binary) file. Use this switch along with /LIST or /CREF to allow these switches to take effect without producing a new object file.
/NOCOMPILE	prevents compilation if the associated object file is current; otherwise it forces compilation. Cancels the /COMPILE or /RELOCATABLE switch. Default
/NOCREF	same as /NOCROSS-REFERENCE
/NOCROSS-REFERENCE	prevents the creation of a cross-reference file. Default
/NODEBUG	excludes special debugging information from your object file. (For FORTRAN programs only.)
/NOFLAG-NON-STANDARD	prevents a line printer listing of a cross-reference file. Default
/NOLIBRARY	same as /NOSEARCH.
/NOLIST	prevents a line printer listing of the program. Default
/NOMACHINE-CODE	prevents generation of a file containing machine code. Default

DEBUG (Cont.)

/NOOPTIMIZE	prevents the generation of a globally optimized object file (for FORTRAN programs only). Default
/NOSEARCH	requires all modules in the object file library (the file accompanied by this switch in the command line) to be loaded even if they are not called by your program. Cancels the /SEARCH switch. Default
/NOSTAY	stops the compiler from being placed in a background fork. Use when /STAY is set as a default for the compiler.
/NOSYMBOLS	prevents a symbol table from being loaded along with the object file.
/NOWARNINGS	prevents display of warnings for nonfatal errors.
/OPTIMIZE	calls for generation of a globally optimized object file, that is, one that runs as quickly as possible. (For FORTRAN programs only, and only if you do not also give the /DEBUG switch).
/PASCAL	compiles the file using the PASCAL compiler. Default for files of type .PAS
/RELOCATABLE	identifies the input file as an object file (regardless of its extension) and prevents compilation of the source file, forcing use of an existing object file even if the object file is out of date. Default for files of type .REL
/SAIL	compiles the file using the SAIL compiler. Default for files of type .SAI
/SEARCH	requires that the object file library (the file accompanied by this switch in the command line) be searched for modules called by your program or by a program subroutine. Only these modules are loaded, along with modules called from the system libraries, which are always searched.
/SIMULA	compiles the file using the SIMULA compiler. Default for files of type .SIM
/SNOBOL	compiles the file using the SNOBOL compiler. Default for files of type .SNO

DEBUG (Cont.)

| /STAY returns your terminal to TOPS-20 command level
| so that you can perform other work while the
| system continues executing the DEBUG command.
| You immediately receive the TOPS-20 prompt (@ or
| \$) and can then issue any user command. Be
| careful not to send incorrect data to programs
| expecting terminal input. (Refer to the
| CONTINUE command, Restrictions: Programs
| competing for terminal input.)

| This switch saves you from having to: issue a
| ^T to make sure the debugger has begun; give a
| ^C to halt debugging; and issue a CONTINUE /STAY
| command to remain at command level during
| debugging.

| /SYMBOLS loads a symbol table along with the object file;
| helpful for debugging a program.
| Default

| /WARNINGS displays warnings for nonfatal errors.
| Default

Characteristics

Compiling New Sources Only

Before debugging programs, the system ordinarily compiles any source (and only those sources) whose write date is more recent than that of the object file of the same name. You can override this action with the /COMPILE or /RELOCATABLE switch. Note that the DDT debugging program is used when /RELOCATABLE prevents a new compilation.

Default Switches Not Passed to Compiler

| Only switches specified in a LOAD-class command are passed
| to the compiler; default switches are not passed. Instead,
| the system assumes that the defaults for the compiler are
| the same as the defaults for the LOAD-class command.

Using Standard File Types

If you specify source files with standard types (.FOR, .MAC, .CBL, or .ALG) in a DEBUG command, the system automatically calls the appropriate compiler when compilation is necessary. If you specify source files by filename only, the system searches your connected directory in the above order for a file of this name and a standard type. To debug programs from sources that have nonstandard file types, give a switch to indicate the proper compiler (/FORTRAN, /MACRO, /COBOL, or /ALGOL). A switch will take precedence over a standard file type if they indicate different languages. If no compiler is indicated with either a switch or a standard file type, the FORTRAN compiler is used.

DEBUG (Cont.)

Name of Debugging Program Loaded by DEBUG

Ordinarily the DEBUG command causes the appropriate debugging program to be loaded along with your program (FORDDT with FORTRAN programs. COBDDT with COBOL programs, DDT with MACRO and ALGOL programs). Use the /DDT switch to specify that DDT be used.

Hints

Commas Between Filespecs

If you give two or more filespecs separated by commas as arguments to DEBUG, the loaded programs exist in memory at the same time and will act as a single program. You can use this feature to substitute one module for another under varying conditions or for different applications.

Plus Signs Between Filespecs

If you give two or more filespecs separated by plus signs (+) as arguments to DEBUG, they are treated as a single file by compilers. Their object module is stored under any filename given as the "object" argument of the command, or (if none) under the last filename in the group and file type .REL.

Indirect Files as Arguments

You can store the arguments (source and object filespecs, switches) of a DEBUG command in an indirect file, and specify them by typing an at sign (@) and its filespec as a DEBUG command argument.

Establishing Default Arguments with the SET Command

You can issue the SET DEFAULT COMPILE-SWITCHES command to set up default global arguments to the DEBUG command. Insert this SET command in your COMAND.CMD file to change your own defaults permanently.

Including all FORTRAN Debugging Information

If you are debugging a FORTRAN program and you wish to examine line numbers or DO loops, or use statement tracing or array dimension checking, give the /DEBUG and /COMPILE switches with the DEBUG command to include the necessary information.

Running LINK Directly

The DEBUG command automatically runs LINK, the system's loader program, but if you require control of the loading process you can run LINK directly. See the TOPS-20 LINK Reference Manual.

DEBUG (Cont.)

Wildcards Illegal with DEBUG

The DEBUG command does not accept wildcard characters (* and %) in a file specification.

Effect on Memory

The DEBUG command clears any unkept forks from memory, loads the appropriate compiler if necessary, then loads your program and a compatible debugging program.

Related Commands

COMPILE, LOAD, and EXECUTE	other LOAD-class commands for performing related functions
DDT	for loading and starting the DDT debugging program, or for starting the debugging program you have already loaded

Examples

1. Debug a FORTRAN program.

```
@DEBUG FORT.FOR
FORTRAN: FORT
MAIN.
LINK: Loading
[LNKDEB FOR DDT Execution]
STARTING FORTRAN DDT
```

>>

2. Debug a FORTRAN program using the /COMPILE switch to force compilation and the /DEBUG switch to generate additional debugging information.

```
@DEBUG /COMPILE /DEBUG FORT.FOR
FORTRAN: FORT
MAIN.
LINK: Loading
[LNKDEB FORDDT Execution]
STARTING FORTRAN DDT
```

>>

DEBUG (Cont.)

3. Using incompatible switches, try to debug a program. (The system ignores one of them and continues.)

```
@DEBUG/COMPILE/OPTIMIZE/DEBUG FORT
FORTRAN: FORT
%ERROR IS GLOBAL OPTIMIZATION NOT SUPPORTED WITH
/DEBUG - /OPT IGNORED
MAIN.
LINK: Loading
[LNKDEB FORDDT Execution]
```

STARTING FORTRAN DDT

>>

4. Get a time-ordered list of TEST1 files in your directory. Debug an old version of it.

```
@TDIRECTORY TEST1.*
WRITE

PS:<LATTA>
TEST1.CBL.2      5-Jan-85 13:10:57
.LST.1          6-Jan-85 14:22:00
.REL.1          6-Dec-84 10:08:17
```

Total of 3 files

```
@DEBUG TEST1/RELOCATABLE
LINK: Loading
[LNKDEB DDT Execution]
DDT
```

DEFINE

Establishes or cancels logical names for your job.

Format

@DEFINE (LOGICAL NAME) name: list

where

name: is any combination of up to 39 alphanumeric characters that you want to use as a logical name. Use an asterisk (*) for this argument to withdraw all logical names. The colon after the logical name is optional.

list is a series of devices, file structures, directories, file specifications, and/or other logical names; each item should be separated from the others by commas.

Default - not specifying a list withdraws the logical name definition

Characteristics

Colon Designates a Logical Name

Normally, when you give a logical name to an EXEC command in the place of a filespec, structure, or directory name, a colon must follow the logical name. However, for the DEFINE and INFORMATION LOGICAL-NAMES commands, where the argument can only be a logical name, a colon after the logical name is optional.

Hints

DEFINE in LOGIN.CMD File

Your DEFINE command is valid for the current terminal session only. If there are logical names that you always want to use, put DEFINE commands into a LOGIN.CMD (or, for batch jobs started by SUBMIT commands within the control files of other batch jobs, a BATCH.CMD) file in your log-in directory.

Redefining System Logical Names

You can use the DEFINE command to redefine any system logical name for your own job. By repeating a system logical name in its own search list you expand its definition to include the other items, in the order you specify. Consider the system logical name SYS:, which is searched whenever you give a program name in place of a TOPS-20 command. If you redefine SYS: to be str:<directory>, SYS: you can run programs in str:<directory> by typing just their names. This will work as long as the program names are not the same as TOPS-20 commands.

DEFINE (Cont.)

Logical Names as Dummy Filespecs

You can use logical names as dummies for filespecs or devices when writing programs. Then, just before running such a program, use the DEFINE command to define these as real filespecs or devices, without changing the program itself.

More Information

For more information about using logical names, see the TOPS-20 User's Guide.

Special Cases

Using Recognition in the Filespec

Normally, when you attempt to use recognition in a nonexistent filename, the system rings the terminal bell. However, for the DEFINE command, instead of ringing the terminal bell, the system may append part(s) of the default file specification, .0 or ..0, to the logical name definition. This is because DEFINE allows you to define a directory or filespec that may not yet exist.

Note that a logical name definition that includes .0 or ..0 may not work for your use of the logical name; it is recommended that you specify the complete directory name or filespec.

Restriction

Adding Comments to a DEFINE Command Line

You can add a comment to the end of any TOPS-20 command by preceding the comment with one of the comment characters: an exclamation point (!) or a semicolon (;). However, only the exclamation point can be used with the DEFINE command.

Using Short Logical Names Only

Although logical names can be up to 39 characters long and can include dollar signs (\$), hyphens (-), and underlines (_), some commands and programs (e.g., programs originally written for the TOPS-10 operating system) accept a more limited set of logical names. These can be no more than 6 characters long and cannot include any special symbols. If all your logical names are of this kind, they will be acceptable to any TOPS-20 programs and commands.

DEFINE (Cont.)

Related Commands

INFORMATION LOGICAL-NAMES for finding out the current definitions of logical names

Examples

1. Define a logical name for your job.

```
@DEFINE LGN: <MANUALS>, <SARTINI>
```

2. Withdraw the logical name.

```
@DEFINE LGN:
```

3. Define a logical name to be a set of directories to which you have access. Then use the logical name to copy a file from one of them into your connected directory.

```
@DEFINE MSM: <MANUALS>, <SARTINI>, <MCELMOYLE>
@COPY MSM:4-UPED.TXT
<MCELMOYLE>4-UPED.TXT.1 => 4-UPED.TXT.1 [OK]
```

4. Add one of your own directories to the definition of SYS: so that you can run .EXE files in that directory by typing just the program name.

```
@DEFINE SYS: SYS:,AURORA:<WHITING.TOOLS>
```

DELETE

DELETE

Marks a file(s) for eventual erasure.

Format

```
@DELETE (FILES) filespec,...,  
@@subcommand
```

where

filespec

is the specification of a file that you want to delete.

Default .gen - all generations of the specified files

,...

means that after commas you can give more file specifications

@@subcommand

means that after a final comma you can give one of the following subcommands:

DELETE Command Subcommands

ARCHIVE

both deletes the disk copy (if any) and gives up the tape copy of specified archived files.

CONTENTS-ONLY

deletes and immediately expunges only the disk copy of files that also have a tape copy. Note that you must use the RETRIEVE command, not UNDELETE, to restore such files to disk.

DIRECTORY

deletes and immediately expunges a subdirectory without making the disk space available to the files of other users. Subdirectories appear as files with the type .DIRECTORY in the immediately superior directory. For users with enabled Wheel or Operator capabilities only.

EXPUNGE

immediately and permanently erases the specified files from the directory.

FORGET

deletes and immediately expunges the specified files without making their disk space available to the files of other users; for users with enabled Wheel or Operator capabilities only.

DELETE (Cont.)

KEEP n saves the n most recent generations
 of the specified files while
 deleting the rest.
 Default n - 1

Output

Notice of Deleted Archived Files

Whenever an archived file is completely expunged as a result of your DELETE command (that is, when you also give the ARCHIVE subcommand), the operator sends a mail message notifying the owner of the directory from which the file was taken.

Characteristics

Privileged Subcommands to DELETE

The DIRECTORY and FORGET subcommands to the DELETE command are intended for privileged users only, and only as a last resort, because they withhold freed disk space from system use. Users with enabled Wheel or Operator capabilities can run the CHECKD program to recover this disk space. DIRECTORY should not be used unless the KILL subcommand to a BUILD command fails to delete the directory. FORGET is for removing damaged files from directories, and should not be used unless DELETE without subcommands fails to delete the file.

Hints

Removing Open Files

If DELETE with the EXPUNGE subcommand fails to erase a file, it may be that some job in the system has opened it. The INFORMATION FILE-STATUS command tells whether your own job has done so. If it has, give the CLOSE or (if the file is mapped) RESET command before repeating DELETE and EXPUNGE.

Recovering Deleted Archived Files

If you have given the DELETE command with the ARCHIVE subcommand to delete an archived file, and the disk copy has already been expunged, you may still be able to recover the tape copy. The operator will send a MAIL message (see Output, above) concerning the discarded tape copy of the deleted file. Use this information, along with Hints - Undoing DISCARD, in the DISCARD command description, to attempt recovery of the deleted file.

DELETE (Cont.)

Special Cases

Files With the "Permanent" Attribute

The system erases only the contents of any files that have the Permanent attribute (e.g., MAIL.TXT in your log-in directory) when you include them in a DELETE command. Their file specifications remain among your deleted files, and cannot be removed by TOPS-20 commands.

Restriction

Using Logical Names When Specifying Files for Deletion

If you include a logical name when specifying arguments to a DELETE command, the system will search for the specified file in only the first directory of the logical name's definition. This restriction prevents the accidental deletion of another file if the file you intended to delete has already been deleted.

Warning

Erasure of Deleted Files

Ordinarily an UNDELETE command given during the same terminal session as an original deletion will recover the deleted files, unless you included the EXPUNGE subcommand to DELETE or gave a subsequent EXPUNGE command. However, if any user or a batch job logs out while connected to your directory, all deleted files are permanently erased. Also, if available disk space is low on the system, the operator or the system itself may expunge all deleted files from a structure even though you have not logged out. A warning message is usually sent before this happens.

Related Commands

	DIRECTORY, with the	for displaying a list of deleted
	DELETED subcommand	files
	DISCARD	for giving up only the tape copy of
		on-line files
	EXPUNGE	for permanently removing deleted
		files
	INFORMATION DISK-USAGE	for finding out how much disk space
		is available, and how much is
		associated with deleted files
	UNDELETE	for recovering deleted files

DELETE (Cont.)

Examples

1. Delete two of your files.

```
@DELETE TTY.SCM, VERCBL.BAT
TTY.SCM.1 [OK]
VERCBL.BAT.2 [OK]
```

2. Delete all your object files and all your backup files produced by the EDIT program. Then log out (this will expunge them).

```
@DELETE *.REL, *.Q*
TESTA1.REL.1 [OK]
TESTF1.REL.1 [OK]
TESTC1.QBL.2 [OK]
TESTF1.QOR.4 [OK]
@LOGOUT
Killed Job 32, User J.L.PAGE, Account 341, TTY 41
at 25-Apr-84 10:15:51, Used 0:1:46 in 1:23:59
```

3. Delete some files, and check what files are currently deleted in your connected directory. Give the UNDELETE command for two of these, then expunge the remaining deleted files and verify that they are gone.

```
@DELETE *.QXT
4-UPED.QXT.7 [OK]
MAIL.QXT.1 [OK]
REMARK.QXT.3 [OK]
@DIRECTORY,
@@DELETED
@@
PS:<J.L.PAGE>
4-UPED.QXT.1,2,3,4,5,6,7
.TXT.7,8,9
MAIL.QXT.1
MEMO.QMD.1
REMARK.QXT.1,2,3
TTY.SCM.1
VERCBL.BAT.2
```

```
Total of 17 files
@UNDELETE TTY.SCM, VERCBL.BAT
TTY.SCM.1 [OK]
VERCBL.BAT.2 [OK]
@EXPUNGE
PS:<J.L.PAGE> [8 pages freed]
@DIRECTORY,
@@DELETED
@@
@
```

DEPOSIT

Modifies the contents of a specific memory location.

Format

```
@DEPOSIT (MEMORY LOCATION) address (CONTENTS) data
```

where

address is an octal number or a symbol

data is a symbolic or numerical expression

Output

Status of Pages

When you complete a DEPOSIT command, the system gives you a message indicating the status of the page you are trying to change: "[New]" for previously nonexistent pages, "[Shared]" for those having Copy-on-Write status, or "?Can't write that page" for other pages. (See also Hints - Setting the Page-access of Memory Pages, below.) However, no message is printed for deposits made to private pages.

Hints

Using Symbols

For symbols that are defined in multiple modules of a program, you can be specific by giving the module name followed by an ampersand (&) and the symbol name.

Using DDT Instead

Usually the DEPOSIT command is unnecessary, as the DDT program provides more powerful methods for modifying the contents of memory.

Abbreviating DEPOSIT Arguments

The contents of each memory location are represented as two 6-digit octal numbers. By inserting a pair of commas between these two numbers, you can abbreviate them. For example, to deposit 000004000050 into memory location 151003, use the command

```
@DEPOSIT 151003 4,,50
```

This is the same as

```
@DEPOSIT 151003 4000050
```

DEPOSIT (Cont.)

Note that you can also insert commas between expressions. For example, the command

```
@DEPOSIT 1 1+3,, 5+7
```

deposits 000004000014 into memory location 1. (Expressions are considered to be octal unless they contain an 8 or a 9, in which case they are considered to be decimal and are translated to octal.)

The DEPOSIT command itself can be abbreviated by the single letter D.

Deposit Address Defaults to the One Examined, and Vice Versa

The first argument of a DEPOSIT command defaults to the address examined by your most recent EXAMINE command. (You must press the ESCAPE key to take this default.) The argument of an EXAMINE command defaults to the address whose contents were modified by your most recent DEPOSIT command. Therefore you can examine a memory location, deposit a new value in it, and verify your action, while specifying the location only once. If you give DEPOSIT commands without intervening EXAMINE commands (or vice versa), the default address increases by 1 for each subsequent command.

Setting the Page-access of Memory Pages

If the system responds to a DEPOSIT command with an error message of the form, "?Can't write that page", give the SET PAGE-ACCESS COPY-ON-WRITE command for the page. Then give DEPOSIT again. If the system allows it, you will be given your own copy of the page to modify.

Using DEPOSIT With Inferior Processes

To modify memory for a process inferior to the one immediately below the TOPS-20 command processor, you must give the FORK command to specify this process before using DEPOSIT. Remember that for an inferior process to run, all superior processes must be running too. INFORMATION PROGRAM-STATUS tells you which processes these are.

Effect on Memory

The DEPOSIT command changes one location in memory.

Related Commands

DDT	for calling a debugging program, allowing more efficient modification of memory
EXAMINE	for displaying the contents of a specific memory location

DEPOSIT (Cont.)

FORK	for selecting the process whose memory you want to modify
INFORMATION MEMORY-USAGE	for displaying a list of memory pages, their contents and status
SET PAGE-ACCESS	for making it possible to write to specified pages

Examples

1. Deposit a value in a memory location.

```
@DEPOSIT 1500 21
```

2. Modify a memory location, using symbols. Then examine the location.

```
@DEPOSIT T3+1 P+2
@EXAMINE T3+1
T3+1/ P+2 (4/ 21)
```

3. Try to deposit a number into a page of memory that does not allow it. Examine memory, set the page to Copy-on-Write status, and try again (succeeding this time).

```
@DEPOSIT 716505 0
?Can't write that page
@INFORMATION MEMORY-USAGE
```

```
216. pages, Entry vector loc 462207 len 254000
```

Section 0	R, W, E, Private
0-11	Private R, W, E
20	Private R, W, E
400-401	Private R, W, E
402-660	<FIELD-IMAGE>FORTRA.EXE.3 13-271 R, CW, E
700-730	<NEXT-RELEASE>PAL050.EXE.4 1-31 R, E
731-733	Private R, W, E

```
@SET PAGE-ACCESS 716 COPY-ON-WRITE
@DEPOSIT 716505 0
[Shared]
@EXAMINE 716505
716505/ 0
```

DEPOSIT (Cont.)

4. Check your program status (the arrow [=>] indicates your current process [fork]). Select an inferior process, deposit a value into a memory location, and verify that memory for the superior process is not changed to this.

@INFORMATION PROGRAM-STATUS

Used 0:00:05 in 0:10:11

TOPS-20: 0:00:03.5

SET UUO-SIMULATION (FOR PROGRAM)

SET CONTROL-C-CAPABILITY (OF PROGRAM)

=> MACRO (1): ^C from IO wait at 775701, 0:00:00.3

Fork 2: HALT at 472052, 0:00:00.1

@FORK 2

@DEPOSIT 3500 12

@EXAMINE 3500

3500/ 12

@FORK 1

@EXAMINE 3500

3500/ 202200,,1136

DETACH

Disconnects your job from your terminal.

Format

@DETACH (AND) argument

where

argument

can be one of these:

CONTINUE - directs the current program to proceed, just as if you had typed the CONTINUE command

REENTER - reenters the current program, just as if you had typed the REENTER command

START - starts the current program, just as if you had typed the START command

Default - the program is left in its present state

Characteristics

Effects of Detached Jobs

Detached jobs use scarce system resources (e.g., swapping space, process slots, job slots) and can prevent new users from logging in.

Warning

Programs Writing to the Controlling Terminal (Device TTY:)

If a program running in a detached job attempts to write to device TTY:, the job will wait until it is again attached to a terminal.

Effect on Terminal

The DETACH command leaves your terminal detached from the system in the state before log-in.

DETACH (Cont.)

Related Commands

ATTACH	for joining a detached job to your terminal
SYSTAT	for finding out which jobs are detached
SUBMIT	for running independent jobs
UNATTACH	for disengaging another job from its terminal

Examples

1. Detach your job.

```
@DETACH
Detaching job # 16
```

2. Detach your job while starting the program in memory, then log in again.

```
@DETACH START
Detaching job # 45
```

```
BOSTON, TOPS-20 Development System, TOPS-20 Monitor 6.1(7)
@LOGIN LATTA 341
```

3. Log in and put a program in memory; detach the job while starting this program, and repeat the entire procedure. Log in a third time and begin execution of a third program. Interrupt this execution with CTRL/C, then detach this third job while continuing its program. Now you have three jobs running at once. Instead of logging in again, attach the first job (specifying the job number) and verify the system's action.

```
@LOGIN LATTA 341
Job 5 on TTY230 26-Mar-84 14:38:09, Last Login 26-Mar-84 11:36:12
```

```
@GET DMN
@DETACH START
Detaching job # 5
```

```
BOSTON, TOPS-20 Development System, TOPS-20 Monitor 6.1(7)
@LOGIN LATTA 341
Job 22 on TTY222 26-Mar-84 14:42:03, Last Login 26-Mar-84 14:38:09
```

```
@GET TESTA1
@DETACH START
Detaching job # 22
```

```
BOSTON, TOPS-20 Development System, TOPS-20 Monitor 6.1(7)
@LOGIN LATTA 341
Job 53 on TTY222 26-Mar-84 14:44:02, Last Login 26-Mar-84 14:42:03
```


DETACH (Cont.)

@EXECUTE TESTF1
FORTRAN: TESTF1
MAIN.
LINK: Loading
[LNKXCT TESTF1 Execution]
^C

@DETACH CONTINUE
Detaching job # 53

BOSTON, TOPS-20 Development System, TOPS-20 Monitor 6.1(7)
@ATTACH LATTA
?Job # required - LATTA has more than one detached job
@ATTACH LATTA 5
Password:

EXIT
@SYSTAT LATTA
5* 222 EXEC LATTA
22 DET TESTA1 LATTA
53 DET TESTF1 LATTA

DIRECTORY

Displays information about the files in a directory.

Format

```
@DIRECTORY (OF FILES) filespec,...,  
@@subcommand
```

where

filespec is the specification of a file about
 which you want information
 Default filespec - *.*.*

,... means that after commas you can give
 more file specifications

@@subcommand means that, after a final comma, you can
 give one or more subcommands on
 successive lines

Summary of DIRECTORY Command Subcommands (defaults in boldface)

ACCOUNT
ALPHABETICALLY
ARCHIVED
BEFORE date and/or time

CHECKSUM [BY-PAGES
 SEQUENTIALLY

CHRONOLOGICAL [WRITE
 CREATION
 READ
 TAPE-WRITE

COMPLETE
CRAM

DATES [WRITE
 CREATION
 OFFLINE-EXPIRATION
 ONLINE-EXPIRATION
 READ
 TAPE-WRITE

DIRECTORY (Cont.)

DELETED
DOUBLESPEACE
EVERYTHING
FIND number of generations Default number - 1
GENERATION-RETENTION-COUNT
HEADING
INVISIBLE
LARGER number of pages
LENGTH
LPT

NO [ACCOUNT
CHECKSUM
CRAM
DATES
DOUBLESPEACE
FILE-LINES
GENERATION-RETENTION-COUNT
HEADING
LENGTH
LPT
PROTECTION
REVERSE
SEPARATE
SIZE
SUMMARY-LINES
TIMES
USER

OFFLINE
ONLINE
OUTPUT filespec Default filespec - DIR.DIR
PROHIBIT-MIGRATION
PROTECTION
RESIST-MIGRATION
REVERSE
SEPARATE
SINCE date and/or time
SIZE
SMALLER number of pages

TIMES [WRITE
CREATION
OFFLINE-EXPIRATION
ONLINE-EXPIRATION
READ
TAPE-WRITE

USER [WROTE
CREATED

DIRECTORY (Cont.)

DIRECTORY Command Subcommands

ACCOUNT		prints the account to which storage fees for the files are charged
ALPHABETICALLY		lists the files in alphabetical order Default
ARCHIVED		restricts the listing to archived files only, visible and invisible, offline and online
BEFORE	date and time or day of week (or TODAY) and time	restricts listing to files last written before the date and time given
CHECKSUM	SEQUENTIALLY BY-PAGES	computes and prints 6-digit octal checksums for the files, either sequentially and without going beyond the EOF (end-of-file) mark, or by pages on disk, accounting for holes in files and pages beyond the EOF mark; output will be followed by letter P in this case. Default - BY-PAGES
CHRONOLOGICAL	CREATION WRITE READ TAPE-WRITE	lists files in order (oldest first) according to • date of creation, or • date they were last changed, or • date they were last read, or • date their tape copy was created, Default - WRITE
COMPLETE		prints the complete file specification, which includes the structure and directory names
CRAM		compresses formats to reduce printing space and time

DIRECTORY (Cont.)

DATES	<div>CREATION WRITE READ TAPE-WRITE OFFLINE-EXPIRATION ONLINE-EXPIRATION</div>	<p>lists for the specified files, the</p> <ul style="list-style-type: none">• date of creation, or• date they were last changed, or• date they were last read, or• date the tape copy was created, or• date of expiration Default - WRITE
DELETED		limits descriptions to deleted files that have not yet been expunged
DOUBLESPEACE		double-spaces the DIRECTORY command output
EVERYTHING		prints, in this order, the following information about the files - file specification; protection; account number; size in pages and in bytes (and associated byte size); generation retention count; date and time of creation, of last change (Write), last time read, and of the creation of any tape copy; the name of the user who created the file, and of the user who last wrote in the file.
FIND n		prints the specifications of all but the n most recent generations of the files, omitting any files having n or fewer generations Default n - 1
GENERATION-RETENTION-COUNT		tells the number of generations of each file the system will retain in the given directory
HEADING		prints a headline labeling each category of information supplied by the command Default
INVISIBLE		restricts the listing to invisible files only, both on-line and off-line
LARGER n		lists only files of size greater than n pages

DIRECTORY (Cont.)

LENGTH	gives the file length in bytes and the associated byte size
LPT	directs the command output to LPT: instead of to your terminal
NO	<div> <div> ACCOUNT CHECKSUM CRAM DATES DOUBLESPEACE FILE-LINES GENERATION-RETENTION-COUNT HEADING LENGTH LPT PROTECTION REVERSE SEPARATE SIZE SUMMARY-LINES TIMES USER </div> <div> suppresses the action or information associated with the specified subcommand. (FILE-LINES refers to the information pertaining to the individual files, which is the bulk of the DIRECTORY command output. SUMMARY-LINES refers to the information following the file lines, giving a total file-count, and total page-count and total checksum if required by subcommands.) Default - HEADING </div> </div>
OFFLINE	restricts the listing to (visible) off-line files only, both archived and not archived
ONLINE	restricts the listing to on-line files
OUTPUT filespec	directs the command output to the specified file rather than to your terminal Default filespec - DIR.DIR
PROHIBIT-MIGRATION	restricts the listing to files that are never migrated, because they were specified in a SET FILE PROHIBIT command
PROTECTION	prints the protection code (protection number) of the file
RESIST-MIGRATION	restricts the listing to files that the system considers last for migration. These files were specified in a SET FILE RESIST command.
REVERSE	causes an ordering subcommand, such as ALPHABETICALLY or CHRONOLOGICAL, to arrange its output in reverse

DIRECTORY (Cont.)

SEPARATE	lists the complete specification for each file on a separate line (instead of listing successive generation numbers of the file on the same line, separated by commas; and instead of listing files of the same name and different type by file type only, indented under the first complete file specification)
SINCE date and time or day of week (or TODAY) and time	limits listing to files last written after the date (or day of week) and time given
SIZE	prints the size of the files in pages
SMALLER n	lists only files of size less than n pages
TIMES <div>CREATION WRITE READ TAPE-WRITE OFFLINE-EXPIRATION ONLINE-EXPIRATION</div>	<p>lists, for the specified files, the</p> <ul style="list-style-type: none">• time and date of creation, or• time and date they were last changed, or• time and date they were last read, or• time and date the tape copy was created, or• time and date of expiration <p>Default - WRITE</p>
USER <div>CREATED WROTE</div>	<p>gives the name of the user who</p> <p>created the file, or</p> <p>changed the file last</p> <p>Default - WRITE</p>

Hints

Listing Unneeded Files

In preparation for deleting files so that your directory will fall within disk quotas, you can get a list of your largest files by using the LARGER and/or SIZE subcommands, and of your oldest or least-used files with DATES, TIMES, and BEFORE. With FIND you can discover extra generations of files.

DIRECTORY (Cont.)

Finding Files of a Particular Age or Size

To examine only files of a certain age or size, give the pair of subcommands BEFORE and SINCE, or LARGER and SMALLER, with appropriate arguments.

Comparing Checksums of Files

You can use the numbers reported by the CHECKSUM subcommand to compare two files: if they have differing contents they will almost certainly yield different values; and identical files will have the same checksums. The CHECKSUM subcommand causes a checksum of checksums as well.

Special Cases

Asterisks Appearing Before Filespecs

An asterisk (*) appearing before a filename in the response to a DIRECTORY command indicates a possible hardware-related error, one caused by a read operation at a marginally functional area of disk. To test whether there actually is an error in the file, use the COPY command to copy the file to a new specification. If the COPY command succeeds, there is no error in the file, and no asterisk will precede the new file specification. If the COPY command fails, you should move the disk to another drive and repeat the command. If it still fails, you may have to write your own program to recover everything but the missing part of the file (usually, just one page).

DIRECTORY-class Commands for Labeled Magnetic Tapes

The FDIRECTORY, TDIRECTORY, and VDIRECTORY commands for labeled magnetic tapes are equivalent to the DIRECTORY command for labeled magnetic tapes. All these commands rewind the tape set to the beginning of the first volume, print a directory of files, then rewind the set again. You can give only these subcommands when using DIRECTORY-class commands with labeled magnetic tapes: ALPHABETICALLY, DOUBLESPEACE, HEADING, LPT, NO, OUTPUT, REVERSE, and SEPARATE.

Related Commands

FDIRECTORY (Full DIRECTORY)] other DIRECTORY-class commands for performing related functions
TDIRECTORY (Time-ordered DIRECTORY)	
VDIRECTORY (Verbose DIRECTORY)	

DIRECTORY (Cont.)

Examples

1. Obtain a listing of your files.

@DIRECTORY

```
PS:<HERRICK>
4-UPED.TXT.13
ACCT20.FOR.1
DUMPER.MAC.1
F-O.DIRECTORY.1
FORD.CTL.2,3,4,5,6
MEMO.CMD.1
.FIL.1
.FRM.2
MULTIP.FOR.2
```

Total of 13 files

2. Use a DIRECTORY command with a filespec consisting of wildcard characters and the account attribute (;A) to find out which files' storage fees are being charged to account MONITOR.

@DIRECTORY *.*;AMONITOR

```
PS:<HERRICK>
FORD.CTL.2
MEMO.FRM.2
```

Total of 2 files

3. Find out what files of type .TXT there are in your connected directory and in one to which you have group rights.

@DIRECTORY *.TXT, <SARTINI>*.TXT

```
PS:<HERRICK>
4-UPED.TXT.13
MAIL.TXT.1
REMARK.TXT.4
```

Total of 3 files

```
PS:<SARTINI>
CHAP21.TXT.33
CHAPT2.TXT.16
CHAPT3.TXT.8
PRIVATE.TXT.1
TEST.TXT.1
```

Total of 5 files

Grand total of 8 files

DIRECTORY (Cont.)

4. Give a DIRECTORY command with the BEFORE and SINCE subcommands to find out which files were changed during the week of March 6, 1979.

```
@DIRECTORY,  
@@BEFORE 3-12-85  
@@SINCE 3-5-85  
@@
```

```
PS:<HERRICK>  
DIVIDE.FOR.4  
MULTIP.FOR.2  
QUOTNT.EXE.1  
SQUARE.EXE.1
```

Total of 4 files

5. Give the DIRECTORY command to list all the files in a directory that you have access to.

```
@DIR WORK:<HERRICK>
```

```
WORK:<HERRICK>  
CALENDAR.TXT.26  
COMAND.MIC.3  
QUERY.DAVE.1  
    .GENE.2  
RESULT.SCM.1  
WEEKLY.STA.15
```

Total of 6 files

DISABLE

Disables any special capabilities, such as those of Wheel or Operator, that you have enabled.

Format

```
$DISABLE (CAPABILITIES)
@
```

Characteristics

Resumption of Standard Prompt

The DISABLE command causes the system to resume the standard at sign prompt (@) in place of the dollar sign prompt (\$), which indicated enabled capabilities.

Warning

Disabling Promptly

Be sure to disable your capabilities as soon as you have finished using them, so that you or a program you run cannot accidentally damage the system.

Related Commands

ENABLE for activating any capabilities that the system manager has given you

Examples

1. Disable your capabilities.

```
$DISABLE
@
```

2. Try copying a file from a directory to which you have no access. Then enable your capabilities (assuming you have been granted capabilities), copy the file, and give up your capabilities with the DISABLE command.

```
@COPY <MON-SPCS>FFE.SPC
?Directory access privileges required
@ENABLE
$COPY <MON-SPCS>FFE.SPC
<MON-SPCS>FFE.SPC.1 => FFE.SPC.2 [OK]
$DISABLE
@
```

DISCARD

Gives up the tape copy of specified on-line files.

Format

@DISCARD (TAPE INFORMATION FOR FILES) filespec,...

where

filespec is the specification of a file
whose tape copy you want to discard

,... means that after commas you can
give more file specifications.

Characteristics

Action of DISCARD

| The DISCARD command causes the tape pointer in the FDB (File
| Descriptor Block) of the specified file to be deleted. It
| does not actually destroy the tape copy of the file. The
| tape copy is destroyed when the tape is recycled by the
| operator. (See also Hints - Undoing DISCARD, below.)

Withdrawing Archive Status of Files

When you give the DISCARD command for an on-line archived
file, you withdraw archive status from the disk copy of the
file. That is, the file becomes an ordinary disk file,
which you can edit or delete if you wish.

DISCARD for Non-archived Files

You can also use the DISCARD command to give up the tape
copy of files that have been migrated to tape
(automatically, by the system) and then retrieved using the
RETRIEVE command.

Hints

Undoing DISCARD

You receive a mail message from the operator for every file
whose tape copy you discard. The message gives the tape
number, saveset number, and file number within the saveset
of each tape copy. If you have given the DISCARD command
for a file and later wish to use the tape copy, you may be
able to recover it using this information, as long as the
tapes have not yet been recycled.

DISCARD (Cont.)

Related Commands

ARCHIVE	for requesting that a permanent tape copy of specified files be made
DELETE (with CONTENTS-ONLY subcommand)	for deleting only the disk copy of files that also have a tape copy
RETRIEVE	for requesting that an off-line file be restored to disk

Examples

1. Discard the tape copy of a file.

```
@DISCARD TESTER.EXE  
TESTER.EXE.1 [OK]
```

2. Attempt to alter an archived file. When you find out it has archive status, discard its tape copy (this revokes its archive status) and perform the alteration. Archive the resulting file and check its status.

```
@APPEND FOO.LOG DRCHIVE.TXT  
FOO.LOG.1  
?File has archive status, modification is prohibited: DRCHIVE.TXT.1  
@DISCARD DRCHIVE.TXT  
DRCHIVE.TXT.1 [OK]  
@APPEND FOO.LOG DRCHIVE.TXT  
FOO.LOG.1 [OK]  
@ARCHIVE DRCHIVE.TXT  
DRCHIVE.TXT.1 [Requested]  
@INFORMATION ARCHIVE-STATUS DRCHIVE.TXT  
DRCHIVE.TXT.1 Archive requested
```

DISMOUNT

Gives up access to the specified structure or tape set.

Format

@DISMOUNT medium (NAME) dev: /switch(es)

where

| medium is one of the following optional arguments:

STRUCTURE - for dismounting file structures (disk packs)

TAPE - for dismounting magnetic tapes

| dev: is either the structure identification (or alias), or a logical name referring to the tape set, e.g., the tape setname specified in your previous MOUNT command, or a logical device name of the form MTn:. The colon after the device name is optional.

| /switches are keywords, chosen from the list below, indicating your choice of DISMOUNT command options

DISMOUNT Command Switches
(for use with argument STRUCTURE only)

Switch

/NOWAIT tells the system to return your terminal to TOPS-20 command level as soon as you give the DISMOUNT command, and to send a message to your terminal when the request has been processed. Otherwise, your terminal waits for the message.

DISMOUNT (Cont.)

Switch

`/REMARK:"remark"`

sends the specified remark (of 119 or fewer characters, which must be enclosed in quotation marks [" "]) to the operator when he is notified of your request. The remark is sent only if you also include the `/REMOVE` switch.

`/REMOVE`

tells the operator that you want him to physically dismount the structure from the drive; makes the structure unavailable for further mount requests. See also Hints - Action of DISMOUNT Command Including `/REMOVE` Switch, below.

`/STRUCTURE-ID:structure identification`

gives the name of the structure as recorded in the disk(s); used when you give some alias as argument `dev:`, above. See Hints - Using the `/STRUCTURE-ID` Switch, below.

Characteristics

Action of DISMOUNT STRUCTURE Command

Ordinary DISMOUNT STRUCTURE

The DISMOUNT STRUCTURE command reduces by 1 the mount count of the specified structure (i.e., the number of users who have given a MOUNT but not a DISMOUNT command for the structure) if you had given a previous MOUNT command for it. An ordinary DISMOUNT STRUCTURE command does not withdraw the structure from system use.

DISMOUNT (Cont.)

Including /REMOVE Switch

If you include the /REMOVE switch when giving the DISMOUNT STRUCTURE command, the specified structure is made unavailable for further mount requests. The operator is informed of your dismount request, and any further action depends on him. If he denies your request, the structure is again made available to other users; if he grants your request, the structure remains unavailable for further mount requests, and is taken off line and physically removed. Under extreme conditions the operator may take a structure off line and physically remove it even though some users have not dismounted the structure. Before doing so, he will usually send a message to such users to allow them to close their files.

Action of DISMOUNT TAPE Command

The DISMOUNT TAPE command unloads the currently mounted volume of the specified tape set (i.e., rewinds it completely onto its source reel) so that it can be physically removed by the operator, and returns the tape drive to the pool of available resources. (Note that if the /NOUNLOAD switch was given in your original MOUNT command, no volumes are unloaded by the system or removed by the operator, even after your DISMOUNT command is completed.) If a logical name (e.g., the setname of the tape set) is used in the DISMOUNT command to specify the tape set, the system also withdraws the definition of the logical name. Use DISMOUNT TAPE only for tape drives having device names of the form MTn:, i.e., drives obtained using the MOUNT command. Use UNLOAD to unload tapes from drives having device names of the form MTAn:.

Hints

Omitting "medium" Argument

If the dev: argument of your DISMOUNT command will be unambiguous (i.e., you do not have both a structure and a tape set mounted using the same device name), you need not specify the medium. The shortened command, DISMOUNT dev:/switch(es), is sufficient.

Using the /STRUCTURE-ID Switch

The /STRUCTURE-ID switch gives the name of the structure as recorded in the disk(s) of the pack itself, where it is used by the system for identification. You may use this switch to dismount a structure that had been mounted using an alias different from its structure identification. (See Hints - Using the /STRUCTURE-ID Switch, in the MOUNT command description.)

DISMOUNT (Cont.)

Using INFORMATION VOLUMES before DISMOUNT TAPE

If you give the INFORMATION VOLUMES command before dismounting a tape set, the system will respond with a list of the volids for mounted volumes, including volids for any volumes newly added to the set. You should keep an up-to-date record of these for use with further MOUNT commands.

Effect on Terminal

The DISMOUNT command with the /NOWAIT switch, leaves your terminal at TOPS-20 command level. If you have not given the /NOWAIT switch, your terminal waits until the system has processed your request, or until you give a CTRL/C to return to TOPS-20 command level. This CTRL/C does not cancel your request.

Related Commands

CANCEL for withdrawing mount requests before they are processed

INFORMATION AVAILABLE DEVICES
 for finding which tape devices (if any) have been assigned to your job

INFORMATION MOUNT-REQUESTS
 for finding out information about pending mount requests for structures and tape sets, and currently mounted tape sets

INFORMATION STRUCTURE
 for finding out information about the specified mounted structure, including its mount count and the names of users who have given the MOUNT, CONNECT, and ACCESS commands for the structure

INFORMATION VOLUMES
 for finding out the volids of all mounted volumes (including newly created volumes) of a tape set

DISMOUNT (Cont.)

Examples

1. Dismount a magnetic tape set you have been using.

```
@DISMOUNT TAPE MT3:  
[Tape dismounted]
```

2. Dismount the same tape set, referring to it by its setname.

```
@DISMOUNT TAPE LAT:  
[Tape dismounted, logical name LAT: deleted]
```

3. Find out the volids of your tape set before dismounting it, in case the tape set has been extended to another volume.

```
@INFORMATION VOLUMES MT3:  
Volumes of tape set LAT: LAT,00J16  
@DISMOUNT MT3  
[Tape dismounted]
```

4. Find out if you have any mount requests pending or any currently mounted tape sets. Dismount a currently mounted tape set (these display the actual device name (here, MTA0) in the column headed, Status).

```
@INFORMATION MOUNT-REQUESTS/USER
```

```
Tape/Disk Mount Queue:  
Volume      Status  Type    Write   Req Name  Req#   Job#   User  
-----  
UNLBLD      MTA0    Tape    Locked  UNLBLD    128    55     LATTA  
There is 1 Request in the Queue  
@DISMOUNT TAPE UNLBLD:  
[Tape dismounted, logical name UNLBLD: deleted]
```

5. Dismount a structure you have mounted named SNARK.

```
@DISMOUNT SNARK  
Structure SNARK: dismounted
```

DISMOUNT (Cont.)

- Find out whether your mount request for a structure has been satisfied yet (it has not). Use the CANCEL command to withdraw this request.

@INFORMATION MOUNT-REQUESTS

Tape/Disk	Mount Queue:						
Volume	Status	Type	Write	Req Name	Req#	Job#	User
MARK	MTA1	Tape	Enabled	MARK	126	60	HOVSEPIAN
TAPE	MTA3	Tape	Enabled	TAPE	148	13	WALLACE
LATB	Waiting	Disk		LATB	157	65	LATTA

There are 3 Requests in the Queue

@CANCEL MOUNT 157
[1 mount request canceled]

- Find out whether you can safely dismount and remove a structure you have mounted. Use the SEND command to ask another user to dismount the structure; then enable your capabilities and give a DISMOUNT command that will physically remove it.

@INFORMATION STRUCTURE LATB:

Status of structure LATB:
Mount count: 2, open file count: 0, units in structure: 1
Foreign

Users who have MOUNTed LATB: LATTA, GBLAINE

Users ACCESSing LATB: LATTA, GBLAINE

No users CONNECTed to LATB:

@SEND GBLAINE PLEASE DISMOUNT LATB: AS SOON AS CONVENIENT. -
I MUST REMOVE THE STRUCTURE. THANKS.

@INFORMATION STRUCTURE LATB:

Status of structure LATB:
Mount count: 1, open file count: 0, units in structure: 1
Foreign

Users who have MOUNTed LATB: LATTA

Users ACCESSing LATB: LATTA

No users CONNECTed to LATB:

@END-ACCESS LATB:<OPERATOR>

@ENABLE

\$DISMOUNT STRUCTURE LATB: /REMOVE/REMARK:"PLEASE LEAVE LATB: -
ON RP06 CABINET"

[Mount Request LATB Queued, Request-ID 164]

Structure LATB: removed

\$DISABLE

@

EDIT ¹

Invokes your defined editor to modify a file.

Format

@EDIT (FILE) /switch(es) input filespec (OUTPUT AS) output filespec

where

switches are keywords, chosen from the list below, indicating your choice of EDIT command options

Defaults are shown in the list of switches

input filespec is the specification of the file you want to edit

Default - last file specification and associated switches you gave in a CREATE or EDIT command during the current terminal session

output filespec is the specification with which you want to name the edited file

Default - the input file specification, but with a generation number 1 higher than the highest existing generation number

Summary of EDIT Command Switches (Defaults in boldface)

NOTE

These switches are applicable only if you are using the EDIT editor.

/BAK
/C128
/C64
/DECIDE
/DPY
/EXPERT
/INCREMENT:n Default n - 100
/ISAVE:n
/LOWER
/M33
/M37
/NOBAK
/NODECIDE
/NONSEPARATORS
/NONUMBER
/NOVICE
/NUMBER
/OLD

¹ This manual assumes that you are using the EDIT program to edit. Refer to the Special Cases section below for information relating to other editors.

EDIT (Cont.)

/OPTION:name	
/PLINES:n	Default n - 16
/R	
/READONLY	
/RONLY	
/RUN:filespec	Default file type - .EXE
/SAVE:n	
/SEPARATORS	
/SEQUENCE	
/START:n	Default n - argument of INCREMENT switch
/STEP:n	Default n - 100
/UNSEQUENCE	
/UPPER	
/WINDOW:n	Default n - 10

EDIT Command Switches

/BAK	causes an unedited copy of the file to be saved at the end of an editing session under the specification name.Qyp, where name.typ is the file's original specification Default
/C128	specifies a 128-character alphabet, allowing insertion of control characters in an alternate format. See the <u>TOPS-20 EDIT Reference Manual</u> for details.
/C64	specifies a 64-character alphabet, disallowing use of an alternate format for insertion of control characters Default
/DECIDE	lets you decide whether to accept or reject each change caused by the operation of the S (substitute) command of the EDIT program
/DPY	has no effect in the current monitor
/EXPERT	tells the EDIT program that you need only abbreviated error messages, and fewer warnings and reminders
/INCREMENT:n	specifies the value that will be added to each line number of the file to obtain the next line number Default n - 100
/ISAVE:n	instructs the EDIT program to update the backup file of specification name.Qyp after every n lines you insert, instead of only at the end of the EDIT session
/LOWER	specifies that all alphabetic characters you type should be considered lowercase characters; give uppercase characters by preceding the corresponding lowercase character with a single quotation mark (').

EDIT (Cont.)

/M33	has no effect in the current monitor
/M37	has no effect in the current monitor
/NOBAK	prevents an unedited copy of the file from being saved at the end of an editing session under specification name.Qyp, where name.typ is the file's original specification
/NODECIDE	ensures the automatic operation of the S (substitute) command of the EDIT program Default
/NONSEPARATORS	notifies the EDIT program that the characters . (period), \$ (dollar sign), and % (percent sign) are to be regarded as ordinary textual characters and not as field delimiters (separators) in the file being edited Default
/NONUMBER	suppresses the printing of line numbers with each line of a file
/NOVICE	tells the EDIT program that you want to see complete error messages and all appropriate warnings and reminders; opposite of /EXPERT switch. Default
/NUMBER	prints a line number for each line of the file Default
/OLD	causes the first backup file to be saved under the specification name.Zyp, where name.typ is the file's original specification
/OPTION:name	sets any EDIT switches contained in lines of your SWITCH.INI file labeled with name (of six or fewer characters). The system expects this file to be in your log-in directory.
/PLINES:n	specifies how many lines to print in response to each P (print) command of the EDIT program Default n - 16
/R	same as /READONLY
/READONLY	prevents any changes to the file during the current session of the EDIT program, that is, makes it a read-only session. This switch cannot be given in the SWITCH.INI file.
/RONLY	same as /READONLY
/RUN:filespec	specifies the program to be run when you end the current session of the EDIT program with the G command Default file type - .EXE

EDIT (Cont.)

/SAVE:n	instructs the EDIT program to update the backup file of specification name.Qyp after every n EDIT program commands that modify the file
/SEPARATORS	notifies the EDIT program that the characters . (period), \$ (dollar sign), and % (percent sign) are not ordinary textual characters but are field separators in the accompanying file
/SEQUENCE	tells the EDIT program not to strip the line numbers from the file when the EDIT session ends Default
/START:n	specifies the first line number for the EDIT program to use when numbering the file Default n - argument of /INCREMENT switch
/STEP:n	same as /INCREMENT
/UNSEQUENCE	tells the EDIT program to strip the line numbers from the file when the EDIT session ends
/UPPER	specifies that all alphabetic characters you type should be considered uppercase characters; give lowercase characters by preceding the corresponding lowercase character with a single quotation mark ('). Default
/WINDOW:n	specifies the number n (between 10 and 99) of pages to be held in memory during the EDIT session Default n - 10

Characteristics

Edit Mode or Input Mode

The EDIT command runs the EDIT system program in Edit mode, which uses an asterisk prompt (*). (However, see also Special Cases - Using an Editor Other than EDIT, below.) In Edit mode you can use any EDIT program commands to modify the specified file. If the EDIT program starts by printing the word Input instead of Edit, the specified file does not yet exist. You are then in Input mode, just as if you had used the CREATE command instead of EDIT. See the CREATE command description for details.

EDIT (Cont.)

Saving Backup Files Periodically

Whenever you use EDIT, be sure to keep an extra copy of the file you are modifying, in case of a system failure. By default the system renames the unedited copy of your file to name.Qyp at the end of an editing session. By using the /SAVE:n switch you can have this backup file updated periodically during the editing session to reflect your edits.

SWITCH.INI File

If there is a group of EDIT command switches that you always or often use with EDIT or CREATE commands, put them into a file named SWITCH.INI in your log-in directory, in a line of that file beginning with "EDIT:abc", where abc is any set of characters you choose to identify the line. Then if you include the single switch /OPTION:abc when you give an EDIT or CREATE command, all these switches will be in effect.

Hints

Debugging Your Programs and Editing the Sources

You can use EDIT to modify files containing source programs written in a programming language. The DDT and DEBUG commands run system programs that offer more efficient and powerful techniques for testing temporary corrections to your programs, but you should use the EDIT command to make final changes to the source files.

Further Information

For more information about the EDIT program, see the TOPS-20 EDIT Reference Manual.

Special Cases

Using an Editor Other than EDIT

The CREATE, EDIT, and PERUSE command descriptions in this manual assume that these commands call on the EDIT program for their action. If your job uses another editing program, for example EDT, the switches and examples shown here will not be applicable.

The editor used by CREATE, EDIT, and PERUSE is specified by logical name EDITOR:, so you can find out the name of this program by giving the command, INFORMATION LOGICAL-NAMES EDITOR:. The job-wide definition (if any) will be given first, followed by the system-wide definition; the job-wide definition prevails if both exist. If the definition of EDITOR: is SYS:EDIT.EXE, the CREATE and EDIT commands will function as described in this manual. Otherwise, you must consult the appropriate manual (for example, the EDT-20 Reference Manual) for information.

EDIT (Cont.)

You can use the DEFINE command to define logical name EDITOR: to be any editing program available at your installation. Then this program will be in effect when you give the CREATE or EDIT command.

Attempting to Edit Archived Files

If you attempt to edit an on-line archived file, the system will let you produce an edited version of the archived file, but will retain the original (archived) file unchanged under the specification name.Qyp (or name.Zyp if you included the /OLD switch in the EDIT command), where name.typ is the file's original specification. See also Hints - Editing Files of Type .Qyp, below.

Editing Files of Type .Qyp

If you edit a file of type .Qyp (i.e., any file whose type begins with the letter Q), the EDIT program does not save the unedited copy as a backup file. In such cases, give the /OLD switch to retain the unedited copy under file type .Zyp. If the file of type .Qyp is an archived file, you will not be allowed to produce an altered version using the EDIT command unless you include the /OLD switch.

Effect on Memory

| The EDIT command clears any unkept forks from memory, then loads
| the editor program defined by the logical name EDITOR:.

Related Commands

CREATE	for creating new files
DIRECTORY-class commands	for getting lists of existing files
PERUSE	for editing files in read-only mode

Examples

1. Edit a file.

```
@EDIT FILE.FOR
Edit: FILE.FOR.1
*
```

2. Edit a file using the EDIT editor, requesting that an updated copy of the file be saved after every three EDIT program commands; ask that the first such backup file be saved under specification FILE.ZOR.

```
@EDIT /SAVE:3/OLD FILE.FOR
Edit: FILE.FOR.1
*
```

EDIT (Cont.)

3. Edit a large text file, adjusting several EDIT program parameters as you begin, and give new specifications for the output file.

```
@EDIT /EXPERT/DECIDE/PLINES:50/WINDOW:99 REMARK.TXT REVISION.TXT  
Edit: REMARK.TXT.18  
*
```

4. Use the EDIT editor to create a SWITCH.INI file with one line for the switches used in Example 2, and one line for those in Example 3. Use this file to repeat Example 3.

```
@CREATE SWITCH.INI  
Input: SWITCH.INI.1  
00100 EDIT:ABC/SAVE:3/OLD  
00200 EDIT:DEF/EXPERT/DECIDE/PLINES:50/WINDOW:99  
00300  
*E  
_
```

```
[SWITCH.INI.1]  
@EDIT /OPTION:DEF REMARK.TXT REVISION.TXT  
Edit: REMARK.TXT.18  
*
```

ENABLE

Enables any special capabilities you may have.

Format

```
@ENABLE (CAPABILITIES)
$
```

Characteristics

Dollar Sign Prompt

The ENABLE command causes the system to print a dollar sign prompt (\$), indicating enabled capabilities, in place of the standard at sign prompt (@). The dollar sign prompt is printed after ENABLE even if you have not been granted any capabilities.

Capabilities of Log-In Directory Only

The ENABLE command activates only those capabilities that have been granted to the owner of your log-in directory. You do not receive any capabilities as a result of CONNECT or ACCESS commands or group memberships.

Hints

Displaying Capabilities

Capabilities are defined by your login directory but are a characteristic of your job and can be enabled in any directory to which you connect. To list your capabilities, give the INFORMATION DIRECTORY command for your login directory.

More Information

Capabilities are assigned with the BUILD command. See the BUILD command subcommands in this manual for brief descriptions of special capabilities.

Special Cases

Dollar Sign Prompt in Batch Jobs

Because a dollar sign placed in the location of a TOPS-20 prompt could be confused with a batch command, the system precedes the enabled prompt with a space for batch jobs.

ENABLE (Cont.)

Capabilities Changed While Logged In

Capabilities are given to your job when you log in. If your capabilities are changed while you are logged-in, you must log out and log in again for the change to take effect.

Warning

Disabling Capabilities Promptly

Because your commands are much more powerful if you have capabilities enabled, you should disable them as soon as you have finished using them. Otherwise you or a program that you run could accidentally damage the system.

Related Commands

DISABLE	for suspending any capabilities that the system manager has given you
INFORMATION DIRECTORY (for the login directory)	for finding out which capabilities, have been granted to you.

Examples

1. Enable your capabilities.

```
@ENABLE
$
```

2. Try to assign a plotter to your job before taking it off line for repairs. But it is already assigned to another user, whose terminal is set to refuse links. Enable your capabilities and ask him to deassign the plotter. Then disable capabilities.

```
@ASSIGN PLT2:
?PLT2: Already assigned to job 29
@SYSTAT 29
  29      53  EXEC      R.SCHNEIDER
@TALK R.SCHNEIDER
?Refused, send mail to the user instead
@ENABLE
$TALK R.SCHNEIDER

LINK FROM F.DOMINO, TTY 221
$;ROBIN - PLEASE DEASSIGN PLT2:. IT MUST BE TAKEN OFF LINE
$;FOR MAINTENANCE. USE PLT3: INSTEAD. THANKS.
@;OKAY, SURE.
@DEASSIGN PLT2:
@
$BREAK
$DISABLE
@
```

END-ACCESS

Terminates your ownership rights to an accessed directory, as well as group rights borrowed from its owner.

Format

@END-ACCESS (TO DIRECTORY) dev:<directory>

where

dev:<directory> is the directory to which you want to end access

Default dev: - your connected structure

Default <directory> - the directory (on the specified structure) of the same name as your connected directory

Hints

Implicit END-ACCESS

You can access only one directory at a time on each mounted structure. Each ACCESS command ends access obtained by any previous ACCESS command for a directory on the specified structure. Therefore you do not need to give the END-ACCESS command if you access another directory on the structure, or if the structure is dismounted.

Restoring Previous Rights

END-ACCESS does not restore owner and group rights obtained by a previous ACCESS command for the specified structure. Give another ACCESS command to regain these. (Note that you must access your log-in directory to regain group rights obtained by the LOGIN command, lost by accessing another directory on the public structure.)

Related Commands

ACCESS for obtaining ownership rights to a directory and the group rights of the owner

DISMOUNT for decrementing the mount count of a previously accessed structure

INFORMATION STRUCTURE for finding out who is accessing a structure

END-ACCESS (Cont.)

Examples

1. Give up your access rights to another user's directory.

```
@END-ACCESS <HOLLAND>
```

2. Access another user's directory, copy a file from it, and give up your rights to it. Then give a command that depends on your own group rights. (It fails.) Access your own directory to establish these, and repeat the command, successfully this time.

```
@ACCESS <HOLLAND>  
Password: _____  
@COPY <HOLLAND>DIST.LST  
  <HOLLAND>DIST.LST.2 => DIST.LST.2 [OK]  
@END-ACCESS <HOLLAND>  
@INFORMATION DIRECTORY <LATTA.*>,  
?No such directory  
@ACCESS <LATTA>  
@INFORMATION DIRECTORY <LATTA.*>,  
@NAME-ONLY  
@@  
  Name PS:<LATTA.A>  
  Name PS:<LATTA.A.F-O>
```

3. Mount a structure, and access a user's directory there. Get a listing of his files of type .TXT. End the access and dismount the structure.

```
@MOUNT STRUCTURE SNARK:  
Structure SNARK: mounted  
@ACCESS SNARK:<HOLLAND>  
Password: _____  
@DIRECTORY SNARK:<HOLLAND>*.TXT  
  
  SNARK:<HOLLAND>  
  ACCT.TXT.1  
  MAIL.TXT.2  
  REMARKS.TXT.1  
  SYSTEM.TXT.1  
  
  Total of 4 files  
@END-ACCESS SNARK:<HOLLAND>  
@DISMOUNT STRUCTURE SNARK:  
Structure SNARK: dismounted
```

EOF

Writes an end-of-file mark on the specified magnetic tape. Use this command for unlabeled tapes only.

Format

@EOF (DEVICE) dev:

where

dev: is the name of the magnetic tape drive on which you want to write an end-of-file mark. The colon after the device name is optional.

Hints

EOF Seldom Needed

Because tape-writing programs and commands automatically write end-of-file marks in the appropriate places, you do not ordinarily need the EOF command. But it can be useful if such a program is interrupted (by your CTRL/C or by a system failure and restart) and you want to preserve the information already written. Also, you can shorten files on an existing tape by giving an EOF command at the desired point.

Restrictions

EOF With Open Files

If you have given a CTRL/C to exit from a program that has opened a magnetic tape drive and you then give the EOF command for that tape drive, the system will first allow you to close the associated file. You must do so for the EOF command to succeed, but you will probably be unable to continue the program from that point, because the file will now be closed.

Related Commands

BACKSPACE

REWIND

SKIP

UNLOAD

other TOPS-20 commands for controlling magnetic tape drives

EOF (Cont.)

Examples

1. Put an end-of-file mark (EOF) on your magnetic tape.

@EOF MTA0:

ERUN

Runs a system program without disturbing the program already in memory by placing the program in an ephemeral fork.

Format

@ERUN (PROGRAM) filespec

where

filespec is the file specification of a system program
Default dev:<directory> - SYS:

Default .typ - .EXE

Characteristics

Characteristics of an Ephemeral Fork

The ERUN command runs a program in an ephemeral fork. A program that runs in an ephemeral fork acts like an EXEC command (excluding those EXEC commands that run programs or otherwise affect memory). Ephemeral forks and EXEC commands share these characteristics:

- They do not affect programs in memory. For example, if you exit a program and issue a SYSTAT command, or run a program in an ephemeral fork, neither the command nor the ephemeral fork will disturb the program in memory.

A program that runs ephemeraly is always placed in a new fork.

- They disappear when interrupted or when processing completes. For example, if you stop execution of a SYSTAT command or an ephemeral fork with CTRL/C, neither the command nor the ephemeral fork can be continued.

Whenever you stop or exit an ephemeral fork, the fork is automatically reset (cleared from memory).

Good candidates for ephemeral forks are programs that may have short execution times and simply display information in a manner similar to the INFORMATION and SYSTAT commands.

Related Commands

INFORMATION LOGICAL-NAMES for examining the definition of
SYS:

R for running executable programs
stored on SYS:

ERUN (Cont.)

RUN	for running executable user programs
SET FILE EPHEMERAL	for giving a file a permanent ephemeral attribute
SET PROGRAM EPHEMERAL	for running a program in an ephemeral fork

Examples

1. Display the status of the fork in memory with the INFORMATION FORK-STATUS command. Then, run a program in an ephemeral fork in order to preserve the state of your job's memory. Redisplay the fork status and note that the ephemeral program has been reset and has not replaced the original fork.

```
@INFORMATION FORK-STATUS
=> EMACS (1): HALT AT 50340, 0:00:03.6
@ERUN TERMSTAT
TERMSTAT>SHOW FREE TERMINALS

Lab   Terminals in use   Free terminals
---   -
A           17           0
B           12           4

TERMSTAT>EXIT
@INFORMATION FORK-STATUS
=> EMACS (1): HALT at 50340, 0:00:03.6
```

EXAMINE

Displays the contents of a memory location.

Format

@EXAMINE (MEMORY LOCATION) octal or symbolic address

Output

Contents of Memory Location or Message

When you complete an EXAMINE command, the system prints the memory address examined, followed by a slash (/) and its contents. If you previously used the SET TYPEOUT MODE SYMBOLIC command, this information is both in symbolic and, in parentheses, numeric (octal) format. (The numeric information will always appear for this setting of the command; symbolic information will appear if the system finds that it is different from the numeric.)

Generally the numeric format shows two 6-digit octal numbers separated by a pair of commas (,,). If you do not see this pair of commas, only the right half of the memory location is being displayed; as the left half is 0. However, if you are not permitted to examine this location, the system prints only a message telling you of the restriction.

Hints

Using Symbols

For symbols that are defined in multiple modules of a program, you can be specific by giving the module name followed by an ampersand (&) and the symbol name.

Abbreviating EXAMINE

The EXAMINE command can be abbreviated by the single letter E.

Default Argument for EXAMINE

The argument of your current EXAMINE command defaults to a value greater by 1 than the last address examined, allowing you to inspect a section of memory with only a minimum of typing. But if you gave a more recent DEPOSIT command, the argument of your current EXAMINE command defaults to that address, allowing you to verify the deposit.

Using EXAMINE With Noncurrent and Inferior Forks

The EXAMINE command displays memory locations of the current fork. To examine the memory of noncurrent or inferior forks, make the fork the current fork by giving the FORK command with the fork name or number as an argument.

EXAMINE (Cont.)

To run an inferior fork after examining it, you must ensure that all superior forks are running too. Give the CONTINUE command with the superior fork name or number as an argument to let the superior fork continue its inferiors.

Related Commands

DDT	for calling a debugging program, allowing more efficient examination of memory
DEPOSIT	for changing the contents of a specific memory location
FORK	for selecting the fork whose memory you want to examine
INFORMATION MEMORY-USAGE	for displaying a list of memory pages, their contents and status
SET TYPEOUT MODE	for displaying information in symbolic or numeric format.

Examples

1. Examine location 550 of the current fork.

```
@EXAMINE 550
550/74473,,414155
```

2. Examine location 20, first in numeric typeout mode, then in the symbolic mode.

```
@SET TYPEOUT MODE NUMERIC
@EXAMINE 20
20/104000,,56
```

```
@SET TYPEOUT MODE SYMBOLIC
@EXAMINE 20
P+1/104000,,.JBBLT+11 (20/104000,,56)
```

3. Put a program into memory and find out what pages it occupies. Examine a location on page 2, and then (using the abbreviated form of the EXAMINE command) one on page 400.

```
@GET DMN
@INFORMATION MEMORY-USAGE
```

5. pages, Entry vector loc 400010 len 254000

```
Section 0      R, W, E, Private
0-3          DMN.EXE.1 1-4   R, CW, E
400          DMN.EXE.1 5    R, CW, E
```

```
@EXAMINE 2550
2550/600170
@E 400550
400550/0
```

EXECUTE

Loads your program into memory, compiling the source file first if necessary. Then it starts the program.

Format

@EXECUTE (FROM) /switch(es) source/switch(es) object,...

where

switches are keywords chosen from the list below, indicating your choice of EXECUTE command options. They have different effects depending on their position in the command line: placed before all files in the command, they act on defaults for all; otherwise they affect only the nearest preceding file.
Defaults are shown in the list of switches

source is the file specification of the source program. The filename must be of 6 or fewer characters, and the file type of 30 fewer characters; you cannot use a generation number. This argument is not necessary if you supply an object filespec.

object is the file specification of the object program. The filename must be of six or fewer characters, and the file type must be .REL; you cannot use a generation number. This argument is not necessary if you supply a source.

Default (if you give neither source nor object filespecs) - last filespecs and associated switches you gave in a LOAD-class command

,... means that, after commas, you can give more arguments (switches, source, and object) of the form already shown

Summary of EXECUTE Command Switches (defaults in boldface)

	/10-BLISS
	/36-BLISSS
	/68-COBOL
	/74-COBOL
	/ABORT
	/ALGOL
	/BINARY
	/COBOL
	/COMPILE
	/CREF
	/CROSS-REFERENCE
	/FAIL
	/FLAG-NON-STANDARD

EXECUTE (Cont.)

```
| /FORTRAN
| /LANGUAGE-SWITCHES:"/switch(es) "
| /LIBRARY
| /LIST
| /MAC
| /MACRO
| /MAP
| /NOBINARY
| /NOCOMPILE
| /NOCREF
| /NOCROSS-REFERENCE
| /NOFLAG-NON-STANDARD
| /NOLIBRARY
| /NOLIST
| /NOOPTIMIZE
| /NOSEARCH
| /NOSTAY
| /NOWARNINGS
| /OPTIMIZE
| /PASCAL
| /RELOCATABLE
| /SAIL
| /SEARCH
| /SIMULA
| /SNOBOL
| /STAY
| /WARNINGS
```

Descriptions of these switches are given below. Although the system will not reject switches described under any of the LOAD-class commands, only those switches commonly associated with EXECUTE are described here.

EXECUTE Command Switches

```
| /10-BLISS      compiles the file using the BLISS-10 compiler.
|                  Default for files of type .B10 and .BLI
|
| /36-BLISS      compiles the file using the BLISS-36 compiler.
|                  Default for files of type .B36
|
| /68-COBOL      compiles the file using the COBOL-68 compiler.
|                  Default for files of type .C68 or .68C
|
| /74-COBOL      compiles the file using the COBOL-74 compiler.
|                  Default for files of type .C74 or .74C
|
| /ABORT         stops a compile if a fatal error is detected
|                  and returns your terminal to TOPS-20 command
|                  level.
|
| /ALGOL         compiles the file using the ALGOL compiler.
|                  Default for files of type .ALG
|
| /BINARY        allows generation of an object (binary) file
|                  for each source file given.
|                  Default
```

EXECUTE (Cont.)

| /COBOL compiles the file using the COBOL compiler,
| either COBOL-68 or COBOL-74, that your
| installation has stored in the file
| SYS:COBOL.EXE.
| Default for files of type .CBL

| /COMPILE forces compilation of the source file even if a
| current object file already exists. Use this
| switch along with a /LIST or /CREF switch to
| obtain listings when you have current object
| files.

| /CREF same as /CROSS-REFERENCE.

| /CROSS-REFERENCE creates a file containing cross-reference
| information for each compilation. The file
| name is that of the object file; the file type
| is .CRF. Use the CREF command to obtain a
| listing of the file. (For COBOL files this
| switch automatically produces a cross-reference
| listing.)
| Default

| /FAIL compiles the file using the FAIL compiler.
| Default for files of type .FAI

| /FLAG-NON-STANDARD indicates nonstandard syntax in a file

| /FORTRAN compiles the file using the FORTRAN compiler.
| Default in the absence of a standard
| source file type and a language
| switch
| Default for files of type .FOR

| /LANGUAGE-SWITCHES:"/switch(es)"
| passes the specified switches to the compiler
| that will process the file(s) to which this
| switch applies. You must include the switches
| in double quotation marks (" ").

| /LIBRARY same as /SEARCH.

| /LIST prints a line printer listing of the program in
| ASCII format; the name of this listing is the
| filename of the object file. The /CREF switch
| overrides /LIST when they both apply to the
| same file.

| /MAC same as /MACRO.

| /MACHINE-CODE produces a file containing the generated
| machine code. The filename is that of the
| object file; the file type is .LST. For
| high-level languages.

| /MACRO assembles the file using the MACRO assembler.
| Default for files of type .MAC

EXECUTE (Cont.)

/MAP	produces a loader map and stores it in the file object.MAP, where object is the name of the module containing the start address; or (if no start address) nnnLNK.MAP, where nnn is your job number.
/NOBINARY	prevents generation of an object (binary) file. Use this switch along with /LIST or /CREF to allow these switches to take effect without producing a new object file.
/NOCOMPILE	prevents compilation if the object file is current; otherwise it forces compilation. Cancels the /COMPILE or /RELOCATABLE switch.
/NOCREF	same as NOCROSS-REFERENCE.
/NOCROSS-REFERENCE	prevents the creation of a cross-reference file. Default
/NOFLAG-NON-STANDARD	prevents the flagging of non-standard syntax in the file. Default
/NOLIBRARY	same as /NOSEARCH.
/NOLIST	prevents a line printer listing of the program. Default
/NOMACHINE-CODE	prevents generation of a file containing machine code. Default
/NOOPTIMIZE	prevents the generation of a globally optimized object file (for FORTRAN programs only). Default
/NOSEARCH	requires all modules in the object file library (the file accompanied by this switch in the command line) to be loaded even if they are not called by your program. Cancels the /SEARCH switch. Default
/NOSTAY	stops the compiler from being placed in a background fork. Use when /STAY is set as a default for the compiler.
/NOWARNINGS	prevents display of warnings for nonfatal errors.
/OPTIMIZE	generates a globally optimized object file, i.e., one that runs as quickly as possible. (For FORTRAN programs only, and only if you do not also give the /DEBUG switch (see the DEBUG command description).)

EXECUTE (Cont.)

	/PASCAL	compiles the file using the PASCAL compiler. Default for files of type .PAS
	/RELOCATABLE	identifies the input file as an object file (regardless of its extension) and prevents compilation of the source file, forcing use of an existing object file even if the object file is out of date. Default for files of type .REL
	/SAIL	compiles the file using the SAIL compiler. Default for files of type .SAI
	/SEARCH	requires that the object file library (the file accompanied by this switch in the command line) be searched for modules called by your program or by a program subroutine. Only these modules are loaded, along with modules called from system libraries, which are always searched.
	/SIMULA	compiles the file using the SIMULA compiler. Default for files of type .SIM
	/SNOBOL	compiles the file using the SNOBOL compiler. Default for files of type .SNO
	/STAY	returns your terminal to TOPS-20 command level so that you can perform other work while the system continues to execute your program. You immediately receive the TOPS-20 prompt (@ or \$), and can then issue any user command. Be careful not to send incorrect data to programs expecting terminal input. Refer to the CONTINUE command, Restrictions: Programs Competing for Terminal Input.) This switch saves you from having to: issue a ^T to make sure execution has begun; give a ^C to halt the job; and issue a CONTINUE /STAY command to remain at command level during execution.
	/WARNINGS	displays warnings for nonfatal errors. Default

Characteristics

Compiling New Sources Only

Before executing programs, the system ordinarily compiles any source (and only those sources) whose write date is more recent than that of the object file of the same name. You can override this action with the /COMPILE or /RELOCATABLE switch.

EXECUTE (Cont.)

Using Standard File Types

If you specify source files with standard types (.FOR, .MAC, .CBL, or .ALG) in an EXECUTE command, the system automatically calls the appropriate compiler when compilation is necessary. If you specify source files by filename only, the system searches your connected directory in the above order for a file of this name and a standard type. To execute programs from sources that have nonstandard file types, give a switch to indicate the proper compiler (/FORTRAN, /MACRO, /COBOL, or /ALGOL). A switch will take precedence over a standard file type if they indicate different languages. If no compiler is indicated with either a switch or a standard file type, the FORTRAN compiler is used.

Default Switches Not Passed to Compiler

Only switches specified in a LOAD-class command are passed to the compiler; default switches are not passed. Instead, the system assumes that the defaults for the compiler are the same as the defaults for the LOAD-class command.

Hints

Commas Between Filespecs

If you give two or more filespecs separated by commas as arguments to EXECUTE, the loaded programs exist in memory at the same time and will act as a single program. You can use this feature to substitute one module for another under varying conditions or for different applications.

Plus Signs Between Filespecs

If you give two or more filespecs separated by plus signs (+) as arguments to EXECUTE, they are treated as a single file by compilers. Their object module is stored under any filename given as the "object" argument of the command, or (if none) under the last filename in the group and file type .REL.

Indirect Files as Arguments

You can store the arguments (source and object filespecs, switches) of an EXECUTE command in an indirect file, and specify them by typing an at sign (@) and its filespec as an EXECUTE command argument.

Establishing Default Arguments with the SET Command

You can issue the SET DEFAULT COMPILE-SWITCHES command to set up default global arguments to the EXECUTE command. Insert this SET command in your COMAND.CMD file to change your own defaults permanently.

EXECUTE (Cont.)

Running LINK Directly

The EXECUTE command automatically runs LINK, the system's loader program, but if you require control of the loading process you can run LINK directly. See the TOPS-20 LINK Reference Manual.

Wildcards Illegal with EXECUTE

The EXECUTE command does not accept wildcard characters (* and %) in a file specification.

Effect on Memory

The EXECUTE command clears any unkept forks from memory, loads the appropriate compiler if necessary, then loads and starts your program.

Related Commands

COMPILE, LOAD, and DEBUG other LOAD-class commands for performing related functions

RUN for running executable programs

Examples

1. Execute a program, indicating the language with a standard file type.

```
@EXECUTE CAFN.FOR
FORTRAN: CAFN
LINK:   LOADING
[LNKXCT CAFN EXECUTION]
```

```
END OF EXECUTION
CPU TIME: 0.04 ELAPSED TIME: 0.89
```

```
EXIT
```

2. Execute a program, indicating the language with a switch. Specify the /STAY switch to return immediately to TOPS-20 command level.

```
@EXECUTE CAFN/FORTRAN/STAY
```

EXECUTE (Cont.)

3. Execute two programs, requesting a cross-reference file for one of them.

```
@EXECUTE CAFN, TAFN/CREF
FORTRAN: CAFN
MAIN.
FORTRAN: TAFN
MAIN.
LINK:    LOADING
[LNKXCT TAFN EXECUTION]

END OF EXECUTION
CPU TIME: 0.04 ELAPSED TIME: 0.15
EXIT
```

4. Combine two source programs into a single object program, and run this program.

```
@EXECUTE CAFN+TAFN
FORTRAN: CAFN
MAIN.
MAIN.
LINK:    LOADING
[LNKXCT TAFN EXECUTION]

END OF EXECUTION
CPU TIME: 0.04 ELAPSED TIME: 0.16
EXIT
```

5. Execute an ALGOL program, ensuring that the compilation includes required modules only; request a map.

```
@EXECUTE /COMPILE/MAP CALEND/ALGOL, ALGMOD.LBR/SEARCH
ALGOL: CALEND
LINK:    LOADING

EXIT
```

EXPUNGE

Permanently erases all the deleted files from a directory.

Format

```
@EXPUNGE (DIRECTORY) dev:<directory>,  
@@subcommand
```

where

dev:<directory> is the name of the directory you wish to expunge; you may use wildcard characters to expunge more than one directory.

Default dev: - your connected structure

Default <directory> - the directory (on the specified structure) of the same name as your connected directory

Default (if no arguments - your are given) connected directory

@@subcommand means that after a final comma you can give one or more optional subcommands on successive lines

DELETE deletes and expunges temporary files, i.e., those with the Temporary (;T) attribute, created by some system programs to hold interim data. Do not use if you will have any further need of these files.

PURGE expunges all files which you have opened but not closed

REBUILD rebuilds the symbol table of the directory named

Output

After a successful EXPUNGE command, the system reports the number of disk pages freed with the message [n pages freed]. If deleted files are mapped, they will not be expunged, and so will not contribute to the number of pages freed. Occasionally the system will report a negative number. This can mean that files were being written in the directory during the EXPUNGE, or (especially if you include the REBUILD subcommand) that previous computations of directory size had not adequately accounted for some files, for example, files written near the time of a system crash and reload.

EXPUNGE (Cont.)

Hints

Using the REBUILD Subcommand

The REBUILD subcommand is not needed under usual conditions, as the system performs this action automatically. Use REBUILD if a message is printed on your terminal advising you to rebuild the symbol table of a directory.

Using the PURGE Subcommand

The PURGE subcommand is useful chiefly for removing the remains of files that were being created at the time of a system crash or a structure dismount. Do not give it while anyone might be using the directory, because that user's program might be deprived of necessary files as a result.

Special Cases

Files With the "Permanent" Attribute

The system erases only the contents of any files that have the Permanent attribute, for example your MAIL.TXT file, when you try to expunge them. The file specifications of permanent files remain among your deleted files, and cannot be removed by TOPS-20 commands.

Related Commands

DELETE	for marking files to be later expunged
DIRECTORY-class commands	for obtaining lists of file specifications
INFORMATION DISK-USAGE	for finding out the size of a directory
UNDELETE	for recovering deleted files

Examples

1. Expunge all deleted files from your directory.

```
@EXPUNGE
PS:<LATTA> [6 pages freed]
```

EXPUNGE (Cont.)

2. Find out how much of your disk space is in use and how much is occupied by deleted files. Delete some of your backup files, then give the EXPUNGE command to erase all of these.

@INFORMATION DISK-USAGE

PS:<LATTA>

154 Pages assigned, 101 in use, 53 deleted
590 Working pages, 590 Permanent pages allowed
33371 Pages free on PS:

@DELETE *.Q*

BLUE.QAR.1 [OK]

REMARK.QXT.1 [OK]

RIMOUSKI.QXT.1 [OK]

@EXPUNGE

PS:<LATTA> [56 pages freed]

FDIRECTORY

The FDIRECTORY (Full DIRECTORY) command is equivalent to the DIRECTORY command with the subcommands CRAM, EVERYTHING, and NOHEADING. Use the same format and subcommands with FDIRECTORY as with DIRECTORY. For further information, see the DIRECTORY command description in this manual.

When used with magnetic tapes, the FDIRECTORY command is equivalent to DIRECTORY for magnetic tapes.

Examples

1. Get a "Full DIRECTORY" listing, on your terminal, for one of your files.

```
@FDIRECTORY TESTF1.FOR
MISC:<LATTA>
TESTF1.FOR.17;P777700;A341 1 162(7) 1 25-Oct-85 11:17:46
25-Oct-85 11:17:46 Never Never LATTA LATTA
```

2. Give the FDIRECTORY command for a file, this time requesting the only piece of information about current files not ordinarily supplied by the command. Ask for a heading also.

```
@FDIRECTORY TESTF1.FOR,
@@HEADING
@@CHECKSUM
@@
MISC:<LATTA>
Write          Read      PGS Bytes(SZ)  Ret   Creation
Checksum      Tape-write  Creator Writer
TESTF1.FOR.17;P777700;A341 1 162(7) 1 25-Oct-85 11:17:46
25-Oct-85 11:17:46 Never    Never    LATTA LATTA 566101P
```


| Makes the specified fork your current fork. The current fork is the
| fork to which TOPS-20 commands are applied.

Format

@FORK (IS) fork

where

fork is one of the following: Fork name
Fork number
Default - the fork with the
highest fork number

Characteristics

Default Fork

If you do not specify a fork name or number with the FORK command, the fork with the highest fork number (usually the last fork created) becomes your current fork, and the fork name is printed in brackets, [FORK-NAME].

Fork Name and Number

Forks are named after the program they contain and are numbered in the order that they are created. In multiforking class commands, the fork name and number are interchangeable.

Hints

More Information

The FORK command is one of the TOPS-20 multiforking-class commands. For more information about multiforking, see the section named Running Multiple Programs in the TOPS-20 User's Guide.

Special Cases

Fork 0

If you are a user with enabled Wheel privileges you can give the command, FORK 0. This references the command processor (EXEC) itself.

FORK (Cont.)

Related Commands

INFORMATION MEMORY-USAGE	for examining memory of the current process
INFORMATION FORK-STATUS	for finding out the number and status of each fork in your job
INFORMATION PROGRAM-STATUS	for finding what fork attributes have been set with the SET PROGRAM command and the number and status of each fork in your job
CONTINUE, FREEZE, KEEP, RESET, SET NAME, SET PROGRAM, and UNKEEP	other multiforking-class commands

Examples

1. Make the first fork you created your current fork.
@FORK 1
2. Display the fork status, and make the last fork you created your current fork. Then, redisplay the fork status to check the result. (In the FORK-STATUS display, an arrow (=>) indicates the current fork).
@INFORMATION FORK-STATUS
=> EDIT (1): Kept, HALT at 6254, 0:00:12.8
DUMPER (2): Kept, HALT at 6065, 0:00:30.1
HOST (3): Kept, HALT at 67543, 0:00:09.3
@FORK
@INFORMATION FORK-STATUS
EDIT (1): Kept, HALT at 6254, 0:00:12.8
DUMPER (2): Kept, HALT at 6065, 0:00:30.1
=> HOST (3): Kept, HALT at 67543, 0:00:09.3
3. Make the FORK named DUMPER your current fork; then display the fork status.
@FORK DUMPER
@INFORMATION FORK-STATUS
EDIT (1): Kept, HALT at 6254, 0:00:12.8
=> DUMPER (2): Kept, HALT at 6065, 0:00:30.1
HOST (3): Kept, HALT at 67543, 0:00:09.3

FORK (Cont.)

4. Find out which forks exist in your job. Look at memory for the first fork, then examine a particular location. Make the second inferior fork current, and do the same thing there.

@INFORMATION FORK-STATUS

=> QUILL (1): Kept, HALT at 50340, 0:00:04.5

Fork 2: HALT at 21010, 0:00:00.4

@INFORMATION MEMORY-USAGE

124. pages, Entry vector loc 4570 len 3

```

Section 0      R, W, E, Private
0-5           Private  R, W, E
6-55          RANDOM:<QUILL>TECPUR.EXE.1120 1-50    R, E
56-77         Private  R, W, E
116-123       Private  R, W, E
620-637       RANDOM:<QUILL>ABBRE.:EJ.614 0-17    R, E
640-643       RANDOM:<QUILL>TYPE.:EJ.27 0-3      R, E
644-645       RANDOM:<QUILL>INIT.:EJ.17 0-1      R, E
646-661       RANDOM:<QUILL>LSTSQ.:EJ.424 0-13    R, E
662-663       RANDOM:<QUILL>SYSTEM.:EJ.1 0-1     R, E

```

@EXAMINE 6400

6400/ 200040,, 4636

@FORK 2

@INFORMATION MEMORY-USAGE

95. pages, Entry vector loc 15710 len 3

```

Section 0      R, W, E, Private
0-11          Private  R, W, E
13-15         Private  R, W, E
16-110        RANDOM:<TOOLS>DEFFNA.3 3-75    R, CW, E
117           Private  R, W, E
166           Private  R, W, E
170           Private  R, W, E
172           Private  R, W, E
174           Private  R, W, E
224           Private  R, W, E
226           Private  R, W, E
231-250       Private  R, W, E

```

@EXAMINE 2600

2600/ 0

FREEZE

Halts execution of a fork.

Format

@FREEZE (FORK) fork

where

fork is one of the following: Fork name
Fork number
Default - the current fork

Characteristics

Same Function as CTRL/C

The FREEZE command stops running background forks while you are at EXEC command level. The effect is the same as if you typed two CTRL/Cs while at the fork's program level.

Hints

More Information

The FREEZE command is one of the TOPS-20 multiforking-class commands. For more information about multiforking, see the section named Running Multiple Programs in the TOPS-20 User's Guide.

Related Commands

CONTINUE/BACKGROUND for continuing a halted fork in the background
INFORMATION FORK-STATUS for displaying the fork status
FORK, other multiforking-class commands
INFORMATION PROGRAM-STATUS
KEEP, RESET, SET NAME,
SET PROGRAM, and UNKEEP

Examples

1. Give the FREEZE command to stop the current running background fork. Then, display the fork status. The arrow points to the current fork.

```
@FREEZE
@INFORMATION FORK-STATUS
=> BLISS (1): ^C from RUNNING at 500000, 0:00:13.1
   EDIT (2): Kept, HALT at 6254, 0:00:00.5
```

FREEZE (Cont.)

2. Display the fork status and give the FREEZE command to stop a running background fork. Then, redisplay the fork status to check the result.

@INFORMATION FORK-STATUS

BLISS (1): Background, RUNNING at 500000, 0:00:13.1
=> EDIT (2): Kept, HALT at 6254, 0:00:00.5

@FREEZE BLISS

@INFORMATION FORK-STATUS

BLISS (1): ^C from RUNNING at 500000, 0:00:13.1
=> EDIT (2): Kept, HALT at 6254, 0:00:00.5

GET

Places an executable program into memory.

Format

@GET (PROGRAM) filespec /switch

where

filespec is the specification of any file containing an
executable program
 Default file type - .EXE

/switch is /USE-SECTION:n
 specifies the memory section (from 0 to 37
 octal) into which your program is to be
 loaded. You can use this switch only if your
 program can be contained in one section.

Effect on Memory

The GET command clears any unkept forks, puts the specified program into memory.

Related Commands

	INFORMATION MEMORY-USAGE	for examining the contents of memory
	KEEP	for making the specified fork a kept fork.
	LOAD	for loading a source or object program into memory
	MERGE	for putting an executable program into memory without first clearing memory
	SAVE	for storing a copy of the program in memory in a file in executable format
	START	for starting the program in the current fork

GET (Cont.)

Examples

1. Put an executable program into memory.

@GET TESTF1.EXE

2. Verify that you have a magnetic tape drive assigned to your job. Get one of your executable programs, save a copy of it on tape, and then start it.

@INFORMATION AVAILABLE DEVICES

Devices available to this job:

DSK, PS, SNARK, MISC, LANG, REL3, DX20, MTA0

LPT, LPT0, LPT1, CDR, PCDR0, CDP, FE0-15

PTY23-61, NUL, PLT, PLT0, DCN, SRV

Devices assigned to/opened by this job: MT0, TTY230

@GET TESTF1

@SAVE MT0:

MT0:TESTF1 Saved

@START

THIS IS A TEST.

END OF EXECUTION

CPU TIME: 0.03 ELAPSED TIME: 0.72

EXIT

HELP

Displays explanatory text for many TOPS-20 system features.

Format

@HELP (ON SUBJECT) name

where

name is the name of a topic chosen from the list given in response to the command HELP ?

Default name - HELP

Sample of HELP Command Arguments

ACCT20	ACCTPR	ACTGEN	APL	APLSF	BLIS10	CHECKD	CHKPNT
COBDDT	COBOL	CONV20	CREF	DAEMDB	DBINFO	DBMEND	DIRTST
DLUSER	DUMPER	EDIT	FE	FILCOM	FORDDT	FORDML	FORMAT
FORTRA	HELP	ISAM	LIBARY	LINK	LPTSPL	MACRO	MAIL
MAKLIB	MAKRAM	MAKVFU	OPLEAS	PLEASE	PTYCON	QUEUE	RDMAIL
RERUN	RSXFMT	RUNINP	RUNOFF	SCHEMA	SORT	SYSERR	SYSJOB
TRANSL	ULIST	USAG20	USAH20	WATCH			

Characteristics

Other HELP Command Arguments

Note that some of the HELP command arguments shown here may be omitted if the associated topics are not available at your site. The list may include other texts inserted by your system administrator to describe features special to your system. Also, this list is revised frequently to reflect improvements and additions to standard TOPS-20 programs.

Hints

Printing HELP Files on the Line Printer

The texts displayed by the HELP command are stored in system logical name HLP: under the name of the topic and file type .HLP. Use the PRINT command to request your own copy.

Example

1. Ask for information about the FILCOM program.

```
@HELP FILCOM  
FILCOM V21B(60)
```

```
FILCOM compares two files in either ASCII mode  
or binary depending upon switches or file name extensions.  
All standard binary extensions are recognized as binary by  
default.
```

```
Switches are :-
```

```
/A compare in ASCII mode
```

```
.
```

```
.
```

```
.
```

```
/W compare the Word mode but don't expand files
```

```
/X expand files before word mode compare
```

INFORMATION

Displays information about system and job parameters.

Format

@INFORMATION (ABOUT) argument

where

argument is a keyword, chosen from the list below, indicating your choice of INFORMATION command options

Summary of INFORMATION Command Arguments (defaults in boldface)

ADDRESS-BREAK

ALERTS

ARCHIVE-STATUS filespecs

ARPANET

AVAILABLE [LINES
DEVICES

BATCH-REQUESTS [/ALL
/FAST
/PROCESSING-NODE:node name
/USER:user name Default user name - your user
name

CLUSTER

COMMAND-LEVEL

DECNET node-name

DEFAULTS [ALL
CARDS
COMPILE-SWITCHES
PAPER-TAPE
PLOT
PRINT
SUBMIT
TAKE

DIRECTORY dev:<directory>,
@@VERBOSE
@@FAST
@@NAME-ONLY

Default dev:<directory> - your
connected directory

DISK-USAGE dev:<directory>

Default dev:<directory> - your
connected directory

FILE-STATUS octal JFN

Default JFN - all JFNs in your
job

INFORMATION (Cont.)

FORK-STATUS
JOB-STATUS

LOGICAL-NAMES $\left[\begin{array}{l} \text{SYSTEM} \\ \text{JOB} \\ \text{ALL} \\ \text{logical name:} \end{array} \right.$

MAIL $\left[\begin{array}{l} \text{user name} \\ \text{SYSTEM} \end{array} \right.$ Default user name - your user name

MEMORY-USAGE
MONITOR-STATISTICS

OUTPUT-REQUESTS $\left[\begin{array}{l} /ALL \\ /FAST \\ /USER:\text{user name} \end{array} \right.$ Default user name - your user name

PROGRAM-STATUS
PSI-STATUS

RETRIEVAL-REQUESTS $\left[\begin{array}{l} /ALL \\ /FAST \\ /USER:\text{user name} \end{array} \right.$ Default user name - your user name

SPOOLED-OUTPUT-ACTION
STRUCTURE dev: Default dev: - your connected structure

SUBSYSTEM-STATISTICS
SYSTEM-STATUS
TAPE-PARAMETERS
TERMINAL-MODE number Default number - your terminal line number

VERSION
VOLUMES

INFORMATION Command Arguments

ADDRESS-BREAK gives the location (in numeric or symbolic format - depending upon previous specification of the SET TYPEOUT MODE command) and mode of any address breaks for the program currently in memory. Set with SET ADDRESS-BREAK.

ALERTS lists the dates and times that the system is to signal you at the terminal. The last line of the display indicates whether alerts are to be sent unconditionally to your terminal (depending upon previous specification of the SET AUTOMATIC command). Set with SET ALERT.

INFORMATION (Cont.)

ARCHIVE-STATUS filespecs prints the archive status of all specified files for which archival has been requested or for which migration has been prohibited

Default filespec - *.*.* in your connected directory

ARPANET

displays, if the system is a member, information about Internet networks, including ARPANET, Milnet and Local Area Networks. The display includes:

- the name of the local host system followed by its Internet name and its Internet address
- the status of the network interface
- whether network interface output is enabled
- whether network service is enabled
- the date and time of the last network interface online transition, offline transition, and cycle transition

AVAILABLE

[LINES
DEVICES

lists the devices or terminal lines available to you or already assigned to your job. Use ASSIGN to obtain devices (use MOUNT for structures).

Default - DEVICES

BATCH-REQUESTS

[/ALL
/FAST
/PROCESSING-NODE:node name::
/USER:user name

lists the jobs being processed and waiting to be processed by the batch system. The list includes:

- the jobname and request ID number of the request (an asterisk (*) appears before the jobname if the job is currently being processed)
- the scheduled run time of the request
- the name of the user who initiated the request
- the values of the switches /AFTER and /DEPENDENCY-COUNT, if values were given in the original SUBMIT or subsequent MODIFY command

Use SUBMIT, MODIFY, or CANCEL to change this list.

INFORMATION (Cont.)

The /ALL switch adds the switches /ASSISTANCE, /PRIORITY, /RESTARTABLE, /SEQUENCE, and /UNIQUE to this list, while /FAST eliminates the display of all switches and column headings; /PROCESSING-NODE specifies the DECnet network node about whose batch jobs you want information; /USER restricts descriptions to jobs of the user named, and can be given with any of the other three switches.

Default user name - your user name

CLUSTER

displays the names of the systems in a Common File System (CFS) cluster:

- local cluster node (the system you are logged in on).
- accessible CFS nodes (the other systems in the CFS cluster).
- accessible HSC servers (the HSC50 device controllers in the cluster).

COMMAND-LEVEL

prints the status of the LATE-CLEAR-TYPEAHEAD parameter, which prevents you from giving another TOPS-20 command until any error message resulting from a previous command has been printed. Set with SET LATE-CLEAR-TYPEAHEAD.

DECNET node-name

tells whether the specified DECnet network node is accessible to your system. If you do not specify a node name, the system prints the name of your host system, the total number of reachable nodes, and the names of all reachable nodes.

Default node-name - all accessible nodes

DEFAULTS

ALL
CARDS
COMPILE-SWITCHES
PAPER-TAPE
PLOT
PROGRAM
PRINT
SUBMIT
TAKE

displays, in a format suitable for entering them, default arguments established at the current level of TOPS-20 for the specified command. CARDS and PAPER-TAPE refer to the PUNCH CARDS and PUNCH PAPER-TAPE commands, respectively. COMPILE-SWITCHES refers to LOAD-class commands and PROGRAM refers to the SET PROGRAM command. The ALL argument displays the defaults for all these categories. Set with SET DEFAULT.

Default - ALL

INFORMATION (Cont.)

DIRECTORY dev:<directory>,

| @@FAST lists the current parameter values set
| @@VERBOSE for the indicated directory (with the
| @@NAME-ONLY exception of the directory password) by
the SET DIRECTORY or BUILD commands, or
by default. The subcommands call for
either a short list of non-default (that
is, user-determined) values only (FAST),
or a complete list including defaults
(VERBOSE), or a listing of directory
names only (NAME-ONLY). If you use
NAME-ONLY, specify a directory in the
form <directory.*>, <*directory*>, or
<*>. The categories of information
include:

- the name of the directory
- working and permanent storage limits
- capabilities (assigned or withheld)
- whether you can establish DECnet or ARPANET network connections
- whether expired files should be automatically archived
- directory number
- default file protection
- default account for login
- directory protection
- default number of generations maintained for files
- maximum number of subdirectories allowed
- date and time that you started the current terminal session with LOGIN (for log-in directory only)
- off-line and on-line expiration defaults
- group memberships
- user group numbers assignable to subdirectories

INFORMATION (Cont.)

- TOPS-10 project-programmer number

Set with SET DIRECTORY or (for subdirectories) BUILD.

Default dev:<directory> - your
connected
directory

Default subcommand - FAST

DISK-USAGE dev:<directory>

prints, for the indicated directory

- the name of the directory
- the number of pages of assigned disk storage, and the number of deleted pages, if any
- working and permanent page limits
- total number of unused pages on the file structure containing the directory

The wildcard characters, * and % can be included in the <directory> field. For example, type <%directory*>, <directory.*>, or <*> to get information about all matching directories or subdirectories.

Default dev:<directory> - your
connected
directory

FILE-STATUS octal JFN

gives, for the specified JFN (an internal number identifying each file opening)

- the JFN
- the associated file specification
- the mode of access (Append, Execute, Read, or Write) for which the JFN is open (or was opened last, if NOT OPENED precedes the access mode)
- special access conditions, namely DATA ERROR if an error is made in accessing the file, or EOF if the file pointer is at the end of the file
- if appropriate, byte pointer and byte size, which tell the number of bytes transferred to or from the file, and

INFORMATION (Cont.)

- a list of devices currently assigned to or opened by this job But if a file has been opened by another process for its sole use, you see only the message, "Restricted JFN".
Default JFN - all JFNs for your job

FORK-STATUS

gives a summary of the status of each fork belonging to your current copy of the TOPS-20 command processor, including Kept status, RUN status, and total CPU time used so far. An arrow (=>) indicates your current fork.

JOB-STATUS

prints your

- host system (Displayed only if your host system is part of a DECnet or ARPANET network.)
- job number
- user name
- connected directory (if not your log-in directory)
- account; session remark (if any)
- terminal number
- network node to which your output device, requests are sent. (Displayed only if not your host node.) Set with the command, SET LOCATION.

You can set some of these parameters with CONNECT, SET ACCOUNT, SET LOCATION, and SET SESSION-REMARK.

LOGICAL-NAMES

ALL
JOB
SYSTEM
logical name:

prints the logical names and definitions which have been established for your job, for the system, or for both; or prints the job-wide and system-wide definitions of the specified logical name. Establish and withdraw logical names with DEFINE.

INFORMATION (Cont.)

For the DEFINE and INFORMATION LOGICAL-NAMES commands, a colon following the logical name is optional. However, in INFORMATION LOGICAL-NAMES the logical name SYS: must always be followed by a colon. Otherwise, the system interprets SYS as an abbreviation for the SYSTEM argument.

The wildcard characters, * and % can be included in the logical name. For example, type A* to list all logical names that begin with the letter 'A'. Refer to example 6.

Default - JOB

MAIL [user name
SYSTEM

tells whether there is unread mail for the user, if you have read access to the user's mailbox; otherwise, you see only the message, "Mailbox protected." Also, displays any system messages since your last login when you type SYSTEM instead of user-name. Send mail with one of the two mail programs, MAIL and DECmail/MS. Read mail with the RDMail or DECmail/MS program.

Default user name - your user name

MEMORY-USAGE

prints, for the current process of your job

- the number of pages of memory assigned
- location (in numeric or symbolic format - depending upon previous specification of the SET TYPEOUT MODE command) and length of the current program's entry vector (see with SET ENTRY-VECTOR)

and on each succeeding line

- the page numbers of pages occupied by a file or program
- the file specification if the pages are file pages; the process specification if the pages are mapped from another process; PRIVATE otherwise.

INFORMATION (Cont.)

- the page numbers of file pages or process pages. If a page is mapped by indirect pointers, the file specification is printed to which it is mapped; "Fork n" means that these pages are mapped indirectly through another process (process n) of the job; "No page" can mean either of these conditions, when the destination page does not yet exist.

- the permitted accesses to the pages (set with SET PAGE-ACCESS):

R - Read access

W - Write access

CW - Copy-on-Write access

E - Execute access

Refer to Example 4 at the end of this command description for obtaining information on pages assigned to extended sections of memory.

MONITOR-STATISTICS

gives you

- the length of time (in hours, minutes, and seconds) since the monitor was reloaded
- an analysis of monitor overhead time, by percentages
- the number of swap-reads and -writes, and file-reads and -writes
- the number of pages of memory available to user programs
- the number of terminal wake-ups (occasions when a program "wakes up" after waiting for terminal input or output to finish, and of terminal interrupts (occasions when a program is interrupted by a CTRL/C, CTRL/O, or CTRL/T (or other, user-enabled control characters) typed at a user's terminal)
- the average number of processes in the balance set (NBAL, a subset of the run set - these are runnable, and each receives a share of total CPU time) and in the remainder of the run set (NRUN - these are waiting to be run)

INFORMATION (Cont.)

- the number of seconds of CPU time given to each of the scheduler queues (where the leftmost listing describes the highest priority queue, for interactive processes, and the rightmost listing is for CPU-bound processes)
- if class scheduling is enabled, the allotted share and actual use of the system (expressed as a percentage of total CPU time) by each class, and the 1-, 5-, and 15-minute load averages of each class

All averages and totals are computed for the time since system start-up.

MOUNT-REQUESTS [/ALL
/FAST
/USER:user name

prints a list, at your terminal, of pending structure-mount and tape-mount requests, and of tape-mount requests currently being satisfied. The list includes

- the volid of the first volume of tape that will be mounted, or the volid of the mounted tape, or the structure identification of each disk pack that will be mounted
- the status of each volume of tape (either the number of the tape drive, in the form, MTAn, on which it is mounted, or Waiting)
- the type of request (either Disk or Tape)
- the tape density specified in the tape-mount request
- the mode (either Enabled, if the /WRITE-ENABLED switch was specified or assumed in the original MOUNT-TAPE command, or Locked if /READ-ONLY applies) in which each volume of tape is to be mounted
- the request number (i.e., request ID number) of each request
- the number of the job that made the request

INFORMATION (Cont.)

- the user name of the owner of the job that made the request

Use the MOUNT, CANCEL (for pending requests), and DISMOUNT (for satisfied requests) commands to change this list.

The /ALL switch adds the following to the display: the /ASSISTANCE, /PRIORITY, /RESTARTABLE/, /NOTE, /SEQUENCE, /UNIQUE, and /REMARK switches, whether a tape mount request is for a labeled tape, and the tape volume-set name. The /FAST switch eliminates column headings and the sum of the number of requests; /USER restricts descriptions to jobs of the user named, and can be given with either of the other two switches.

Default user name - your user name

OUTPUT-REQUESTS

```
[ /ALL
  /FAST
  /USER:user name
```

prints a listing, at your terminal, of the requests being sent or waiting to be sent to an output device. The list includes

- the name of the queue (card punch, paper tape punch, plotter, or line printer)
- the jobname and request ID number of the request (an asterisk (*) appears before the jobname if the request is currently being processed)
- the output limit, in appropriate units (number of pages, minutes of plotter time, feet of paper tape, or number of cards)
- the name of the user who initiated the request, and
- values of the switches /AFTER, /FORMS, and /UNIT, if given non-default values in the original PRINT, PLOT, PUNCH, or subsequent MODIFY command.

Use PRINT, PLOT, PUNCH, MODIFY, or CANCEL to change this list.

INFORMATION (Cont.)

The /ALL switch adds the /NOTE and /SEQUENCE switches to this list, while the /FAST switch eliminates the display of all switches and column headings; /USER restricts descriptions to jobs of the user named, and can be given with either of the other two switches.

Default user name - your user name

PROGRAM-STATUS

gives the following information for the current level of the TOPS-20 command processor (EXEC):

- the amount of CPU time you have used, and total elapsed time since you logged in
- the amount of TOPS-20 command processor time used
- SET UUO-SIMULATION (set with SET UUO-SIMULATION) if the TOPS-10 compatibility package is enabled to simulate TOPS-10 monitor calls issued by a program you are running
- SET CONTROL-C-CAPABILITY (set with SET CONTROL-C-CAPABILITY) if your program is allowed to handle CTRL/C interrupts itself
- the settings established with the SET TRAP and SET TYPEOUT commands
- the settings established with the SET DEFAULT PROGRAM command
- the settings established with the SET PROGRAM command
- a summary of the status of each fork belonging to the current copy of the TOPS-20 command processor, including kept status, RUN status, and total CPU time used so far

An arrow (=>) indicates your current fork.

PSI-STATUS

tells you:

- whether the PSI (programmed-software-interrupt) system is in use (ON) or not (OFF)
- the memory address of the level table and of the channel table - 0 if none was set

INFORMATION (Cont.)

- the numbers of the priority levels for which there are interrupts in progress (1 and/or 2 and/or 3), where 1 is the highest priority
- the numbers of channels enabled (ready) to accept interrupts, and of channels with pending interrupts

For further discussion of the interrupt system see the TOPS-20 Monitor Calls Reference Manual.

RETRIEVAL-REQUESTS

[/ALL
/FAST
/USER:user name

prints a list, at your terminal, of pending retrieval requests. Each file for which you request retrieval constitutes a separate request, even if specified within a single RETRIEVE command. The list includes:

- the name of the request (the first six characters of the filename)
- the request ID number
- the volids of each tape containing the file
- the name of the user who made the request

The /ALL switch includes the complete specification (up to 49 characters of the file, while the /FAST switch eliminates column headings; /USER restricts descriptions to requests of the user named and can be used with either of the other two switches.

Note that the /ALL switch does not display the complete file specification unless you have Wheel or Operator privileges.

Default user name - your user name

SPOOLED-OUTPUT-ACTION

tells you whether the system processes your spooled output requests immediately, or defers them until you log out. Set with SET SPOOLED-OUTPUT-ACTION.

INFORMATION (Cont.)

STRUCTURE dev:

gives, for each structure named:

- information as to whether the system performs checking operations while writing to the data or swapping areas of the structure. The system would perform this checking by immediately reading the data that it has just written. If the system manager has enabled these functions, the following lines appear at the top of the display: "Write verification for data", and "Write verification for swapping".
- the number of users who have mounted the structure, the number of open files on the structure, and the number of disks in the structure
- kind of structure - Public or Private, Domestic or Foreign (see the TOPS-20 User's Guide)
- names of users who have mounted the structure
- names of users who have accessed the structure
- names of users who have connected to the structure

The colon after the structure name is optional. Use an asterisk * for dev: to specify all mounted structures. Mount and dismount structures with the MOUNT and DISMOUNT commands.

Default dev: - your connected structure

SUBSYSTEM-STATISTICS

gives, for each subsystem (any name specified by the SETSN JSYS), the following information:

- its name and total runtime since the system last started - SNames, STimes
- the average number of page faults per second it has caused - SPFLTS
- the number of long-term waits it has caused - SNBLKS
- its average working-set size (the number of pages it occupies in memory) - SSize

INFORMATION (Cont.)

- the number of times a SETSN JSYS has been executed for it (excluding the EXEC subsystem)

See the TOPS-20 Monitor Calls Reference Manual for more information.

SUPERIOR

tells you the number of forks that are superior to the current EXEC level. This number is equal to the number of times you gave the PUSH command without intervening POP commands.

Note that many programs have PUSH commands and that some programs automatically do a PUSH. These PUSHes also change the number of superior forks reported by this command.

SYSTEM-STATUS

tells you:

- whether the operator is present
- what kinds of logins are allowed - local, remote, pseudo-terminal, DECnet, Arpanet, or console
- whether accounting (assessing and recording charges for system use) is being done
- whether account validation (checking accounts against lists of authorized users) is enabled
- whether working set preloading is enabled (Working set preloading is discussed in the System Manager's Guide and in the Software Installation Guide.)
- whether sending of level zero system messages (messages primarily of interest to operations personnel) is enabled
- whether sending of level one system messages (messages of interest to all users) is enabled
- whether sending of operator messages (like BUGCHK, BUGINF, and "RESOURCE LOW") to the CTY (central terminal) is enabled
- whether tape-drive allocation (automatic assignment of tape drives) is enabled

INFORMATION (Cont.)

- whether automatic file retrieval-waits (the delaying of a command's execution until specified off-line files are [automatically] retrieved) are enabled
- the system's expiration default date for off-line files
- the current setting of the scheduler bias control
- whether class scheduling is enabled, and, if it is enabled, the special class (if any) for batch jobs, and the default class (if any)

TAPE-PARAMETERS

gives the default settings of these parameters for magnetic tapes:

- tape density, in bits per inch
- tape parity (ODD or EVEN)
- format (ANSI-ASCII, CORE-DUMP, INDUSTRY-COMPATIBLE, or SYSTEM-DEFAULT), and
- tape record length, in bytes

Set with SET TAPE.

TERMINAL-MODE number

gives the following information about the specified terminal:

- its type (for example, LA36, VT52, or SYSTEM-DEFAULT)
- its speed (baud rate), in bits per second. If the terminal is connected to the system through another node, such as a DECserver-100 or another TOPS-20 system, the terminal speed cannot be determined by this command. This is indicated in the display by the message !Terminal speed indeterminate!.
- whether all output that does not originate from your own job is inhibited.
- whether it is set to receive or refuse links, advice, and system messages
- whether it is set to pause in printing output when you type the pause character, and/or at the end of each full page of output

INFORMATION (Cont.)

- the pause and continue characters that you may have set with the `TERMINAL PAUSE CHARACTER` command (only if `TERMINAL PAUSE END-OF-PAGE` and `TERMINAL PAUSE COMMAND` are in effect, and if `CTRL/S` and `CTRL/Q` were not the specified characters)
- the length (in number of lines) and width (in number of characters) of its page
- whether it is capable of printing lowercase characters, whether it is set to raise lowercase letters you type to uppercase, and whether it will mark (flag) capital letters with a single quotation mark (')
- whether it has a formfeed mechanism, and whether it is set to only indicate formfeeds or to perform them
- whether it has mechanical tab stops, whether it is set to immediately echo input you type
- whether it is operating in `FULLDUPLEX` or `HALFDUPLEX` mode

Set with `TERMINAL`. The `SYSTAT` command displays terminal numbers.

VERSION

tells you:

- the name of the host system
- the TOPS-20 operating system's name and octal version number
- the octal version of the TOPS-20 command processor (`EXEC`) in use
- the name (and decimal or octal version number, if any) of the program in the current fork for which program data vectors (PDVs) exist and that are associated with the current process. (Refer to the Monitor Calls Reference Manual and to the description of the `/PVBLOCK` switch in the LINK Reference Manual for information on PDVs.) See Example 5.

INFORMATION (Cont.)

- the decimal version of the UUO simulation package in use (if a TOPS-10 program is in memory)

The format of a version number is:

a.b(c)-d

where: (1) a and b are respectively incremented for major and minor changes in the software (2) c gives a rough indication of the number of times the software component has been edited (3) d, a holdover from earlier versions of TOPS-20 which is now rarely used, identifies the programmer(s) responsible for the software component.

VOLUMES setname: gives the volids of currently mounted and newly created volumes in the specified tape set. A colon after the tape set name is optional.

Hints

Specifying the Current Fork of TOPS-20

Use the FORK command to specify the fork to be described by the ADDRESS-BREAK, FILE-STATUS, MEMORY-USAGE and VERSION arguments. Find out your current fork with INFORMATION FORK-STATUS.

Related Commands

SYSTAT for printing information about the current state of the system.

Examples

1. Use an INFORMATION command to determine your current terminal settings.

```
@INFORMATION TERMINAL-MODE
TERMINAL VT100
TERMINAL SPEED 9600
.
.
.
TERMINAL NO IMMEDIATE
TERMINAL FULLDUPLEX
```

INFORMATION (Cont.)

2. Mount a structure and access your directory on the structure. Compare the disk space available in this directory and in your connected directory. (Note that there are many more pages free on your connected structure (MISC:) as a whole than on structure SNARK;; this is likely to make your use of the system more efficient if you work only within MISC:.)

```
@MOUNT STRUCTURE SNARK:
Structure SNARK: mounted
@ACCESS SNARK:
@INFORMATION DISK-USAGE SNARK:
  SNARK:<LATTA>
    198 Pages assigned
    400 Working pages, 400 Permanent pages allowed
    2836 Pages free on SNARK:
@INFORMATION DISK-USAGE
  MISC:<LATTA>
    119 Pages assigned
    590 Working pages, 590 Permanent pages allowed
    33172 Pages free on MISC:
```

3. Print a file, ordering several copies and supplying a note to be attached to it. Use an INFORMATION command to verify that your request is in the output queue. Modify the date on which the job will be printed, and use the INFORMATION command again to confirm this action.

```
@PRINT TESTF1.FOR /AFTER:17:00/COPIES:20/FORMS:NARROW/NO -
TE:"T-TH LAB"
[Printer job TESTF1 queued, request-ID 219, Limit 54]
```

```
@INFORMATION OUTPUT-REQUESTS /ALL/USER
```

```
Printer Queue:
Job Name  Req#  Limit  User
-----
TESTF1    219    54  LATTA /Forms:NARROW
          /After: 8-Nov-85 17:00 /Note:T-TH LAB /Seq:1791
There is 1 job in the queue (none in progress)
```

```
@MODIFY PRINT 219 /AFTER:15-NOV-85 17:00
[1 Job modified]
```

```
@INFORMATION OUTPUT-REQUESTS /ALL/USER
```

```
Printer Queue:
Job Name  Req#  Limit  User
-----
TESTF1    219    54  LATTA /Forms:NARROW
          /After:15-Nov-85 17:00 /Note:T-TH LAB /Seq:1791
There is 1 job in the queue (none in progress)
```

INFORMATION (Cont.)

4. Place a program in memory section 17. Then give the INFORMATION MEMORY-USAGE command to verify that the program was appropriately placed. The page numbers, beginning at 17000, indicate that section 17 is in use, because a section comprises 1000 (octal) pages. Also, the left half of the entry vector location contains 17.

```
@GET GRADES.EXE.1 /USE-SECTION:17
@INFORMATION MEMORY-USAGE
```

64. pages, Entry vector loc 17,,542 len 254000

Section 0	R, W, E, Private
Section 17	R, W, E, Private
17000-17002	GRADES.EXE.1 1-3 R, CW, E
17374-17425	GRADES.EXE.1 4-35 R, CW, E
17600-17637	GRADES.EXE.1 36-75 R, CW, E
17643-17645	GRADES.EXE.1 76-100 R, CW, E

5. Issue the INFORMATION VERSION command for information on programs in your memory area that have program data vectors associated with them. Note that the merging of such programs yields consolidated information.

```
@GET IOLIB
@INFORMATION VERSION
BOSTON TOPS-20 System, TOPS-20 Monitor 6.1(7)
TOPS-20 Command processor 6.1(5)
Program is IOLIB
PDVs: Program name IOPAK, version 1.1(420)
@GET MATHLB
@INFORMATION VERSION
BOSTON TOPS-20 System, TOPS-20 Monitor 6.1(7)
TOPS-20 Command processor 6.1(5)
Program is MATHLB
PDVs: Program name MATHLB, version 3.33(360)
@MERGE IOLIB
@INFORMATION VERSION
BOSTON TOPS-20 System, TOPS-20 Monitor 6.1(7)
TOPS-20 Command processor 6.1(5)
Program is MATHLB
PDVs: Program name MATHLB, version 3.33(360)
      Program name IOPAK, version 1.1(420)
@MERGE RPTGEN
@INFORMATION VERSION
BOSTON TOPS-20 System, TOPS-20 Monitor 6.1(7)
TOPS-20 Command processor 6.1(5)
Program is MATHLB
PDVs: Program name REPORT, version 3.1(156)
      Program name MATHLB, version 3.33(360)
      Program name IOPAK, version 1.1(420)
```

INFORMATION (Cont.)

6. Use the INFORMATION LOGICAL-NAMES command with the * wildcard to list all the job-wide and system-wide logical names that begin with the letter 'P'.

@INFORMATION LOGICAL-NAMES P*
Job-wide:

PAS: => PUB:<DBONIN.PASCAL>
PB: => PUB:PHONE.BOOK
PUB: => PUBLIC:<DBONIN>

System-wide:

PCL: => RANDOM:<PCL>
POBOX: = PUBLIC:
POST-OFFICE: => PUBLIC:<OPERATOR>
PS: => GIDNEY:

KEEP

Protects a fork from being cleared from memory.

Format

@KEEP (FORK) fork

where

fork is one of the following:

Fork name
Fork number
Default - the current fork

Characteristics

Characteristics of Kept Forks

The KEEP command gives a fork a "kept" status. A kept fork has these characteristics:

- A kept fork is not reset when another program is brought into memory. Normally, when a program is run, it replaces the fork currently in memory. However, if the program in memory is in a kept fork and a new program is run, the new program is placed in a new fork. This allows you to have several programs in memory.
- A kept fork is not cleared from memory with the RESET command unless one of these RESET arguments is specified: the fork name, a period or an asterisk.
- A kept fork can be restarted by typing the kept fork name as an EXEC command. The kept fork name can be abbreviated to the point where it is unique from EXEC commands and other kept fork names. ESCAPE recognition and question mark help also function with kept fork names.

The KEEP command sets the kept fork to restart at its starting address when the kept fork name is given as a command. For information on changing the fork's restart address see Hints, Setting the Kept Fork's Restart Address.

- A kept fork is named after the program it contains. Forks are numbered in the order in which they were created. In multiforking-class commands the fork name and number are interchangeable.

Inferior Forks

Any inferior forks created by a kept fork are also kept.

KEEP (Cont.)

Hints

Keeping Forks Automatically

Place SET PROGRAM KEEP commands in your LOGIN.CMD or COMAND.CMD file for programs that you normally place in kept forks. Then when you load the program, the system automatically keeps the fork and notifies you with the message [Keeping FORK-NAME].

The SET PROGRAM command applies only to the current EXEC level. If you want your SET PROGRAM commands to be in effect after a PUSH command, put the commands into your COMAND.CMD file. The COMAND.CMD file is executed automatically after every PUSH command.

Kept Forks Continued Using the Fork Name

The KEEP command sets the fork to be restarted at its starting point when the fork name is given as a command. So, if a program that was kept with the KEEP command is running in a background fork, and you type the kept fork name, execution of the program is canceled and the program returns to its start address, which is usually the program's prompt.

With the SET PROGRAM KEEP command, you to specify the point at which the fork will restart when the fork name is given as a command. The starting point can be the program's continue, reentry, or start address. The command SET PROGRAM KEEP CONTINUE gives the fork name the same function as the CONTINUE /NORMALLY command. So, if a program that was kept with the SET PROGRAM KEEP CONTINUE command is running in a background fork, and you type the kept fork name, execution of the program continues and your terminal is placed at program level.

More Information

The KEEP command is one of the TOPS-20 multiforking-class commands. For more information about multiforking, see the section named Running Multiple Programs in the TOPS-20 User's Guide.

Restrictions

Limited Number of Forks

There is a limited number of forks available on a system. When all forks are in use, existing users cannot add forks and new users cannot log in. Therefore, KEEP only necessary forks and return idle forks to the system with the UNKEEP or RESET commands.

KEEP (Cont.)

Related Commands

INFORMATION FORK-STATUS	for displaying the fork status
RESET	for clearing forks from memory
UNKEEP	for changing a kept fork to an unkept fork
CONTINUE, FORK, FREEZE, INFORMATION PROGRAM-STATUS, SET NAME, and SET PROGRAM	other multiforking-class commands

Examples

1. Display the fork status with the INFORMATION FORK-STATUS command. Then, give the KEEP command to make the current fork a kept fork and redisplay the fork status.

```
@INFORMATION FORK-STATUS
=> EDIT (1): HALT at 6254, 0:00:00.5
    FILCOM (2): ^C from IO wait at 700272, 0:00:00.3
@KEEP
@INFORMATION FORK-STATUS
=> EDIT (1): Kept, HALT at 6254, 0:00:00.5
    FILCOM (2): ^C from IO wait at 700272, 0:00:00.3
```

2. Display the fork status, and KEEP the FILCOM fork. Then verify the new fork status.

```
@INFORMATION FORK-STATUS
=> EDIT (1): Kept, HALT at 6254, 0:00:00.5
    FILCOM (2): ^C from IO wait at 700272, 0:00:00.3
@KEEP FILCOM
@INFORMATION FORK-STATUS
=> EDIT (1): Kept, HALT at 6254, 0:00:00.5
    FILCOM (2): Kept, ^C from IO wait at 776721, 0:00:00.3
```

LOAD

Loads your program into memory, compiling the source file first if necessary.

Format

@LOAD (FROM) /switch(es) source/switch(es) object,...

switches are keywords chosen from the list below, indicating your choice of LOAD command options. They have different effects depending on their position in the command line: placed before all files in the command, they act as defaults for all; otherwise they affect only the nearest preceding file.

Defaults are shown in the list of switches

source is the file specification of the source program. The filename must be of 6 or fewer characters, and the file type of 3 or fewer characters; you cannot use a generation number. This argument is not necessary if you supply an object filespec.

object is the file specification of the object program. The filename must be of 6 or fewer characters, and the file type must be .REL; you cannot use a generation number. This argument is not necessary if you supply a source filespec.

Default (if you give neither source nor object filespecs) - last filespecs and associated switches you gave in a LOAD-class command

,... means that, after a comma, you can give more arguments (source, switches, and object) of the form already shown

Summary of LOAD Command Switches (defaults in boldface)

```
|      /10-BLISS
|      /36-BLISS
|      /68-COBOL
|      /74-COBOL
|      /ABORT
|      /ALGOL
|      /BINARY
|      /COBOL
|      /COMPILE
|      /CREF
|      /CROSS-REFERENCE
|      /DDT
|      /DEBUG
|      /FAIL
|      /FLAG-NON-STANDARD
|      /FORTRAN
|      /LANGUAGE-SWITCHES:"switch(es) "
|      /LIBRARY
|      /LIST
|      /MAC
```

LOAD (Cont.)

```
| /MACHINE-CODE
| /MACRO
| /MAP
| /NOBINARY
| /NOCOMPILE
| /NOCREF
| /NOCROSS-REFERENCE
| /NODEBUG
| /NOFLAG-NON-STANDARD
| /NOLIBRARY
| /NOLIST
| /NOMACHINE-CODE
| /NOOPTIMIZE
| /NOSEARCH
| /NOSTAY
| /NOSYMBOLS
| /NOWARNINGS
| /OPTIMIZE
| /PASCAL
| /RELOCATABLE
| /SAIL
| /SEARCH
| /SIMULA
| /SNOBOL
| /STAY
| /SYMBOLS
| /WARNINGS
```

LOAD Command Switches

```
| /10-BLISS      compiles the file using the BLISS-10 compiler.
|                Default for files of type .B10 and .BLI
|
| /36-BLISS      compiles the file using the BLISS-36 compiler.
|                Default for files of type .B36
|
| /68-COBOL      compiles the file using the COBOL-68 compiler.
|                Default for files of type .C68 or .68C
|
| /74-COBOL      compiles the file using the COBOL-74 compiler.
|                Default for files of type .C74 or .74C
|
| /ABORT         stops a compile if a fatal error is detected
|                and returns your terminal to TOPS-20 command
|                level.
|
| /ALGOL         compiles the file using the ALGOL compiler.
|                Default for files of type .ALG
|
| /BINARY        allows generation of an object (binary) file
|                for each source file given.
|                Default
|
| /COBOL         compiles the file using the COBOL compiler,
|                either COBOL-68 or COBOL-74, that your
|                installation has stored in the file
|                SYS:COBOL.EXE.
|                Default for files of type .CBL
```

LOAD (Cont.)

/COMPILE	forces compilation of the source file even if a current object file already exists. Use this switch along with a /LIST or /CREF switch to obtain listings when you have current object files.
/CREF	same as /CROSS-REFERENCE.
/CROSS-REFERENCE	creates a file containing cross-reference information for each compilation. The file name is that of the object file; the file type is .CRF. Use the CREF command to obtain a listing of the file. (For COBOL files, the switch automatically produces a cross-reference listing.) See the <u>TOPS-20 User Utilities Guide</u> for more information about the CREF program.
/DDT	loads the DDT debugging program along with your object file.
/DEBUG	produces an object file containing debugging information beyond that usually provided during a compilation (for use with FORTRAN programs only, and only if you have not given the /OPTIMIZE switch).
/FAIL	compiles the file using the FAIL compiler. Default for files of type .FAI
/FLAG-NON-STANDARD	indicates nonstandard syntax in file.
/FORTRAN	compiles the file using the FORTRAN compiler. Default in the absence of a standard source file type and a language switch Default for files of type .FOR
/LANGUAGE-SWITCHES:"/switch(es)"	passes the specified switches to the compiler that will process the file(s) to which the switch applies. You must include the switches in double quotation marks (" ").
/LIBRARY	same as /SEARCH.
/LIST	prints a line printer listing of the program in ASCII format. The name of this listing is the filename of the object file. The /CREF switch overrides /LIST when they both apply to the same file.
/MAC	same as /MACRO.
/MACHINE-CODE	produces a file containing the generated machine code. The filename is that of the object file; the file type is .LST. For high-level languages.

LOAD (Cont.)

	/MACRO	assembles the file using the MACRO assembler. Default for files of type .MAC
	/MAP	produces a loader map and stores it in the file object.MAP, where object is the name of the module containing the start address; or (if no start address) nnnLNK.MAP, where nnn is your job number.
	/NOBINARY	prevents generation of an object (binary) file. Use this switch along with /LIST or /CREF to allow these switches to take effect without producing a new object file.
	/NOCOMPILE	prevents compilation if the associated object file is current; otherwise it forces compilation. Cancels the /COMPILE or /RELOCATABLE switch. Default
	/NOCREF	same as /NOCROSS-REFERENCE.
	/NOCROSS-REFERENCE	prevents the creation of a cross-reference file. Default
	/NODEBUG	excludes special debugging information from your object file. Default
	/NOFLAG-NON-STANDARD	prevents the flagging of non-standard syntax in the file. Default
	/NOLIBRARY	same as /NOSEARCH.
	/NOLIST	prevents a line printer listing of the program. Default
	/NOMACHINE-CODE	prevents generation of a file containing machine code. Default
	/NOOPTIMIZE	prevents the generation of a globally optimized object file (for FORTRAN programs only). Default
	/NOSEARCH	requires all modules in the object file library (the file accompanied by this switch in the command line) to be loaded even if they are not called by your program. Cancels the /SEARCH switch. Default
	/NOSTAY	stops the compiler from being placed in a background fork. Use when /STAY is set as a default for the compiler.

LOAD (Cont.)

	/NOSYMBOLS	prevents a symbol table from being loaded along with the object file.
	/NOWARNINGS	prevents display of warnings for nonfatal errors.
	/OPTIMIZE	calls for generation of a globally optimized object file, that is, one that runs as quickly as possible (for FORTRAN programs only, and only if you do not also give the /DEBUG switch).
	/PASCAL	compiles the file using the PASCAL compiler. Default for files of type .PAS
	/RELOCATABLE	identifies the input file as an object file (regardless of its extension) and prevents compilation of the source file, /RELOCATABLE switch forcing use of an existing object file even if the object file is out of date. Default for files of type .REL
	/SAIL	compiles the file using the SAIL compiler. Default for files of type .SAI
	/SEARCH	requires that the object file library (the file accompanied by this switch in the command line) be searched for modules called by your program or by a program subroutine. Only these modules are loaded, along with modules called from the system libraries, which are always searched.
	/SIMULA	compiles the file using the SIMULA compiler. Default for files of type .SIM
	/SNOBOL	compiles the file using the SNOBOL compiler. Default for files of type .SNO
	/STAY	returns your terminal to TOPS-20 command level so that you can perform other work while the system continues to load your program. You immediately receive the TOPS-20 prompt (@ or \$), and can then issue any user command. Be careful not to send incorrect data to programs expecting terminal input. (Refer to the CONTINUE command, Restrictions: Programs Competing for Terminal Input. This switch saves you from having to: issue a ^T to make sure loading has begun; give a ^C to halt the job; and issue a CONTINUE /STAY command to remain at command level during loading.
	/SYMBOLS	loads a symbol table along with the object file (helpful for debugging a program). Default
	/WARNINGS	displays warnings for nonfatal errors. Default

LOAD (Cont.)

Characteristics

Compiling New Sources Only

Before loading programs, the system ordinarily compiles any specified source (and only those sources) whose write date is more recent than that of the object file of the same name. You can override this action with the /COMPILE or /RELOCATABLE switch.

Using Standard File Types

If you specify source files with standard types (.FOR, .MAC, for example) in a LOAD command, the system automatically calls the appropriate compiler when compilation is necessary. If you specify source files by filename only, the system searches your connected directory for a file of this name and a standard type. To load programs from sources that have nonstandard file types, give a switch to indicate the proper compiler (/FORTRAN, /MACRO, /COBOL, or /ALGOL). A switch will take precedence over a standard file type if they indicate different languages. If no compiler is indicated with either a switch or a standard file type, the FORTRAN compiler is used.

Default Switches Not Passed to Compiler

Only switches specified in a LOAD-class command are passed to the compiler; default switches are not passed. Instead, the system assumes that the defaults for the compiler are the same as the defaults for the LOAD-class command.

Hints

Commas Between Filespecs

If you give two or more filespecs separated by commas as arguments to LOAD, the loaded programs exist in memory at the same time and will operate as a single program. You can use this feature to substitute one module for another under varying conditions or for different applications.

Plus Signs Between Filespecs

If you give two or more source filespecs separated by plus signs (+) as arguments to LOAD, they are compiled together as if they were a single file. Their object module is stored under any filename given as the "object" argument of the command, or (if none) under the last filename in the group and file type .REL.

Indirect Files as Arguments

You can store arguments (source and object filespecs, switches) of a LOAD command in an indirect file, and specify them by typing an at sign (@) and its filespec as a LOAD command argument.

LOAD (Cont.)

Establishing Default Arguments with the SET Command

You can issue the SET DEFAULT COMPILE-SWITCHES command to set up default global arguments to the LOAD command. Insert this SET command in your COMAND.CMD file to change your own defaults permanently.

Running Link Directly

The LOAD command automatically runs LINK, the system's linking loader, but if you require more control of the loading process you can run LINK directly. See the TOPS-20 LINK Reference Manual.

Using GET Instead of LOAD

If you have used the SAVE command to save your programs in executable format, you can use the GET command instead of LOAD to place them in memory. This is a faster and less expensive means of loading programs into memory.

Wildcards Illegal with LOAD

The LOAD command does not accept wildcard characters (* and %) in a file specification.

Warning - Generation Numbers, Long Filespecs

You must not give generation numbers when specifying source or object files; the system automatically uses the highest generation. Also, most compilers require filenames of 6 or fewer characters and file types of 3 or fewer characters.

Related Commands

COMPILE, EXECUTE, and DEBUG	other LOAD-class commands for performing related functions
SAVE	for saving the loaded program in an .EXE file
START	for starting the loaded program
SET DEFAULT COMPILE-SWITCHES	for establishing default switches for LOAD-class commands
INFORMATION DEFAULTS COMPILE-SWITCHES	for examining default switches established for LOAD-class commands

LOAD (Cont.)

Examples

1. Load an object file into memory.

```
@LOAD LSTSQ.REL
LINK:  LOADING

EXIT
```

2. Load the same program, allowing the system to update the object file if necessary.

```
@LOAD LSTSQ/FORTRAN
FORTRAN: LSTSQ
MAIN.
LINK:    LOADING

EXIT
```

3. Load a MACRO program and request a loader map or memory map. (Notice the filename of this map.)

```
@LOAD TEST2/MAP
MACRO:  FT
LINK:    LOADING

EXIT
@TDIRECTORY          WRITE
```

```
PS:<LATTA>
FT.MAP.1          6-APR-85 15:23:17
TEST2.REL
```

4. Load a COBOL program, forcing a new compilation that includes only the required modules. Request a map.

```
@LOAD /MAP TEST1/COMPILE, COBLIB/SEARCH
COBOL:  DBL [TEST1.CBL]
LINK:    LOADING

EXIT
```

5. Compile a program. Then load it, requesting a cross-reference listing this time. Finally, save the program in executable format.

```
@COMPILE TEST1/COBOL
COBOL:  DBL [TEST1.CBL]
@LOAD /COMPILE/CREF
COBOL:  DBL [TEST1.CBL]
LINK:    LOADING

EXIT
@SAVE
TEST1.EXE.1 SAVED
```

LOAD (Cont.)

6. Combine two FORTRAN sources into an object program under a new name. Start this program.

```
@LOAD LSTSQ+ABRR REGRES
FORTRAN: LSTSQ
MAIN.
MAIN.
LINK:    LOADING

EXIT
@START
```

7. Create an indirect file, and use it to load several modules at once. Request cross-reference files, then give the CREF command to turn these into listings.

```
@CREATE SERVTT.CMD
INPUT: PS:SERVTT.CMD.1
00100    HJRAD/COMPILE, FORLIB/SEARCH
00200    HJVTT/COMPILE, FORLIB/SEARCH
00300    HJINI/RELOCATABLE
00400    $
*E

[SERVTT.CMD.1]
@LOAD /CREF @SERVTT.CMD
FORTRAN: HJRAD
MAIN.
FORTRAN: HJVTT
MAIN.
LINK:    LOADING

EXIT
@CREF
CREF:    HJRAD
CREF:    HJVTT
@
```

LOGIN

Begins your timesharing job and connects you to your log-in directory.

Format

```
| @LOGIN /FAST (USER) name (PASSWORD) password (ACCOUNT)account -  
| (SESSION REMARK) remark  
  
| where  
  
| name          is your user name  
  
| pwd           is your secret password (which is not printed on  
|               your terminal)  
  
| acc           is an account name or number that you are authorized  
|               to use  
  
| remark        is an optional remark of up to 39 characters that  
|               identifies the terminal session for accounting  
|               purposes. Check with INFORMATION JOB-STATUS.  
|               Change with SET SESSION-REMARK.  
  
| /FAST         is an optional switch that prevents the following:  
|               processing of your LOGIN.CMD and COMAND.CMD files  
|               and the system's LOGIN.CMD and COMAND.CMD files,  
|               printing of system mail, and printing of the notice  
|               of new mail. (Your system manager may remove this  
|               switch from your system.)
```

Output

Acknowledgement of Valid Login

The system acknowledges a valid LOGIN command by printing your job number, terminal number, and the current date and time. In addition, it prints the date and time of your last login. You can use this information to determine if another user has learned your password and logged in to your account since the last time you logged out.

Note that a batch job automatically logs in and logs out of your account. The batch login sets the date and time of your last login and should not be confused with illegal access to your account.

Notice of User Mail and System Mail

When you log in, the system notifies you if another user has sent you a message with one of the system mail programs. The system then lists any system mail (mail sent by privileged users to all users) that has accumulated since your last login. Note that this mail appears in the log file if a batch job is run for you between the time the mail was sent and the time you logged in.

LOGIN (Cont.)

Output from Command Files

After a successful LOGIN, the system processes the LOGIN.CMD and COMAND.CMD files in the directory defined by logical name SYSTEM: and the command files in your login directory. The files are processed in this order:

1. SYSTEM:LOGIN.CMD
2. LOGIN.CMD
3. SYSTEM:COMAND.CMD
4. COMAND.CMD

The system displays any output from the commands in these files on your terminal. After execution of each command file, the system displays the message "End of file-name.CMD". If the last command in the command file is a TAKE command with no arguments, this message is not displayed.

Characteristics

Getting the Attention of the System

Before logging in, you may have to press any alphanumeric or special character to display the system herald or greeting and the @ prompt necessary for typing the LOGIN command.

If you are dialing in by telephone to a line declared autobaud by the system manager, this initial character enables the system to determine your terminal's speed setting, as long as the speed is 300, 1200, 1800, 2400, 4800, or 9600. Type a second character if the terminal's speed is 110 or 150. If your initial character(s) fails to get the system identification message, press the BREAK key twice, followed by another character(s).

Rights, Capabilities, and Charges

The LOGIN command gives you ownership rights to your log-in directory, and any group rights established for you on the public structure (usually named PS:). In addition, you are granted whatever capabilities (for example, Maintenance, Wheel) have been awarded to you, and can be sure that any charges you incur for the use of system resources, such as CPU time or the batch and printing systems, will be recorded to your user name.

LOGIN (Cont.)

Hints

Commands in Files Executed at Log-in Time

For Affecting Entire Session or Current Level Only

Commands that affect your entire job, for example, `TERMINAL` and `DEFINE`, belong in `LOGIN.CMD`. Commands that affect only the current level of `TOPS-20`, for example, many `SET` commands, must be put into `COMAND.CMD` if you want them to be executed automatically after every `PUSH` command as well as after `LOGIN`.

For Affecting Batch Jobs

As soon as one of your batch jobs logs in, the system processes the command files in the directory defined by logical name `SYSTEM:` and the command files in your login directory. The files are processed in this order:

1. `SYSTEM:BATCH.CMD`
2. `BATCH.CMD`
3. `SYSTEM:COMAND.CMD`
4. `COMAND.CMD`

Note that certain parameters of the batch job, for example, its time limit and the name of its log file, have already been set before these commands are executed. Such parameters are set either to values specified by switches in the `SUBMIT` command that starts the batch job, or to default values in effect for the job issuing this `SUBMIT` command. See also Hints - For Affecting Nested Batch Jobs, below.

Avoiding Duplicate Commands in Command Files

After executing a `SYSTEM:` command file, the system executes the file of the same name in your login directory. The `SYSTEM:` command files may contain commands that you already have in your own command files. To avoid executing the same commands twice, remove duplicate commands from your command files. To display a `SYSTEM:` command file, give the command `TYPE SYSTEM:file-name.CMD`.

For Affecting Nested Batch Jobs

By placing a `SET DEFAULT SUBMIT` command in your `BATCH.CMD` file, you cause these defaults to be in effect for a nested batch job, (a batch job started by a `SUBMIT` command within the control file of another of your batch jobs).

A Final TAKE Command

To suppress the display of the message "End of file-name.CMD" after execution of a command file, make the last command in the file a `TAKE` command with no arguments.

LOGIN (Cont.)

Simplifying Log-ins

By using the SET DIRECTORY ACCOUNT-DEFAULT command you cause subsequent LOGIN commands to require just your user name and password.

Special Cases

Commands You Can Issue Before Log-in

You can give these commands and arguments before logging in:

Command	Arguments
ATTACH	
BREAK	
DAYTIME	
INFORMATION	AVAILABLE COMMAND-LEVEL MAIL TERMINAL-MODE VERSION
LOGOUT	
SET	LATE-CLEAR-TYPEAHEAD TIME-LIMIT
SYSTAT	(except with subcommands LPT or OUTPUT)
TERMINAL	
UNATTACH	

Logging in to PTYs

You do not need to give a password when logging in under your own user name to a PTY (pseudo-terminal).

Must Log In Within Five Minutes

If you do not log in within five minutes of your initial CTRL/C, your job will be logged out automatically and you will have to type CTRL/C again.

Logging in to Last Available Job Slot

If you attempt to log in to the last available job slot, the system will not log you in but will send you an error message instead. This job slot is intended for users who wish to attach detached jobs using the ATTACH command. To log in a new job you must wait until a current user logs out.

LOGIN (Cont.)

Related Commands

ATTACH	for joining to your terminal a job that has already been logged in
INFORMATION DIRECTORY	for displaying the date and time that you started the current terminal session with LOGIN.
LOGOUT	for ending your timesharing job
SET ACCOUNT	for changing your account during a terminal session
SET DIRECTORY ACCOUNT-DEFAULT	for specifying a default account for subsequent log-ins
SET SESSION-REMARK	for making or changing your session remark during a terminal session

Examples

1. Log in, using account 341 and automatically executing the system LOGIN.CMD file and your LOGIN.CMD file.

```
@LOGIN C.RYDER 341
Job 39 on TTY41 8-Mar-85 11:04:21, Last Login 7-Mar-85 08:32:15
End of SYSTEM:LOGIN.CMD.1
End of LOGIN.CMD.1
```

2. Log in using the default account number and the /FAST switch.

```
@LOGIN /FAST C.RIDER
Job 39 on TTY41 8-Mar-85 11:10:34, Last Login 8-Mar-85 11:04:21
```

3. Type a character to get the TOPS-20 herald, then log in, using account 341 and inserting a session remark. Give INFORMATION JOB-STATUS as your first command, to see this session remark.

```
BOSTON (KL2871), Development System, TOPS-20 Monitor 6.1(7)
@LOGIN URQUHART 341 DEBUG ACCOUNT.PAS
Job 42 on TTY29 8-Mar-85 09:15:15, Last Login 7-Mar-85 09:20:32
@INFORMATION JOB-STATUS
Host AURORA
Job 42, TTY29, User URQUHART
Account 341 Session Remark:DEBUG ACCOUNT.PAS
```

LOGOUT

Ends a timesharing job.

Format

| @LOGOUT /FAST n

| where

| /FAST is an optional switch that prevents processing of your
| LOGOUT.CMD and the system's LOGOUT.CMD files.

| n is an optional job number. Specify n only when logging out
| a job other than your attached job.

Output

System Use Under Current Account

The system acknowledges a valid LOGOUT command by printing your job number, user name, current account, terminal number, and the current date and time. Then it shows the total amount of CPU time you used during the terminal session and the total length of time you were logged in, followed by the account of CPU time used under the current account and the length of time you were logged in under this account.

LOGOUT.CMD Output

| Before logging you out, the system processes the commands in
| your login directory's LOGOUT.CMD file and the system's
| LOGOUT.CMD file and displays any output from these commands.
| Then, after execution of each file, the system displays the
| message End of LOGOUT.CMD, unless the last command in the
| file is a TAKE command.

Characteristics

Expunging Your Log-in and Connected Directories

Before logging you out, the system expunges any deleted files from your log-in and connected directories, and prints a message if either directory is still exceeding its assigned permanent disk quota.

LOGOUT (Cont.)

Logging Out Other Jobs

By specifying a job number you can log out any other job logged in under the same user name as your attached job. A user with Wheel or Operator capabilities enabled can log out any job on the system. Whenever you log out another job, the system prints the job's user name, terminal number, and current program. You must then confirm the LOGOUT command with an extra RETURN.

When a job is logged out by another job, the logout command files are not processed.

Hints

A Final TAKE Command

To suppress the display of the message "End of LOGOUT.CMD" after execution of your LOGOUT.CMD file, make the last command in the file a TAKE command with no arguments. Be sure the file contains only one RETURN after the TAKE command.

Errors in LOGOUT.CMD

If there is an error in a command in your LOGOUT.CMD file, the system processes the commands up to the one in error and cancels the LOGOUT command. To log out, correct the error in the command file or give the LOGOUT command with the /FAST switch.

Effect on Memory and Terminal

The LOGOUT command clears memory and leaves your terminal in the state before log-in. LOGOUT n does not affect memory and leaves your terminal at TOPS-20 command level.

Related Commands

DETACH	for disengaging a job from your terminal without ending the job
LOGIN	for beginning your timesharing job
UNATTACH	for disengaging a job from another terminal without ending the job

LOGOUT (Cont.)

Examples

1. Log out your job.

@LOGOUT

End of SYSTEM:LOGOUT.CMD.2

End of LOGOUT.CMD.5

Killed Job 18, User C.RYDER, Account 341, TTY 233,
at 8-Mar-84 16:25:46, Used 0:0:5 in 1:2:16

2. Log out your job, receiving a warning message that your directory is over its storage quota.

@LOGOUT

<URQUHART> Over permanent storage allocation by 8 page(s).

Killed Job 39, User URQUHART, Account 341, TTY 41
at 8-Mar-84 16:33:12, Used 0:0:1 in 0:1:5

3. Check what jobs are logged in under your user name. Log out a detached job and verify that it is gone, then log out your attached job.

@SYSTAT WALKER

18 DET EXEC WALKER

21* 31 SYSTAT WALKER

@LOGOUT 18

User WALKER, Detached, running EXEC

[Confirm]

@SYS WALKER

21* 31 SYSTAT WALKER

@LOGOUT

Killed Job 43, User WALKER, Account 341, TTY 226,
at 8-Mar-84 16:35:16, Used 0:0:1 in 0:1:1

MERGE

Places an executable program into the current fork, combining it with whatever program (if any) is already there.

Format

| @MERGE (PROGRAM) filespec /switch

where

filespec is the file specification of any executable program
Default file type - .EXE

/switch is one or more of the following:

| /OVERLAY allows pages of the DDT program
| to be loaded over pages occupied
| by the existing program in
| memory.

/USE-SECTION:n specifies the memory section
(from 0 to 37 octal) into which
your program is to be merged.
You can use this switch only if
your program can be contained in
one section.

Characteristics

Executable Files Only

If a program you try to merge is not in executable format, you may get an immediate error message (that is, "?UNEXPECTED END-OF-FILE TRAP...") or a delayed one (that is, "?ENTRY VECTOR LENGTH IS NOT LESS THAN 1000") after the merge. In either case, be sure that you have specified an executable program before investigating further. The MERGE command does not alter the entry vector if the file being merged is in the proper .EXE format.

Existing Pages Not Overlaid

| If there is a program already in memory when you give the
| MERGE command, and pages of the new program overlay it, the
| new program is not placed into memory, and the system prints
| the error message, "?Illegal to overlay existing pages." To
| force the existing pages to be overlaid, reissue the MERGE
| command using the /OVERLAY switch.

Effect on Memory

| The MERGE command combines the specified program with the program
| in the current fork. It does not affect the contents of the
| current fork unless you specify the /OVERLAY switch.

MERGE (Cont.)

Related Commands

INFORMATION MEMORY-USAGE	for examining the contents of memory
GET	for putting a saved (executable) file into memory
SAVE	for storing a copy of the program in the current fork in a file in executable format
START	for starting the program in memory

Examples

1. Merge an executable program into memory.

```
@MERGE TESTF1.EXE
```

2. Place an executable system program in memory, then merge a system debugging program with it. Give INFORMATION MEMORY-USAGE commands to verify that both programs are intact.

```
@GET SYS:DUMPER  
@INFORMATION MEMORY-USAGE
```

```
34. pages, Entry vector loc 4715 len 3
```

```
Section 0      R, W, E, Private  
0             RANDOM:<NEXT-RELEASE>DUMPER.EXE.4 1 R, CW, E  
4-44          RANDOM:<NEXT-RELEASE>DUMPER.EXE.4 2-42 R, CW, E  
@MERGE SYS:UDDT  
@INFORMATION MEMORY-USAGE
```

```
45. pages, Entry vector loc 4715 len 3
```

```
Section 0      R, W, E, Private  
0             RANDOM:<NEXT-RELEASE>DUMPER.EXE.4 1 R, CW, E  
4-44          RANDOM:<NEXT-RELEASE>DUMPER.EXE.4 2-42 R, CW, E  
764-767       RANDOM:<NEXT-RELEASE>UDDT.EXE.1 1-4 R, CW, E  
770-776       RANDOM:<NEXT-RELEASE>UDDT.EXE.1 5-13 R, E
```

MODIFY

Adds or changes switches for a request placed in a batch or output queue.

Format

@MODIFY (REQUEST TYPE) queue (ID) identifier /switch(es)

where

queue is the waiting list in which you placed the original request, chosen from the following list:

BATCH	for requests made using the SUBMIT command
CARDS	for requests made using the PUNCH CARDS command
PAPER-TAPE	for requests made using the PUNCH PAPER-TAPE command
PLOT	for requests made using the PLOT command
PRINT	for requests made using the PRINT command

In the switch summary and descriptions, the word Output in the column headed Applicable Queues means all queues except the batch queue.

identifier is one of the following:

request ID number	the unique identifier assigned by the system to your request. This is the number appearing under the heading "Req#" in the list of requests shown by the INFORMATION BATCH-REQUESTS or INFORMATION OUTPUT-REQUESTS command.
jobname	the jobname of the request, either the first six characters of the first filename in the request, or the argument you supplied to a /JOBNAME switch when making the original request. This is the name appearing under the heading "Job Name" in the list of requests shown by the INFORMATION BATCH-REQUESTS or INFORMATION OUTPUT-REQUESTS command.

MODIFY (Cont.)

/JOBNAME:jobname switch showing the jobname of the request to modify. You can specify a particular jobname when making the original request. See Special Cases - /JOBNAME Switch, below.

/SEQUENCE:sequence number switch showing the sequence number of the request to modify. You can specify a particular sequence number when making the original request.

Use an asterisk (*) as identifier to modify all your requests in the specified queue.

/switches are keywords, chosen from the list below, specifying the parameter you want to change (and, where applicable, the new value of this parameter)

Summary of MODIFY Command Switches

Switch	Applicable Queues		
/AFTER:date and/or time			All
/BEGIN:n			All
/CARDS:n		BATCH	
/COPIES:n			Output
/DELETE	PRINT	BATCH	
/DEPENDENCY-COUNT:n		BATCH	
/DESTINATION-NODE:node name::			All
/FEET:n		BATCH	
ASCII	PRINT		
COBOL	PRINT		
/FILE:ELEVEN	PRINT		
FORTRAN	PRINT		
/FORMS:forms name			Output
/GENERIC			Output
/HEADER			Output
/JOBNAME:jobname			All
/LIMIT:n	PRINT		
/LOWERCASE	PRINT		
/MODE:output mode			Output
/NOHEADER			Output
/NOTE:12-character message			Output
ALWAYS		BATCH	
/OUTPUT ERRORS		BATCH	
NOLOG		BATCH	
/PAGES:n		BATCH	
/PRIORITY:n			All
/PROCESSING-NODE:node name		BATCH	
/REPORT:title	PRINT		
NO			
/RESTARTABLE:YES		BATCH	

MODIFY (Cont.)

Switch	Applicable Queues	
/SEQUENCE:n		All
SINGLE		
/SPACING:DOUBLE	PRINT	
TRIPLE		
/TIME:hh:mm:ss		All
/TPLOT:n	BATCH	
0 or NO		
/UNIQUE:1 or YES	BATCH	
/UNIT:octal number		Output
/UPPERCASE	PRINT	
/USER:user name		All

MODIFY Command Switches

Applicable Queues	
/AFTER:date and/or time, or day of week (or TODAY) and/or time	<p>All ensures that the request will not be processed until after the revised date and/or time specified. NOV-12-79, and 18:00 illustrate two arguments to this switch. If you give both date and time, separate them with a space. When given alone, the time may be preceded by a plus sign (+), which will delay processing by the indicated length of time from the present.</p> <p>Alternatively, you can give a day of the week (e.g., MONDAY) or TODAY as argument; then the job will not be printed until the beginning of the following day. If you follow this argument with a plus sign and a time, the job will be further delayed by this amount.</p>

MODIFY (Cont.)

/BEGIN:n	All	gives the decimal line number of the control file at which processing is to begin (for BATCH), or the decimal page number of the file at which the output is to begin (for CARDS, PAPER-TAPE, PLOT, and PRINT)
/CARDS:n	BATCH	specifies the decimal number of spooled cards the job is allowed to punch
/COPIES:n	Output	tells how many copies of the file to produce
/DELETE	All	deletes the file after processing. Opposite of /PRESERVE.
/DEPENDENCY-COUNT:n	BATCH	sets the request's dependency count to the new value n. This switch can also be followed by a signed value, i.e., +n or -n, which will increase or decrease the old value by the specified amount. A batch request is not processed until its dependency count is 0. See the <u>TOPS-10/20 Batch Reference Manual</u> for more information about dependency counts.
/DESTINATION-NODE:node-name	All	specifies the node on whose line printer the log file of your batch job is to be printed (for BATCH), or the node on whose line printer or other output device your request is to be processed (CARDS, PAPER-TAPE, PLOT, and PRINT). Two colons (:) following the node name are optional.
/FEET:n	BATCH	specifies the decimal number of feet of spooled paper tape the job is allowed to punch

MODIFY (Cont.)

ASCII COBOL /FILE:ELEVEN FORTRAN	PRINT	specifies that the file consists of ASCII text, or COBOL SIXBIT text; or (ELEVEN) contains four eight-bit bytes in each 36-bit word; or is FORTRAN ASCII text, where column 1 of each line is interpreted as a carriage control character.
/FORMS:forms name	Output	specifies, in six or fewer characters, new forms (determining the size of banner, header, and trailer sections; the paper color, width, and weight; vertical format, carriage control tape, the number of plotter steps per inch, etc.) to use with the job
/GENERIC	Output	allows the output to be produced on any available device. Use along with argument PRINT to cancel the /LOWERCASE or /UPPERCASE switch, or with PLOT, PRINT, CARDS, or PAPER-TAPE to cancel the /UNIT switch.
/HEADER	Output	causes a header section containing the jobname to be plotted, printed, or punched before the file itself is produced
/JOBNAME:jobname	All	does not change the jobname, but specifies which job to modify. Same as jobname in "identifier" argument.
/LIMIT:n	Output	places a new limit of n cards, feet, or pages on the output of the job
/LOWERCASE	PRINT	specifies that the file is to be produced on a line printer capable of printing lowercase characters

MODIFY (Cont.)

ASCII BCD /MODE: BINARY IMAGE	CARDS	designates the mode for punching the file onto cards. See the /MODE switch in the PUNCH command description for details.
ASCII BINARY /MODE: IMAGE IMAGE-BINARY	PAPER-TAPE	designates the mode for punching the file onto paper tape. See the /MODE switch in the PUNCH command description for details.
ASCII /MODE: BINARY IMAGE	PLOT	designates the mode for plotting the file. See the /MODE switch in the PLOT command description for details.
ARROW ASCII /MODE: OCTAL SUPPRESS	PRINT	designates the mode for printing the file. See the /MODE switch in the PRINT command description for details.
/NOHEADER	Output	prevents a header section containing the jobname from being produced before the file is produced.
/NOTE: message	Output	labels the header section of output, i.e., the section displaying the jobname, with a message or notation of up to 12 characters. The message must be enclosed in double quotation marks if it contains spaces or punctuation characters.
ALWAYS /OUTPUT: ERRORS NOLOG	BATCH	says whether you want the log file to be printed always, or only in the case of unhandled errors occurring within the job, or never. No matter which option you choose, the log file is always created.

MODIFY (Cont.)

/PAGES:n	BATCH	specifies the decimal number of spooled line printer pages the job is allowed to print
/PRESERVE	All	saves the file after it is processed. Opposite of /DELETE.
/PRIORITY:n	All	assigns a new number n reflecting the urgency of the request. This n must be from 1 to 63, with larger numbers receiving earlier treatment.
/PROCESSING-NODE:node name::	BATCH	specifies the IBM host system on whose CPU the JCL batch job is to be run. The node name must be of six or fewer characters and must be followed by two colons (::).
/REPORT:title	PRINT	scans your files and processes only those lines whose first characters are the title you give. This title can contain up to 12 characters (including the quotation marks that must enclose the title if it contains spaces). The switch is used along with the COBOL report writer.
NO /RESTARTABLE:YES	BATCH	specifies whether the job should be started again if the system crashes and restarts.
/SEQUENCE:n	All	does not change the sequence number of the job but rather specifies which job to modify. Giving this switch is an alternative to supplying a request ID as the request identifier when you have several jobs with the same jobname (if you supply only the jobname to identify the job, the MODIFY command affects all of them).

MODIFY (Cont.)

DOUBLE /SPACING:SINGLE TRIPLE	PRINT	determines the spacing between printed lines
/TIME:hh:mm:ss	BATCH	revises the limit for the maximum amount of CPU time available to the job; given in hours, minutes, and seconds.
/TPLOT:n	BATCH	limits to n the maximum number of minutes of spooled plotter time allowed for the job
NO or 0 /UNIQUE:YES or 1	BATCH	changes your declaration, if two or more jobs are submitted from the same connected directory, whether they must run at separate times
/UNIT:octal number	Output	directs your request to the line printer of the specified octal unit number
/UPPERCASE	PRINT	specifies that the file is to be produced on a line printer that uses uppercase characters only
/USER:user name	PRINT, BATCH	specifies the user whose request is to be modified; for privileged users only.

Characteristics

MODIFY Effective Only Before Processing

The MODIFY command affects a batch or output request only before processing has begun. After processing has begun, you can only cancel the request with the CANCEL command, and then make a new request.

MODIFY (Cont.)

Hints

Using the /DEPENDENCY-COUNT Switch

You can use the /DEPENDENCY-COUNT switch to specify the order in which your batch jobs are processed. Set the dependency count of all but the first job to some positive value when you submit them, and include MODIFY commands in each job's control file to bring the next job's dependency count to 0 at the appropriate time. See Example 4.

Special Cases

/JOBNAME Switch

In the singular case when you want to modify several queue requests of the same jobname using only one command, and that jobname is purely numerical (e.g., 5045), you must use the /JOBNAME:jobname switch as second argument to the MODIFY command. Do not also give the request ID or jobname as a command argument if you give the /JOBNAME:jobname switch.

Related Commands

CANCEL	for removing batch and output requests
INFORMATION BATCH-REQUESTS	for examining entries in the batch queue
INFORMATION OUTPUT-REQUESTS	for examining entries in the output queues
PLOT	for placing requests in a plotter output queue
PRINT	for placing requests in a line printer output queue
PUNCH	for placing requests in a card punch or paper tape punch output queue
SUBMIT	for placing requests in the batch input queue

MODIFY (Cont.)

Examples

1. Modify a batch request (of jobname ARTIFI) to make it start more quickly.

```
@MODIFY BATCH ARTIFI /PRIORITY:63  
[1 Job modified]
```

2. Modify a print request (of jobname PHIAL) to include a note on the header page.

```
@MODIFY PRINT PHIAL /NOTE:"DUE: 11/4"  
[1 Job modified]
```

3. Modify one job of several having the same jobname.

```
@INFORMATION OUTPUT-REQUESTS /USER
```

Printer Queue:

Job Name	Req#	Limit	User
PRTSK	226	27	LATTA /After: 8-Nov-84 17:00
PRTSK	236	27	LATTA /After: 8-Nov-84 17:00
PRTSK	237	27	LATTA /After: 8-Nov-84 17:00
PRTSK	238	27	LATTA /After: 8-Nov-84 17:00
TESTF1	219	54	LATTA /Forms:NARROW

/After:8-Nov-84 17:00

There are 5 jobs in the queue (none in progress)

```
@MODIFY PRINT 237 /AFTER:18:00  
[1 Job modified]
```

MODIFY (Cont.)

4. Use the TYPE command to examine some of your control files. (Notice the use of the MODIFY command within these files to ensure that they are processed in a certain order when submitted together.) Submit these three control files and verify their placement in the batch input queue.

```
@TYPE ARVM%.CTL
ARVM1.CTL.2
```

```
@RUN TESTF1
@PRINT TESTF1.RSM
@MODIFY BATCH ARVM2 /DEPENDENCY-COUNT:0
```

```
ARVM2.CTL.2
```

```
@RUN TESTF2
@PRINT TESTF2.RSM
@MODIFY BATCH ARVM3 /DEPENDENCY-COUNT:0
```

```
ARVM3.CTL.2
```

```
@RUN TESTF3
@PRINT TESTF3.RSM
@PRINT SUMJOB.RSM
@SUBMIT /AFTER:17:00 ARVM1
[Batch job ARVM1 queued, request-ID 240, limit 0:05:00]
@SUBMIT /DEPENDENCY-COUNT:1 ARVM2
[Batch job ARVM2 queued, request-ID 241, limit 0:05:00]
@SUBMIT /DEPENDENCY-COUNT:1 ARVM3
[Batch job ARVM3 queued, request-ID 242, limit 0:05:00]
@INFORMATION BATCH-REQUESTS /ALL/USER
```

Batch Queue:

Job Name	Req#	Run Time	User
ARVM1	240	00:05:00	LATTA /After: 8-Nov-84 17:00
			/Uniq:Yes /Restart:No /Assist:Yes /Seq:1804
ARVM2	241	00:05:00	LATTA /Dep:1 /Uniq:Yes /Restart:No
			/Assist:Yes /Seq:1805
ARVM3	242	00:30:00	LATTA /Dep:1 /Uniq:Yes /Restart:No
			/Assist:Yes /Seq:1806

There are 3 jobs in the queue (none in progress)

MOUNT

Requests that a specified file structure or magnetic tape set be made available for your job's use.

Format

@MOUNT medium (NAME) dev: /switch(es)

where

medium is one of the following:

STRUCTURE - for mounting file structures (disk packs)

TAPE - for mounting magnetic tapes

dev: is either the structure identification (or alias), or the tape setname. The colon after the device name is optional.

/switches are keywords, chosen from the list below, indicating your choice of MOUNT command options

Summary of MOUNT Command Switches (defaults in boldface)

/CHECK-SETNAME

200

556

800

/DENSITY:1600

6250

SYSTEM-DEFAULT

7-TRACK

/DRIVE-TAPE:9-TRACK

ANSI

BYPASS

/LABEL-TYPE:EBCDIC

TOPS-20

UNLABELED

/NEW

/NOUNLOAD

/NOWAIT

/OPERATOR

/PROTECTION:octal protection code

/READ-ONLY

Default code - 770000

Default - unless /NEW or

/SCRATCH specified

MOUNT (Cont.)

```

/REMARK:119-character remark
/SCRATCH
      NUMBER number
/START:VOLID volid                      Default number - 1

/STRUCTURE-ID:structure identification
/VOLIDS:list of volids
/WRITE-ENABLED                          Default - if /NEW or /SCRATCH
                                         specified

```

The switches /NOWAIT and /REMARK are useful with either the STRUCTURE or TAPE medium, while /STRUCTURE-ID is for STRUCTURE only; the other switches are for TAPE only.

MOUNT Command Switches

/CHECK-SETNAME	ensures that the setname of the mounted tapes matches the setname you specify as the "dev:" argument to the MOUNT command; otherwise an error will be generated. For labeled tapes only.
<pre> 200 556 800 /DENSITY:1600 6250 SYSTEM-DEFAULT </pre>	<p>specifies the density, in bits per inch, at which the tape set is to be read or written. Densities 200 and 556 are for unlabeled tapes only. SYSTEM-DEFAULT, one of the values shown (usually 1600), is established at system start-up time.</p>
<pre> 7-TRACK /DRIVE-TYPE:9-TRACK </pre>	<p>specifies the type of drive on which the tape set is to be mounted. Labeled tapes must be mounted on 9-track drives.</p>
<pre> ANSI BYPASS /LABEL-TYPE:EBCDIC TOPS-20 UNLABELED </pre>	<p>tells the system to read and write the tape set according to the specified label standard: ANSI; EBCDIC - IBM TYPES (IN READ-ONLY MODE); TOPS-20 - a superset of ANSI used in TOPS-20 systems; UNLABELED - for unlabeled tapes only. BYPASS (for privileged users only) lets you read and write any tape, labeled or unlabeled, without any label processing.</p>

MOUNT (Cont.)

`/NEW`

tells the system that you are creating a new file set on an existing tape set, whose setname is then changed to be the name you specify as the `dev:` argument to the MOUNT command. (If the tape set has more than one volume, remember to specify their volids using the `/VOLIDS` or `/OPERATOR` switch.) The `/CHECK-SETNAME` and `/READ-ONLY` switches are ignored if present, and `/WRITE-ENABLED` is assumed. Do not give the `/START` switch if you give `/NEW`.

`/NOUNLOAD`

asks the system not to unload a volume (reel) of tape from its tape drive when the drive is released by a volume switch (change of volumes required by a read or write operation) or DISMOUNT command. Use this switch to facilitate processing when sufficient drives are available.

`/NOWAIT`

tells the system to return your terminal to TOPS-20 command level as soon as you give the MOUNT command, and to send a message to your terminal when the request has been processed. Otherwise, your terminal waits for the message.

`/OPERATOR`

asks the operator to specify to the system the volids of the tape set you wish to mount. Do not use if you have given the `/VOLIDS` switch.

`/PROTECTION:code`

specifies a 6-digit octal protection code for new volumes of tape written during the current mount request. The owner always has full access to his tapes, so the first two digits are always interpreted as "77"; also, user groups and directory groups have no effect on tape access, so the middle two digits are always interpreted as "00". Therefore, although six digits can be specified, only the last two digits affect the tape's protection code.

MOUNT (Cont.)

(If you specify only two digits, these will be used as the last two digits of the protection code.) These two digits should be the sum of the values corresponding to the modes of access you want to allow, chosen from the following list:

40 - read files in the file set

10 - overwrite or modify files in the file set

04 - append files to the end of the file set

For tapes of label-type TOPS-20 only.

Default code - 770000

/READ-ONLY

ensures that all volumes in the tape set will be mounted without write rings, to prevent accidental erasures

Default except when /NEW or /SCRATCH is specified

/REMARK:"remark"

sends the specified remark to the operator when he is notified of your mount request. The text of the remark must be enclosed in quotation marks (" ") and can be up to three, 80-character lines long (including the MOUNT command line). Note that while the entire remark is displayed on the operator's terminal, only the first line appears in the INFORMATION MOUNT-REQUESTS display.

For structures, the remark will be sent only if the structure must be put on line or physically mounted to satisfy your mount request.

/SCRATCH

same as /NEW, except that the volumes in the file set you create will be drawn from the pool of scratch tapes (tapes not presently owned by a particular user), rather than from volumes you specify. Use this switch to create a new file set when you are not supplying the volumes of tape to be used.

MOUNT (Cont.)

NUMBER number
/START:VOLID volid

tells the system which volume (reel) of tape to mount first when satisfying your request. (You must also give the /VOLIDS switch, specifying the group of volumes you will be using.) Use the NUMBER argument to give the order of this volume within the group (e.g., 1 for first, 2 for second), or give the VOLID argument to repeat the volid explicitly. You can use this switch to save time and expense when you know which volume you will be using first.

Default - NUMBER 1

/STRUCTURE-ID:structure
 identification

gives the name of the structure as recorded in the disk(s); used when you gave an alias different from the structure identification as argument "dev:", above. See Hints - Using the /STRUCTURE-ID Switch, below. For privileged users only.

/VOLIDS:volid, volid,...

specifies the volids (volume identifiers) of the volumes (reels) of tape you want to access. These must be consecutive volumes, usually of the tape set specified as the "dev:" argument to the MOUNT command. Although you need not specify every volume in the set, any volume not specified will not be accessible. Do not use this switch if you have given the /OPERATOR switch. See also Characteristics - Using the /VOLIDS Switch, below.

/WRITE-ENABLED

ensures that all volumes in the tape set will be mounted with write rings

Default when /NEW or /SCRATCH is specified

MOUNT (Cont.)

Characteristics

Action of MOUNT STRUCTURE Command

If the Structure Has Already Been Mounted

If the structure for which you give the MOUNT command is currently mounted, the system simply increases by 1 the mount count, i.e., the number of users who have given the MOUNT but not the DISMOUNT command for the structure, and returns your terminal to TOPS-20 command level. A structure is not ordinarily dismounted until its mount count is 0.

If the Structure Has Not Yet Been Mounted

If the structure for which you give the MOUNT command is not currently mounted, your request stays in the mount request queue until it is acted upon by the operator or until you cancel the request.

Setnames (File Set Identifiers)

The setname, or file set identifier of a set of tapes, is part of the label information written into each volume of the set. It is rewritten every time the /NEW or /SCRATCH switch is included in a MOUNT command. The "dev:" argument of the MOUNT command becomes the setname in this case. If you add volumes to an existing tape set, the system uses the setname of the old volumes as the setname of the new ones.

Using the /CHECK-SETNAME Switch

If you give the MOUNT command to use an existing file set (i.e., you do not specify the /NEW or /SCRATCH switch), you can give the /CHECK-SETNAME switch to be sure that the setname written on the tapes matches the setname you specify as the "dev:" argument to the MOUNT command. However, because more than one set of tapes can have the same setname, the /CHECK-SETNAME switch does not ensure that the correct tape set will be mounted. For information about ensuring that the correct tapes are mounted, see Characteristics - Using the /VOLIDS Switch, below.

Volids (Volume Identifiers)

The volid, or volume identifier of a volume (reel) of labeled tape, is part of the label information written into each volume of tape. It is written only once, by the operator during the tape's initialization procedure, and is not changed during the life of the tape. (You should also affix a paper label displaying the volid onto each reel of tape.) You can get a list of volids for previously specified or newly written volumes in any mounted tape set by giving the INFORMATION VOLUMES command for that set.

MOUNT (Cont.)

Using the /VOLIDS Switch

If you give the MOUNT command to use an existing multi-volume tape set (i.e., you do not specify the /SCRATCH switch), you can give the volid of each volume you want to use as an argument to the /VOLIDS switch. The system ensures that the correct volumes of a labeled tape will be mounted for your job as long as you use the /VOLIDS switch to specify them. (If the tape set does not consist of labeled tapes, the system does not ensure that the correct tapes are mounted.) The volids must represent consecutive volumes and must be specified in the order written (oldest first). Note that in general you cannot rely on any apparent alphanumerical order when specifying the volids but must maintain your own list of the volids in each tape set. (See Hints - Keeping Track of Volids, below.) You need not specify every volid in the tape set, but any volume not specified will not be accessible through the current MOUNT command. See also Characteristics - Using the /OPERATOR Switch, and Special Cases - Single-volume Tape Sets, below.

Using the /OPERATOR Switch

You can use the /OPERATOR switch instead of the /VOLIDS switch when asking the system to mount a multi-volume set of tapes. The /OPERATOR switch sends a message to the operator asking him to specify the volid of each volume himself. You must be sure to supply the operator with a list of the volids you want him to specify before giving a MOUNT command that contains the /OPERATOR switch.

Hints

Checking Whether Operator is Present

You can give the INFORMATION SYSTEM-STATUS command to find out whether the operator is in attendance and can process your mount request. Even if the operator is not in attendance, your request remains valid until he returns and deals with it in some way.

MOUNT (Cont.)

Using the /STRUCTURE-ID Switch

The /STRUCTURE-ID switch (available only to users with enabled Wheel or Operator capabilities) gives the name of the structure as recorded in the disk(s) of the structure itself, where it is used by the system for identification. Be sure that the structure identification is also written with a felt-tip marker on the upper surface of each disk pack, and on a gummed label on the pack cover. Unless you give this switch, the system mounts the structure with its structure identification as alias. (The alias is the name you use when specifying the structure in file specifications and commands; the INFORMATION STRUCTURE and INFORMATION AVAILABLE DEVICES commands list structures by alias only.) The /STRUCTURE-ID switch allows an enabled Wheel or Operator to mount a structure under a name different from the one recorded in the structure. Use this switch for mounting a structure whose structure identification is the same as the alias of a currently mounted structure. In such cases give the MOUNT STRUCTURE command with any unique alias as the "dev:" argument, and specify the structure identification with the /STRUCTURE-ID switch. In subsequent file specifications and commands referring to the structure, use the alias only.

Dummy "dev:" Arguments for Mounting Tapes

If you want to use different tape sets on successive runnings of a single program, you can refer to those tape sets as a logical name in the program, and use this logical name as the "dev:" argument of your MOUNT command when mounting tapes. As long as you also specify the volid of each volume of tape with the /VOLIDS switch (or use the /OPERATOR switch to ask the operator to do so), you need not give the actual setname of the tape set as the "dev:" argument to the MOUNT command. The system considers the "dev:" argument you supply to be a logical name defined as the mounted tape set. Therefore, your program can access the tape set using this logical name.

Keeping Track of Volids

Unless your site has a tape cataloging facility, you must keep your own record of the volids in each of your tape sets. After creating a file set on a new tape set, i.e., one not previously owned by you (by giving the MOUNT command and including the /SCRATCH switch), you should give the INFORMATION VOLUMES command for the set before giving the DISMOUNT command. The system will respond by printing a list at your terminal of the volids of all volumes in the tape set. Similarly, if you mount an old tape set and then perform write operations, you should give INFORMATION VOLUMES before giving DISMOUNT to learn the volids of any volumes added to the set. Keep an ordered list of these volids in a disk file in your directory, for use in subsequent MOUNT commands when you give the /VOLIDS switch.

MOUNT (Cont.)

Special Cases

Single-volume Tape Sets

If the tape set you want to mount consists of a single volume of tape, you need not give the /VOLIDS or /OPERATOR switch to specify its valid. You can give the valid as the "dev:" argument to the MOUNT command.

Structures Unavailable for Mounting

If the operator has given the OPR program command, SET STRUCTURE UNAVAILABLE for a specified structure, the system sends an error message including the phrase, "Structure unavailable for mounting" in response to subsequent MOUNT commands for the structure.

Restrictions

Using SET TAPE Commands

The TOPS-20 SET TAPE DENSITY and SET TAPE PARITY commands are applicable to unlabeled tapes only (but see also Warnings - /DENSITY Switch Has Limited Effect for Unlabeled Tapes, below). The SET TAPE FORMAT and SET TAPE RECORD-LENGTH commands are applicable to both labeled and unlabeled tapes, but to labeled tapes only if they are mounted using the /LABEL-TYPE:ANSI or /LABEL-TYPE:TOPS-20 switch. In addition, the files that you read from or write to such a labeled tape must be in 36-bit format, and they must not have the ;FORMAT attribute as part of their specification.

Warnings

POP Command Cancels Unsatisfied Mount Requests

If you have given a PUSH command to obtain a new level of TOPS-20 and then give a MOUNT command within that new level, a subsequent POP command will cancel your mount request. However, if the specified structure or tape set has already been mounted, it will remain mounted despite your POP command.

/DENSITY Switch Has Limited Effect for Unlabeled Tapes

The /DENSITY switch, when given in a MOUNT command for an unlabeled tape, ensures only that your tape set will be mounted on a drive that supports the specified density. It does not ensure that the tape set will be read or written at this density. To specify the density at which unlabeled tapes are to be read and written, give the SET TAPE DENSITY command.

MOUNT (Cont.)

Effect on Terminal

The MOUNT command with the /NOWAIT switch, leaves your terminal at TOPS-20 command level. If you have not given the /NOWAIT switch, your terminal waits until the system has processed your request, or to return to TOPS-20 command level. This CTRL/C does not cancel your request.

Related Commands

CANCEL	for withdrawing mount requests before they are processed.
DISMOUNT	for giving up access to a particular tape drive or disk drive
INFORMATION AVAILABLE DEVICES	for finding out just the names of structures available for mounting (these are listed after DSK and PS, and before the line printers (LPT, LPT0, etc.))
INFORMATION MOUNT-REQUESTS	for finding out information about pending mount requests for structures and tape sets, and about currently mounted tape sets
INFORMATION STRUCTURE	for finding out information about currently mounted structures
INFORMATION VOLUMES	for finding out the volids of all mounted volumes (including newly created volumes) of a tape set
SET TAPE commands	for establishing job-wide defaults for tape density, format, parity, and record length.

MOUNT (Cont.)

Examples

1. Mount a structure (it is already physically mounted).

```
@MOUNT STRUCTURE SNARK:  
Structure SNARK: mounted
```

2. Mount a structure that is not yet physically mounted. After completing the command, give CTRL/Cs to return to TOPS-20 command level.

```
@MOUNT STRUCTURE PYBL:  
[Mount Request PYBL Queued, Request-ID 205]  
[MOUNT request remaining in queue]  
^C
```

3. Mount a structure, then give CTRL/Cs to return to TOPS-20 command level and cancel the mount request.

```
@MOUNT STRUCTURE PYBL:  
[Mount Request PYBL Queued, Request-ID 136]  
[MOUNT request remaining in queue]  
^C  
@CANCEL MOUNT 136  
[1 mount request canceled]
```

MOUNT (Cont.)

4. Find out what structures are available for mounting (these are listed after DSK and PS and before the line printers), and mount one of these.

@INFORMATION AVAILABLE DEVICES

Devices available to this job:

DSK, PS, LANG, TYM, MISC, SNARK, REL4, LPT, LPT0
LPT1, CDR, CDP, PCDP0, FE0, FE4-15, PTY7-10
PTY23-61, NUL, PLT, PLT0, DCN, SRV

Devices assigned to/opened by this job: TTY220

@MOUNT STRUCTURE REL4: /NOWAIT

Structure REL4: mounted

5. Ask that a new tape set be created for you from scratch tapes, and copy some files to it. Before dismounting the tape set, find out the volids of the tape volumes you were assigned.

@MOUNT TAPE LAT: /SCRATCH/LABEL-TYPE:T0PS-20

[Mount Request LAT Queued, Request-ID 104]

[Tape set LAT, volume LAT mounted]

[LAT: defined as MT3:]

@COPY DN20A-11.SYS LAT:

DN20A-11A.SYS.1 => MT3:DN20A-11A.SYS.131071 [OK]

DN20A-11B.SYS.1 => MT3:DN20A-11B.SYS.131071 [OK]

DN20A-11C.SYS.1 => MT3:DN20A-11C.SYS.131071 [OK]

@INFORMATION VOLUMES LAT:

Volumes of tape set LAT: 01P02,00L16

@DISMOUNT TAPE LAT:

[Tape dismounted, logical name LAT: deleted]

6. Find out if any tape drives can be used without giving the MOUNT command (any such drives will be of the form MTAn). Assign one of these and use the PLEASE program to ask the operator to mount your (unlabeled) tape on this drive. Set the necessary tape parameters, position the tape, and copy a file from tape to the line printer. Then give up the resources you have been using.

@INFORMATION AVAILABLE DEVICES

Devices available to this job:

DSK, PS, LANG, TYM, MISC, SNARK, REL4, MTA5, LPT, LPT0, LPT1
CDR, CDP, PCDP0, FE0, FE4-15, PTY23-61, NUL, PLT
PLT0, DCN, SRV

Devices assigned to/opened by this job: TTY220

@ASSIGN MTA5:

@PLEASE

Enter text, terminate with CTRL/Z to wait for response,
or ESCape to send message and exit

PLEASE MOUNT MY TAPE NAMED UNBLD IN READ-ONLY MODE ON MTA5:,
WHICH I HAVE ASSIGNED TO MY JOB. MTA5: IS A 7-TRACK DRIVE
THAT SUPPORTS TAPE DENSITIES OF 800 BPI, CORRECT?

[PLSOPN Operator at GIDNEY has been notified at 14:34:26]

@SET TAPE DENSITY 800

@SET TAPE RECORD-LENGTH 128

@REWIND MTA5:

@SKIP MTA5: 4 FILES

@COPY MTA5: LPT:

MTA5: => LPT: [OK]

@UNLOAD MTA5:

@DEASSIGN MTA5:

MOUNT (Cont.)

7. Perform the same task using the same volume of tape as in the previous example by using the MOUNT command. Note that you still cannot specify a particular tape file by name when the tape is an unlabeled tape.

```
@MOUNT TAPE UNLBLD: /LABEL-TYPE:UNLABELED/DENSITY:800/DR -
I'VE-TYPE:7-TRACK
[Mount Request UNLBLD Queued, Request-ID 128]
[Tape set UNLBLD, volume UNLBLD mounted]
[UNLBLD: defined as MT3:]
@INFORMATION MOUNT-REQUESTS/USER
```

```
Tape/Disk Mount Queue:
Volume      Status  Type    Write   Req Name  Req#   Job#   User
-----
UNLBLD      MTA4    Tape    Locked  UNLBLD    128    55     LATTA
There is 1 Request in the Queue
@REWIND UNLBLD:
@SKIP UNLBLD: 4 FILES
@COPY UNLBLD: LPT:
  MT3:..4 => LPT: [OK]
@DISMOUNT TAPE UNLBLD:
[Tape dismounted, logical name UNLBLD: deleted]
```

8. Mount a labeled tape containing the same files as in the previous two examples, and perform the same task. Note that you need not specify tape parameters in this MOUNT command, as this information is present in the tape labels and is read automatically. Also, the system ensures that the correct volume of tape is used. Finally, you can specify the tape file by name when using labeled tapes.

```
@MOUNT TAPE LBLD: /LABEL-TYPE:ANSI/VOLIDS:00115
[Mount Request LBLD Queued, Request-ID 133]
[Tape set LBLD, volume 00115 mounted]
[LBLD: defined as MT3:]
@INFORMATION MOUNT-REQUESTS/USER
```

```
Tape/Disk Mount Queue:
Volume      Status  Type    Write   Req Name  Req#   Job#   User
-----
00115       MTA0    Tape    Locked  LBLD      133    55     LATTA
There is 1 Request in the Queue
@REWIND LBLD:
@COPY LBLD:COMPR.BRN LPT:
  MT3:COMPR.BRN.13107 => LPT:COMPR [OK]
@DISMOUNT TAPE LBLD:
[Tape dismounted, logical name LBLD: deleted]
```

MOUNT (Cont.)

- Mount a two-volume tape set (using the NOUNLOAD switch to simplify volume changes) and overwrite any existing files with new files. Then rewind the tape set. Give various INFORMATION commands as you proceed, to verify logical name and device assignments and to determine whether new volumes have been written.

@MOUNT TAPE LAT: /WRITE-ENABLED/NOUNLOAD/NOWAIT/VOL-
IDS:DBL01, DBL02

[Mount Request LAT Queued, Request-ID 19]

[Tape set LAT, volume DBL01 mounted]

[LAT: defined as MT0:]

@INFORMATION MOUNT-REQUESTS /USER

Tape/Disk Mount Queue:

Volume	Status	Type	Write	Req Name	Req#	Job#	User
DBL01	MTA1	Tape	Enabled	LAT	19	7	LATTA

There is 1 Request in the Queue

@INFORMATION AVAILABLE DEVICES

Devices available to this job:

DSK, PS, LANG, SNARK, NETWORK, REL4, MISC, PACKAG, MTA5
MT0, LPT, LPT0, LPT1, CDP, PCDP0, FE0, FE2-15, PTY13-61
NUL, PLT, PLT0, DCN, SRV

Devices assigned to/opened by this job: MT0, TTY217

@INFORMATION LOGICAL-NAMES JOB

LAT: => MT0:

SYS: => DSK:,SYS:

@REWIND LAT: /ENTIRE-VOLUME-SET

@COPY HLP:.HLP LAT:

PS:<HELP>ACCT20.HLP.1 => MT0:ACCT20.HLP.131071 [OK]

PS:<HELP>ACCTPR.HLP.1 => MT0:ACCTPR.HLP.131071 [OK]

.

.

.

PS:<HELP>WAIT.HLP.2 => MT0:WAIT.HLP.131071 [OK]

PS:<HELP>WATCH.HLP.6 => MT0:WATCH.HLP.131071 [OK]

@INFORMATION MOUNT-REQUESTS /USER

Tape/Disk Mount Queue:

Volume	Status	Type	Write	Req Name	Req#	Job#	User
DBL02	MTA3	Tape	Enabled	LAT	19	7	LATTA

There is 1 Request in the Queue

@INFORMATION VOLUMES LAT:

Volumes of tape set LAT: DBL01,DBL02

@REWIND LAT: /ENTIRE-VOLUME-SET

@INFORMATION MOUNT-REQUESTS /USER

Tape/Disk Mount Queue:

Volume	Status	Type	Write	Req Name	Req#	Job#	User
DBL01	MTA1	Tape	Enabled	LAT	19	7	LATTA

There is 1 Request in the Queue

MOUNT (Cont.)

10. (For privileged users only.) Enable your capabilities and call the OPR program, then give the PUSH command to OPR. (This action puts you at TOPS-20 command level, but allows you also to see the OPR messages caused by your TOPS-20 commands.) Repeat the write operations of the previous example, then dismount the tape set and exit from the OPR program. Notice that, because of the /NOUNLOAD switch in your original MOUNT command, both volumes of your tape set remain mounted on their drives. Therefore, you can mount the tapes again without operator assistance.

```
@ENABLE
$OPR
OPR>PUSH
```

```
TOPS-20 Command processor 6(7)
@REWIND LAT: /ENTIRE-VOLUME-SET
@COPY HLP: LAT:
PS:<HELP>ACCT20.HLP.1 => MT0:ACCT20.HLP.131071 [OK]
PS:<HELP>ACCTPR.HLP.1 => MT0:ACCTPR.HLP.131071 [OK]
.
.
PS:<HELP>CHKPNT.HLP.1 => MT0:CHKPNT.HLP.131071
15:11:55      --Tape Drive Released By User--
              MTA1: Volume DBL01 Remaining mounted on drive

15:11:57      --MTA3: Given to Request 19--
              Volume DBL02 now in use by
              User LATTA, Job 7, Terminal 217
[OK]
PS:<HELP>COBDDT.HLP.6 => MT0:COBDDT.HLP.131071 [OK]
.
.
PS:<HELP>WAIT.HLP.2 => MT0:WAIT.HLP.131071 [OK]
PS:<HELP>WATCH.HLP.6 => MT0:WATCH.HLP.131071 [OK]
@INFORMATION VOLUMES LAT:
Volumes of tape set LAT: DBL01,DBL02
@INFORMATION MOUNT-REQUESTS /USER
```

```
Tape/Disk Mount Queue:
Volume      Status      Type      Write      Req Name      Req#      Job#      User
-----
DBL02      MTA3          Tape      Enabled      LAT           19         7      LATTA
There is 1 Request in the Queue
```

```
@REWIND LAT: /ENTIRE-VOLUME-SET
15:14:51      --Tape Drive Released By User--
              MTA3: Volume DBL02 Remaining mounted on drive

15:14:51      --MTA1: Given To Request 19--
              Volume DBL01 now in use by
              User LATTA, Job 7, Terminal 217
```

MOUNT (Cont.)

```
@DISMOUNT TAPE LAT:
[Tape dismounted, logical name LAT: deleted]
15:15:21      --Tape Drive Released By User--
              MTA1: Volume DBL01 Remaining mounted on drive
@POP
OPR>EXIT
$DISABLE
```

11. Mount the same tape set as in the previous examples, but ask the operator to specify the volids. Use the PLEASE program to help you.

```
@MOUNT TAPE LAT: /WRITE-ENABLED/NOUNLOAD/NOWAIT/OPERATOR
[Mount Request LAT Queued, Request-ID 197]
@PLEASE
Enter text, terminate with CTRL/Z to wait for response,
or ESCape to send message and exit
PLEASE ENTER THE VOLIDS OF MY TAPE SET LAT: FOR
REQUEST 197. THEY ARE RECORDED IN YOUR TAPE
LIBRARY CATALOG. THANKS.
[PLSOPN Operator at GIDNEY has been notified at 14:34:26]
@INFORMATION MOUNT-REQUESTS /USER
```

Tape/Disk Mount Queue:

Volume	Status	Type	Write	Req Name	Req#	Job#	User
DBL01	Waiting	Tape	Enabled	LAT	197	65	LATTA

There is 1 Request in the Queue

PERUSE

Allows you to read a file using read-only editor commands.

Format

`@PERUSE (FILE) /switch(es) filespec`

where

`/switch(es)` are keywords which apply to the EDIT editor. For descriptions of these switches, see the /CREATE or EDIT commands in this manual.

`filespec` is the name of the file you want to read
Default - the last file specification and associated switches you gave in a CREATE, EDIT, or PERUSE command during the current terminal session

Characteristics

The PERUSE command runs the EDIT system program in read-only mode. (However, see Special Cases - Using an Editor Other than EDIT, below.) PERUSE is actually the same as the EDIT /READONLY command. In EDIT /READONLY mode you can use only EDIT program switches and commands that do not modify the file.

Hints

Avoid Accidental File Modification

Use PERUSE when it is important to avoid the risk of accidentally modifying a file.

PERUSE Line in SWITCH.INI

Add a line to your SWITCH.INI file for use with the PERUSE command. (See Example 3.)

Special Cases

Using an Editor Other than EDIT

The CREATE, EDIT and PERUSE commands in this manual assume that these commands call on the program EDIT. If your job uses another editing program, for example, EDT, the switches and examples shown here will not be applicable.

PERUSE (Cont.)

The Editor used by the CREATE, EDIT and PERUSE commands is specified by the logical name EDITOR:. You can find out the name of this program by giving the command, INFORMATION LOGICAL-NAMES EDITOR:. The job-wide definition (if any) will be given first, followed by the system-wide definition; the job-wide definition prevails if both exist. If the definition of EDITOR: is SYS:EDIT.EXE, the CREATE, EDIT and PERUSE commands will function as described in this manual. Otherwise, you must consult the appropriate manual (for example, the EDT20 Reference Manual) for information.

Restrictions

Listing Available EDIT Read-Only Switches and Commands

Many of the EDIT switches and commands that are displayed in response to a ? modify the file and do not function with PERUSE. If you give a file-modifying switch, the switch is ignored but no error message is displayed. If you give a file-modifying EDIT command, you receive the message %ILLEGAL COMMAND.

For further information on these switches and commands see the EDIT Reference Manual.

Effect on Memory

The PERUSE command clears any unkept forks from memory, then loads your edit program.

Related Commands

CREATE	for creating new files
DIRECTORY-class commands	for getting lists of existing files
EDIT	for modifying files
TYPE	for printing files on your terminal

PERUSE (Cont.)

Examples

1. PERUSE a file

```
@PERUSE FILEX.FOR
Read: FILEX.FOR.1
*p
00100 !THIS IS FILEX.FOR
```

2. PERUSE a file, ten lines at a time, and begin at line 100.

```
@PERUSE /PLINES:10 FIND.BAS
Read: FIND.BAS
*p 100
00100 !          ADD ROUTINE
00200   FOR X = 0 TO 400
00300   IF X$(X) = "XXX" THEN GOTO 2050
00400   NEXT X
00500   PRINT STRING$(10,10);"FILE FULL"\SLEEP 4\GOTO 199
00600   PRINT E$ \LINPUT"ENTER THE NAME ";M$
00700   IF M$ <> "" THEN LET X$(X) = M$ ELSE GOTO 199
00800   PRINT E$ \LINPUT"ENTER THE NUMBER ";O$
00900   IF O$ <> "" THEN LET Y$(X) = O$ ELSE GOTO 199
01000   PRINT E$\INPUT"MORE NAMES TO ENTER ";D$
*E
```

PLOT

Places requests in a plotter output queue.

Format

@PLOT (FILES) /switch(es) filespec/switch(es),...

where

switches are keywords, chosen from the list below, indicating your choice of PLOT command options. These switches are of two kinds: job switches and file switches.

Job switches apply to all files specified in the command, no matter where you give the switches.

File switches have different effects depending on their positions in the command line: placed before all files in the command, they act as defaults for all; otherwise they affect only the nearest preceding file.

Defaults are shown in the list of switches

filespec is the specification of a file you wish to plot. You can use wildcard characters (%) and (*) to specify more than one file.

,... means that, after a comma, you can give more arguments of the form already shown

Summary of PLOT Command Switches (defaults in boldface)

Job Switches (affecting the entire command)

/ACCOUNT:account	Default account - your current account
/AFTER:date and/or time	
/DESTINATION-NODE:node name	
/FORMS:forms name	Default forms name - NORMAL
/GENERIC	
/JOBNAME:6-character name	Default name - first six characters of first filename in request
/LIMIT:n	Default n - calculated from length of files
/NOTE:12-character message	
YES	
/NOTIFY:NO	
/PRIORITY:n	Default n - 10
/SEQUENCE:n	
/UNIT:octal number	
/USER:user name	

PLOT (Cont.)

File Switches

(affecting only the nearest preceding file,
unless placed before all filespecs)

```

/COPIES:n                Default n - 1
/DELETE                  Default for files of type .LST
/HEADER
    ASCII
/MODE:BINARy
    IMAGE
/NOHEADER
/PRESERVE                Default for all files except those
                        of type .LST

```

PLOT Command Switches

Job Switches

(affecting the entire command)

/ACCOUNT:account	specifies the account of 39 or fewer characters to charge for your plotting request. This account must be valid for your user name. Default account - your current account. Check with INFORMATION JOB-STATUS.
------------------	--

/AFTER:date and/or time, or ensures that the job will not be plotted until after the date day of week (or TODAY) and/or time specified. NOV-12-79 and 18:00 illustrate two arguments to this switch. If you give both date and time, separate them with a space. When given alone, the time may be preceded by a plus sign (+), which will delay processing by the indicated length of time from the present.

Alternatively, you can give a day of the week (e.g., MONDAY) or TODAY as argument; then the job will not be plotted until the beginning of the following day. If you follow this argument with a plus sign and a time, the job will be further delayed by this amount.

```

/DESTINATION-NODE:node-name    specifies the remote node on whose
                                plotter your request is to be
                                satisfied. Two colons (::)
                                following the node name are
                                optional.

```

PLOT (Cont.)

/FORMS:forms name specifies, in six or fewer characters, the forms (determining the size of banner, header, and trailer sections; the paper color, width, and weight; the number of plotter steps per inch, location of the origin for plotted data, etc.) to use for the plotting job. Using this switch may delay processing until the operator can mount the proper forms. Note that your installation may provide a different default argument to this switch.
Default forms name - NORMAL

/GENERIC allows any plotter to be used for filling the request; use this switch to override a previous /UNIT switch.
Default

/JOBNAME:name assigns a name (of six or fewer characters) to the plotting job
Default name - first six characters of first filename in the request

/LIMIT:n places a limit of n minutes of plotter time on the output of the plotting job
Default limits, usually adequate, are computed from the size of the files you want plotted

/NOTE:message labels the header section of output, i.e., the section displaying the jobname, with a message or notation of up to 12 characters. The message must be enclosed in double quotation marks if it contains spaces or non-alphanumeric characters.

YES
/NOTIFY:NO tells the system whether to send a message to your terminal when the request has been satisfied
Default argument - NO
Default argument (if switch is given) - YES

PLOT (Cont.)

/PRIORITY:n	assigns a number n, reflecting the urgency of the plot request. This n must be from 1 to 63, with larger numbers receiving earlier treatment. Note that for non-privileged users the maximum priority that can be specified is lower (usually 20), and that your installation may provide a different value both for this maximum and for the default priority. Default n - 10
/SEQUENCE:n	specifies sequence number n for the printing request, which you can use when modifying or canceling the request
/UNIT:octal number	directs your request to the plotter of the specified octal unit number
/USER:user name	specifies the user who is to be the owner of the plot request. For privileged users only.

File Switches
(affecting only the nearest preceding file,
unless placed before all file specifications)

/BEGIN:n	starts the plotting at page n of the file Default n - 0
/COPIES:n	requests that n copies of the file be plotted; n must be less than or equal to 62. Default n - 1
/DELETE	deletes the file after plotting Default for files of type .LST
/HEADER	causes a header section containing the jobname to be produced before the file itself is plotted Default
ASCII /MODE:BINAR IMAGE	designates the mode for plotting the file. ASCII treats each word of a disk file as five seven-bit bytes, and truncates each byte to six bits before plotting it. BINARY treats each word as six six-bit bytes, each of which is plotted without modification. IMAGE is the same as BINARY.

PLOT (Cont.)

/NOHEADER	prevents the production of a header section before the file
/PRESERVE	saves the file after plotting Default for all files except those of type .LST

Output

Jobname, Request ID, Limit, Number of Input Files

As soon as you complete a valid PLOT command, the system responds by printing, on your terminal, the jobname, request ID number, the limit in minutes of plotter time assigned to the request, and the number of input files in the request.

Characteristics

Ordinary Operation - No Switches

For most purposes you can use the PLOT command with just a series of filespecs for arguments.

Switch Defaults Set by System Manager

The defaults shown in the list of switches are correct for most user sites. However, your system manager can change some of those default settings. The switches most commonly affected are: /FORMS, /HEADER and /NOHEADER, /LIMIT, and /PRIORITY.

Hints

Using SET DEFAULT PLOT

If there are switches that you always or usually supply when using PLOT, give the SET DEFAULT PLOT command to establish them as defaults (at the current TOPS-20 command level) for the remainder of your terminal session. The switches will then behave as if you had typed them directly after the command name. You can supersede any of these default switches by actually supplying the switch, with another value, when you give the PLOT command. Put SET DEFAULT PLOT into a file of specification COMAND.CMD in your log-in directory if you want these default switches to be in effect for all levels of future terminal sessions as well.

PLOT (Cont.)

Special Cases

/SPOOLED-OUTPUT Switch

You can give the special switch, /SPOOLED-OUTPUT, as sole argument to the PLOT command. This causes any spooled output accumulated so far during your terminal session to be placed in a plotter queue immediately, rather than at log-out time. The /SPOOLED-OUTPUT switch is useful only if the SET SPOOLED-OUTPUT DEFERRED command is in effect. Programs that you run (especially FORTRAN programs) may create spooled output for the plotter, or you can create it directly by giving the command, COPY filespec PLT:.

Related Commands

CANCEL	for withdrawing PLOT requests
INFORMATION OUTPUT-REQUESTS	for examining requests in the output queues
MODIFY	for changing PLOT requests before processing has begun
SET DEFAULT PLOT	for establishing default switches for subsequent PLOT commands.

Examples

1. Plot a file.

```
@PLOT CNTR.MED
[Plotter job CNTR queued, request-ID 91, limit 2]
```

2. Send all files having a four-character file type ending in "CTH" to the plotter. Assign a jobname to the request, and ensure they are not plotted until tomorrow. Check for the request in the output queues, and then cancel it.

```
@PLOT *.CTH /JOBNAME:HATCH/AFTER:TODAY
[Job HATCH Queued, Request-ID 94, Limit 3, 3 Files]
@INFORMATION OUTPUT-REQUESTS
```

Plotter Queue:

Job Name	Req#	Limit	User
-----	-----	-----	-----
CNTR	91	2	LAUDERDALE
HATCH	94	3	ASHLEY /After:21-Jul-79 00:00

There are 2 jobs in the queue (none in progress)

```
@CANCEL PLOT 94
[1 Job canceled]
```


POP

Terminates the current level of TOPS-20 and returns you to its superior process.

Format

@POP (COMMAND LEVEL)

Characteristics

POP the Opposite of PUSH

You can do one and only one POP command for every previous PUSH command. Giving too many POP commands will cause an error message to be printed on your terminal.

Job Parameters Affected by POP

As soon as you complete a valid POP command at some level of TOPS-20, you give up the copy of memory for that level of TOPS-20 and any program you were running. Any defaults established at that level (e.g., default filespecs for LOAD-class and EDIT-class commands, defaults specified by SET DEFAULT commands) are cancelled as well. If POP returns you to a higher level of TOPS-20, all these parameters revert to any values established at that higher level.

Special Cases

Returning to Other Programs With POP

The POP command usually returns you to the level of TOPS-20 from which you gave a previous PUSH command. But a few system programs, e.g., PTYCON and OPR, also allow you to give PUSH to get a new level of TOPS-20. Giving the POP command to this level of TOPS-20 returns you to that program.

Effect on Memory and Terminal

The POP command clears memory, terminates the current level of TOPS-20, and returns your terminal to the previous TOPS-20 command level (but see Special Cases, above). Memory for the previous TOPS-20 command level is not affected by this action.

Related Commands

CONTINUE	for resuming execution of a program in memory
PUSH	for obtaining a new level of TOPS-20

POP (Cont.)

Examples

1. Give the POP command to return to a higher level of the TOPS-20 command processor (EXEC).

@POP

2. Run a program and halt it with CTRL/Cs. Give a CONTINUE STAY command to resume its execution, and then the PUSH command for a new level of TOPS-20. Run another program at this lower level, then use the POP command to return to the first level; in this case you return before receiving the final message of the first program.

@RUN DMN

^C

@CONTINUE /STAY

@PUSH

TOPS-20 Command processor 6.1(7)

@RUN TESTF1

THIS IS A TEST.

CPU time: 0.03 Elapsed time: 0:72

EXIT

@POP

EXIT

PRINT

Places requests in a line printer output queue.

Format

@PRINT (FILES) /switch(es) filespec/switch(es),...

where

switches are keywords, chosen from the list below, indicating your choice of PRINT command options. These switches are of two kinds: job switches and file switches.

Job switches apply to all files specified in the command, no matter where you give the switches.

File switches have different effects depending on their positions in the command file: placed before all files in the command, they act as defaults for all; otherwise they affect only the nearest preceding file.

Defaults are shown in the list of switches

filespec is the specification of a file you wish to print. You can use wildcard characters (%) and (*) to specify more than one file.

,... means that, after a comma, you can give more arguments of the form already shown

Summary of PRINT Command Switches (defaults in boldface)

Job Switches (affecting the entire command)

/ACCOUNT:account	Default account - your current account
/AFTER:date and/or time	
/DESTINATION-NODE:node name	
/FORMS:forms name	Default forms name - NORMAL
/GENERIC	
/JOBNAME:6-character name	Default name - first six characters of first filename in request
/LIMIT:n	Default n - calculated from length of files
/LOWERCASE	
/NOTE:12-character message	
YES	
/NOTIFY:NO	
/PRIORITY:n	Default n - 10
/SEQUENCE:n	
/UNIT:octal number	
/UPPERCASE	
/USER:user name	

PRINT (Cont.)

File Switches

(affecting only the nearest preceding file,
unless placed before all filespecs)

/BEGIN:n	Default n - 0
/COPIES:n	Default n - 1
/DELETE	Default for files of type .LST
ASCII	
COBOL	
/FILE:ELEVEN	
FORTRAN	Default for files of type .DAT only
/HEADER	
ARROW	
ASCII	
/MODE:OCTAL	
SUPPRESS	
/NOHEADER	
/PRESERVE	Default for all files except those of type .LST
/REPORT:12-character title	
SINGLE	
/SPACING:DOUBLE	
TRIPLE	

PRINT Command Switches

Job Switches

(affecting the entire command)

/ACCOUNT:account	specifies the account of 39 or fewer characters to charge for your printing request. This account must be valid for your user name. Default account - your current account (check with INFORMATION JOB-STATUS)
/AFTER:date and/or time, or	
day of week (or TODAY)	
and/or time	ensures that the job will not be printed until after the date and/or time specified. NOV-12-79 and 18:00 illustrate two arguments to this switch. If you give both date and time, separate them with a space. When given alone, the time may be preceded by a plus sign (+), which will delay processing by the indicated length of time from the present.

PRINT (Cont.)

Alternatively, you can give a day of the week (such as, MONDAY) or TODAY as argument; then the job will not be printed until the beginning of the following day. If you follow this argument with a plus sign and a time, the job will be further delayed by this amount.

/DESTINATION-NODE:node-name

specifies the IBM remote station on whose line printer your request is to be printed. Two colons (:) following the node name are optional. You can use this switch to either send output to a remote node or redirect it from a remote node.

/FORMS:forms name

specifies, in six or fewer characters, the forms (determining the number of banner, header, and trailer pages; the paper color, width, and weight; vertical format, carriage control tape, etc.) to use for the printing job. Using this switch may delay processing until the operator can mount the proper forms. Note that your installation may provide a different default argument to this switch.

Default forms name - NORMAL

/GENERIC

allows any printer, either upper or lowercase, and of any unit number, to be used for satisfying the request. Use this switch to override a previous /UPPERCASE, /LOWERCASE, or /UNIT switch.

Default

/JOBNAME:name

assigns a name (of six or fewer characters) to the printing job

Default name - first six characters of first filename in the request

/LIMIT:n

places a limit of n pages on the
output of the printing job

Default limits, usually adequate, are computed from the size of the files you want printed

/LOWERCASE

```
directs the job to a line printer
that can print both uppercase and
lowercase characters
```

PRINT (Cont.)

/NOTE:message

labels the header page of output, i.e., the page displaying the jobname, with a message or notation of up to 12 characters. The message must be enclosed in double quotation marks if it contains spaces or non-alphanumeric characters.

YES
/NOTIFY:NO

tells the system whether to send a message to your terminal when the request has been satisfied

Default argument - NO

Default argument (if switch is given) - YES

/PRIORITY:n

assigns a number n, reflecting the urgency of the print request. This n must be from 1 to 63, with larger numbers receiving earlier treatment. Note that for non-privileged users the maximum priority that can be specified is lower (usually 20), and that your installation may provide a different value both for this maximum and for the default priority.

The system acknowledges this switch by displaying the message [Priority has been modified]

Default n - 10

/SEQUENCE:n

specifies sequence number n for the printing request, which you can use when modifying or canceling the request

/UNIT:octal number

directs your request to the line printer of the specified octal unit number

/UPPERCASE

directs the job to a line printer that uses only uppercase characters

/USER:user name

specifies the user who is to be the owner of the print request. For privileged users only.

PRINT (Cont.)

File Switches
(affecting only the nearest preceding file,
unless placed before all file specifications)

/BEGIN:n	starts the printing at page n of the file Default n - 0
/COPIES:n	requests that n copies of the file be printed; n must be less than or equal to 62. Default n - 1
/DELETE	deletes the file after printing Default for files of type .LST
ASCII COBOL /FILE:ELEVEN FORTRAN	specifies that the file consists of ASCII text, or COBOL SIXBIT text; or (ELEVEN) contains four eight-bit bytes in each 36-bit word - for emulating paper tape punch only; or is FORTRAN ASCII text, where column 1 of each line is interpreted as a carriage control character. Default - ASCII (except for files of type .DAT, for which the default is FORTRAN)
/HEADER	causes header pages containing the jobname to be printed before the file itself Default
ARROW ASCII /MODE:OCTAL SUPPRESS	designates the mode for printing the file. ARROW prints the file literally; but denotes each control character by an up-arrow (^) and the character, except for the following, which are reproduced literally (that is, the control characters perform their normal actions): carriage return, line feed, horizontal tab, vertical tab, form feed, ^P, ^Q, ^R, ^S, and ^T. ASCII prints the file literally, without omissions or substitutions, except for the escape character (^[]) which is represented as a dollar sign.

PRINT (Cont.)

OCTAL prints each word in the file as unsigned octal integers; 3 groups of 128 words (8 rows of 16 columns each) appear on a standard line printer page. SUPPRESS prints the file without any blank lines, causing all vertical format characters (CTRL/K, CTRL/L, CTRL/Q, CTRL/R, CTRL/S, and CTRL/T) to be converted to CRLFs (carriage return/linefeeds), and then interpreting multiple occurrences of CRLFs as a single CRLF.

Default - ARROW

/NOHEADER prevents the printing of header pages before the file

/PRESERVE saves the file after printing
Default for all files except those of type .LST

/REPORT:title scans your files and prints only those lines whose first characters are the title you give. This title may contain up to 12 characters (including the quotation marks that must enclose the title if it contains spaces). The switch is used along with the COBOL report writer.

SINGLE
/SPACING:DOUBLE
TRIPLE determines the spacing between lines in the printout
Default - SINGLE

Output

Jobname, Request ID, Limit, Number of Files

As soon as you complete a valid PRINT command, the system responds by printing, on your terminal, the jobname, request ID number, the limit in pages of output assigned to the request, and the number of files in the request.

Characteristics

Ordinary Operation - No Switches

For most purposes you can use the PRINT command with just a series of filespecs for arguments.

PRINT (Cont.)

Switch Defaults Set by System Manager

The defaults shown in the list of switches are correct for most user sites. However, your system manager can change some of those default settings. The switches most commonly affected are: /FORMS, /HEADER and /NOHEADER, /LIMIT, and /PRIORITY.

Hints

Using SET DEFAULT PRINT

If there are switches that you always or usually supply when using PRINT, give the SET DEFAULT PRINT command to establish them as defaults (at the current TOPS-20 command level) for the remainder of your terminal session. The switches will then behave as if you had typed them directly after the command name. You can supersede any of these default switches by actually supplying the switch, with another value, when you give the PRINT command. Put SET DEFAULT PRINT into a file of specification COMAND.CMD in your log-in directory if you want these default switches to be in effect for all levels of future terminal sessions as well.

Special Cases

/SPOOLED-OUTPUT Switch

You can give the special switch, /SPOOLED-OUTPUT, as sole argument to the PRINT command. This causes any spooled output accumulated so far during your terminal session to be placed in a line printer queue immediately, rather than at log-out time. The /SPOOLED-OUTPUT switch is useful only if the SET SPOOLED-OUTPUT DEFERRED command is in effect. Programs that you run (especially FORTRAN programs) may create spooled output for the printer, or you can create it directly by writing to device LPT: (e.g., by giving the command, COPY filespec LPT:), or giving a CREF command.

Related Commands

CANCEL	for withdrawing PRINT requests
INFORMATION OUTPUT-REQUESTS	for examining requests in the output queues
MODIFY	for changing PRINT requests before processing has begun
SET DEFAULT PRINT	for establishing default switches for subsequent PRINT commands

PRINT (Cont.)

Examples

1. Print two of your files.

```
@PRINT 4-UPED.TXT, CMPTN.TXT
[Printer job 4-UPED queued, request 302, limit 200, 2 files]
```

2. Print three files, assigning a jobname and a note for the header page; postpone the printing. Make 4 copies of one of the files, and double-space another one.

```
@PRINT /JOBNAME:COMFIL/NOTE:CONFIDENTIAL/AFTER:12-DEC-85 -
FOO .CTL, HOLMAX.CTL/COPIES:4, INSIDE.RNO/SPACING:DOUBLE -
[Printer job COMFIL queued, request #306, limit 27, 3 files]
@INFORMATION OUTPUT-REQUESTS /USER/ALL
```

```
Printer Queue:
Job Name  Req#  Limit      User
-----
COMFIL    306    27  LATTA  /After:12-Dec-85 0:00
          /Note:CONFIDENTIAL /Seq:1865
There is 1 job in the queue (none in progress)
```

3. Print a job in a hurry, by assigning a high priority and skipping the header and first five pages. Print 10 copies of the first file, and 18 of the second.

```
@PRINT /JOBNAME:RUSH /PRIORITY:60/NOHEADER/BEGIN:5/COPIES:1 -
0 RFM.CTL, HOLMAX.CTL/COPIES:18
[Printer job RUSH queued, request #312, limit 27, 2 files]
[Priority has been modified]
@INFORMATION OUTPUT-REQUESTS /USER/ALL
```

```
Printer Queue:
Job Name  Req#  Limit      User
-----
* RUSH     312    27  LATTA  On Unit:0 /Prio:20
          /Seq:1870
  Started at 15:00:11, printed 10 of 27 pages
COMFIL    306    27  LATTA  /After:12-Dec-79 0:00
          /Note:CONFIDENTIAL /Seq:1865
There are 2 jobs in the queue (1 in progress)
```

PUNCH

Places requests in a card punch or paper tape punch output queue.

Format

@PUNCH (ONTO) medium (FILES) /switch(es) filespec/switch(es),...

where

medium is the name of the medium on which you want to punch your file(s). It can be either

CARDS

or

PAPER-TAPE

switches are keywords, chosen from the list below, indicating your choice of PUNCH command options. These switches are of two kinds: job switches and file switches.

Job switches apply to all files specified in the command, no matter where you give the switches.

File switches have different effects depending on their positions in the command line: placed before all files in the command, they act as defaults for all; otherwise they affect only the nearest preceding file.

Defaults are shown in the list of switches

filespec is the specification of a file you wish to punch. You can use wildcard characters (%) and (*) to specify more than one file.

,... means that, after a comma, you can give more arguments of the form already shown

Summary of PUNCH Command Switches (defaults in boldface)

Job Switches (affecting the entire command)

/ACCOUNT:account	Default account - your current account
/AFTER:date and/or time	
/DESTINATION-NODE:node-name	
/FORMS:forms name	Default forms name - NORMAL
/GENERIC	
/JOBNAME:6-character name	Default - first six characters of first filename in request
/LIMIT:n	Default n - calculated from length of files
/METERS:n (PAPER-TAPE only)	Default n - calculated from length of files

PUNCH (Cont.)

/NOTE:12-character message

YES

/NOTIFY:NO

/PRIORITY:n

Default n - 10

/SEQUENCE:n

/UNIT:octal number

/USER:user name

File Switches

(affecting only the nearest preceding file,
unless placed before all filespecs)

/COPIES:n

Default n - 1

/DELETE

Default for files of type .LST

/HEADER

ASCII

BCD

/MODE:BINAR Y (CARDS only)

IMAGE

ASCII

BINARY

/MODE:IMAGE (PAPER-TAPE only)

IMAGE-BINARY

/NOHEADER

/PRESERVE

Default for all files except
those of type .LST

/ACCOUNT:account

specifies the account of 39 or fewer
characters to charge for your punching
request. This account must be valid for
your user name.

Default account - your current
account (check
with INFORMATION
JOB-STATUS)

/AFTER:date and/or time or

day of week (or TODAY)

and/or time

ensures that the job will not be punched
until after the date and/or time
specified. NOV-12-79 and 18:00
illustrate two arguments to this switch.
If you give both date and time, separate
them with a space. When given alone,
the time may be preceded by a plus sign
(+), which will delay processing by the
indicated length of time from the
present.

PUNCH (Cont.)

Alternatively, you can give a day of the week (e.g., MONDAY) or TODAY as argument; then the job will not be punched until the beginning of the following day. If you follow this argument with a plus sign and a time, the job will be further delayed by this amount.

/DESTINATION--NODE:node-name

specifies the IBM remote node on whose card punch or paper tape punch your request is to be satisfied. Two colons (::) following the node name are optional.

```
/FORMS:forms name
```

specifies, in six or fewer characters, the forms (determining the weight and color of card or paper stock, the size of banner, header, and trailer sections, etc.) to use for the punching job. Using this switch may delay processing until the operator can mount the proper forms. Note that your installation may provide a different default argument to this switch.

Default forms name - NORMAL

/GENERIC

allows any card punch or paper tape punch to be used for satisfying the request; use this switch to override a previous /UNIT switch.

Default

/JOBNAME:name

```
assigns a name (of six or fewer
characters) to the punching job
```

Default name - first six characters
of first filename
in the request

/LIMIT:n

places a limit of n cards (or n feet of paper tape) on the output of the punching job

Default limits, usually adequate, are calculated from the size of the files you want punched

/METERS:n

places a limit of n meters on the output
of the punching job (PAPER-TAPE only)

/NOTE:message

labels the header section of output, i.e., the section displaying the jobname, with a message or notation of up to 12 characters. The message must be enclosed in double quotation marks if it contains spaces or non-alphanumeric characters.

PUNCH (Cont.)

YES
/NOTIFY:NO tells the system whether to send a message to your terminal when the request has been satisfied
Default argument - NO
Default argument (if switch is given) - YES

/PRIORITY:n assigns a number n, reflecting the urgency of the punch request. This n must from 1 to 63, with larger numbers receiving earlier treatment. Note that for non-privileged users the maximum priority that can be specified is lower (usually 20), and that your installation may provide a different value both for this maximum and for the default priority.
Default n - 10

/SEQUENCE:n specifies sequence number n for the punch request, which you can use when modifying or canceling the request

/UNIT:octal number directs your request to the card punch or paper tape punch of the specified octal unit number

/USER:user name specifies the user who is to be the owner of the punch request. For privileged users only.

File Switches
(affecting only the nearest preceding file,
unless placed before all file specifications)

/COPIES:n requests that n copies of the file be punched; n must be less than or equal to 62.
Default n - 1

| /DELETE deletes the file after punching.
| Opposite of /PRESERVE.
| Default for files of type .LST

/HEADER causes a header section containing the jobname to be punched before the file itself is produced
Default

PUNCH (Cont.)

ASCII
BCD
/MODE: BINARY (CARDS only)
IMAGE

designates the mode for punching the file onto cards. ASCII treats each word of a disk file as five seven-bit bytes and punches each byte into one column of the card, using the ASCII translation table for conversion into Hollerith code. BCD is the same as ASCII, except that it uses the 026 translation table. BINARY treats each group of 26 words as 78 12-bit bytes and punches each byte into one column of the card, from column 3 through column 80; column 1 contains the octal word count in rows 12 through 3 and rows 7 and 9 punched, while column 2 contains a 12-bit folded checksum. IMAGE treats each group of 27 words as 81 12-bit bytes and punches each byte into one column of the card, ignoring the eighty-first byte.

ASCII
BINARY
/MODE: IMAGE (PAPER-TAPE only)
IMAGE-BINARY

designates the mode for punching the file onto paper tape. ASCII treats each word of a disk file as five seven-bit bytes plus an even parity bit for each byte, and punches each byte into one frame of paper tape; if a vertical or horizontal tab is punched, it is followed by a rubout character, and if a formfeed is punched, it is followed by 16 null characters. BINARY treats each group of 33 words as 1 control word followed by 32 words of data, where each word (both control and data) consists of six 6-bit bytes, and punches each byte into one frame of paper tape after adding 200 (octal) to the byte; the control word consists of a folded checksum in the left half and the data word count in the right half. IMAGE treats each word of a disk file as one 8-bit byte followed by 28 zeroes, and punches each byte into one frame of paper tape. IMAGE BINARY treats each word as six 6-bit bytes, and punches each byte into one frame of paper tape after adding 200 (octal) to each byte.

/NOHEADER

prevents the punching of a header section before the file

|
/PRESERVE
|

saves the file after punching. Opposite of /DELETE.

Default for all files

PUNCH (Cont.)

Output

Jobname, Request ID, Limit, Number of Input Files

As soon as you complete a valid PUNCH command, the system responds by printing, on your terminal, the jobname, request ID number, the output limit in number of cards or feet of paper tape assigned to the request, and the number of input files in the request.

Characteristics

Ordinary Operation - No Switches

For most purposes you can use the PUNCH command with just the medium and a series of filespecs for arguments.

Switch Defaults Set by System Managers

The defaults shown in the list of switches are correct for most user sites. However, your system manager can change some of those default settings. The switches most commonly affected are: /FORMS, /HEADER and /NOHEADER, /LIMIT, and /PRIORITY.

Hints

Using the SET DEFAULT Commands

If there are switches that you always or usually supply when using PUNCH, give the SET DEFAULT CARDS or SET DEFAULT PAPER-TAPE command to establish them as defaults (at the current TOPS-20 command level) for the remainder of your terminal session. The switches will then behave as if you had typed them directly after the command name. You can supersede any of these default switches by actually supplying the switch, with another value, when you give the PUNCH command. Put SET DEFAULT commands into a file of specification COMAND.CMD in your log-in directory if you want these default switches to be in effect for all levels of future terminal sessions as well.

PUNCH (Cont.)

Special Cases

/SPOOLED-OUTPUT Switch

You can give the special switch, /SPOOLED-OUTPUT, as sole argument to the PUNCH CARDS or PUNCH PAPER-TAPE command. This causes any spooled output accumulated so far during your terminal session to be placed in a card punch or paper tape punch queue immediately, rather than at log-out time. The /SPOOLED-OUTPUT switch is useful only if the SET SPOOLED-OUTPUT DEFERRED command is in effect. Programs that you run (especially FORTRAN programs) may create spooled paper tape punch or card punch output. Or you can create it directly by giving the command, COPY filespec PTP:, or COPY filespec CDP:, respectively, or by giving a CREF command.

Related Commands

CANCEL	CARDS	
	PAPER-TAPE	for withdrawing PUNCH requests
INFORMATION	OUTPUT-REQUESTS	
		for examining requests in the output queues
MODIFY	CARDS	
	PAPER-TAPE	for changing PUNCH requests before processing has begun
SET DEFAULT	CARDS	
	PAPER-TAPE	for establishing default switches for subsequent PUNCH commands

Examples

1. Punch a file onto cards.

```
@PUNCH CARDS ESTMT.DAT
[Card-Punch job ESTMT queued, request-ID 146, limit 30]
```

2. Punch a file onto paper tape.

```
@PUNCH PAPER-TAPE REAUMUR.LNS
[Papertape job REAUMU queued, request-ID 12, limit 55]
```

3. Punch three files onto paper tape, specifying a particular paper tape punch for two of them and allowing the third to be punched on any available device.

```
@PUNCH PAPER-TAPE /UNIT:2 INDX.LTG, PON.LG4/GENERIC, -
BENNETT.TXT
[Papertape job INDX queued, request-ID 149, limit 110, 3 files]
```

PUNCH (Cont.)

4. Punch a file onto paper tape, specifying that the job not begin for an hour. Check for your requests in the output queues, then cancel both of your paper tape requests.

```
@PUNCH PAPER-TAPE FORUM.APR /AFTER:+1:00
[Papertape job FORUM queued, request-ID 150, limit 10]
@INFORMATION OUTPUT-REQUESTS/USER
```

Papertape Queue:

Job Name	Req#	Limit	User
INDX	149	110	SCARNY
FORUM	150	10	SCARNY /After:20-Jul-79 16:20

There are 2 jobs in the queue (none in progress)

Card-Punch Queue:

Job Name	Req#	Limit	User
ESTMT	146	30	SCARNY

There is 1 job in the queue (none in progress)

```
@CANCEL PAPER-TAPE *
[2 Jobs canceled]
```

PUSH

Creates a new level of TOPS-20 inferior to the one from which you give the PUSH command.

Format

@PUSH (COMMAND LEVEL)

Characteristics

A New Level of TOPS-20

The PUSH command creates an inferior level of the TOPS-20 command processor (EXEC). The system's SYSTEM:COMAND.CMD file and your login directory's COMAND.CMD file are executed again, you have a fresh copy of memory and can begin giving commands as if you had just logged in. However, job-wide parameters (for example, connected and accessed directories, logical name definitions, most parameters altered by SET commands) are unaffected by the PUSH command and retain their values.

Hints

Creating a Different Copy of an EXEC

You can use the PUSH command to create an inferior level of an EXEC of your choice. Normally, PUSH creates the EXEC defined by the system logical name, DEFAULT-EXEC:. Use the DEFINE command to define a job logical name, DEFAULT-EXEC:, with the name of the EXEC you want to create each time you PUSH.

Note that many TOPS-20 programs have their own PUSH commands. However, only the EXEC and OPR PUSH commands refer to the job's definition of DEFAULT-EXEC:.

Using CONTINUE STAY With PUSH

You can use the PUSH command to run two programs at once or to do other work that requires more than one copy of memory. Simply use the CONTINUE /STAY or CONTINUE /BACKGROUND command to continue execution of your current program before using PUSH. After PUSH you can run another program or otherwise alter memory without affecting memory for the first program. See Example 2. But see also Warning, below.

PUSH (Cont.)

Use of Multiforking Instead of PUSH

The PUSH command allows you to run several programs at once by running the programs at different EXEC levels. The EXEC's multiforking feature allows you to run multiple programs at the same EXEC level. Working from a single EXEC makes multiprogramming easier to monitor and manage. For information on multiforking see the KEEP command or the TOPS-20 User's Guide.

Restrictions

Number of Successive PUSH commands

You can give as many pairs of PUSH and POP commands as necessary to complete your task. Although there is a limit to the number of times you can give PUSH without giving intervening POP commands, this limit is large enough (approximately 24, although smaller for a heavily loaded system) not to interfere with most applications. There is a smaller limit (usually 5) on the number of EXECs that can give Queue-class commands.

Use the INFORMATION SUPERIOR command to learn how many superior EXEC levels you have created.

Invalid Definition of DEFAULT-EXEC:

If you define DEFAULT-EXEC: with the name of a nonexistent EXEC, (if, for example, you make a spelling error in your DEFINE command), the PUSH command ignores the job's definition of DEFAULT-EXEC: and creates the EXEC defined by the system definition.

Withheld Log-out Capability

You can usually log out from a lower level of TOPS-20 than the one to which you logged in. By doing so, you simultaneously conclude all processes of your job. However, if a program (e.g., PTYCON) has initialized a level of the TOPS-20 command processor but has withheld log-out capability from it, you must use the POP command, followed, if necessary, by a program command to exit from the program and return to a higher level of TOPS-20, before you can log out.

PUSH (Cont.)

Warning

Competition Between Processes

If you have two programs running at once after using CONTINUE /STAY or CONTINUE /BACKGROUND and PUSH commands (see Hints, above) they may try to access the same files at the same time. Or, TOPS-20 commands given at the lower level may be intercepted by a program running at the higher level. For a discussion of these possibilities, see the Restrictions section of the CONTINUE command description.

Effect on Memory and Terminal

The PUSH command preserves your present memory, gives you a fresh copy of memory, and leaves your terminal at a new TOPS-20 command level.

Related Commands

CONTINUE /STAY	for beginning execution of a program before giving the PUSH command
INFORMATION SUPERIOR	for displaying the number of superior EXEC levels.
POP	for returning to a previous level of TOPS-20

Examples

1. Give the PUSH command.

@PUSH

TOPS-20 Command processor 6.1(7)

PUSH (Cont.)

2. Run a program, and give a CTRL/C to return to TOPS-20 command level. Give a CONTINUE /STAY command to resume this program's execution, and then a PUSH command for a new copy of the TOPS-20 command language. Repeat this process twice; now you have three programs running at once. In the lowest (fourth) level of your job, begin editing a file. (Note: when running more than one program in this way, be sure that they do not use the same compiler or the same data base; otherwise, competition among them could cause unpredictable situations to develop.)

```
@RUN TESTF1
```

```
^C
```

```
@CONTINUE /STAY
```

```
@PUSH
```

```
TOPS-20 Command processor 6.1(7)
```

```
@RUN DMN
```

```
^C
```

```
@CONTINUE /STAY
```

```
@PUSH
```

```
TOPS-20 Command processor 6.1(7)
```

```
@RUN PRODUK
```

```
^C
```

```
@CONTINUE /STAY
```

```
@PUSH
```

```
TOPS-20 Command processor 6.1(7)
```

```
@EDIT ARTIFI.CTL
```

3. Define logical name DEFAULT-EXEC: with the name of a specialized EXEC. Then, run that EXEC with the PUSH command.

```
@DEFINE DEFAULT-EXEC: SYSTEM:EXTENDED-EXEC.EXE.7
```

```
@PUSH
```

```
TOPS-20 Command processor 6.1(6530)
```

R

Places an executable system program in memory and starts it.

Format

@R (PROGRAM) filespec /switch

where

filespec is the file specification of any executable program

Default dev:<directory> - SYS:

Default .typ - .EXE

/switch is /USE-SECTION:n specifies the memory section (from 0 to 37 octal) in which your program is to run. You can use this switch only if your program can be contained in one section.

Characteristics

Need for R Command

Although in most cases you can run system programs by simply typing the program name in place of an EXEC command, the R command is necessary for running a program whose name is the same as an EXEC command or an abbreviation for an EXEC command. For example, if your site has a system program named CONNECT, it must be run with the R command in order to distinguish it from the EXEC's CONNECT command. If you have a system program named GE, it must be run with the R command to distinguish it from the GE abbreviation for the GET command.

Cancels the Ephemeral Attribute

If a system program has been set ephemeral by the system manager or, you have given a SET PROGRAM EPHEMERAL command, you can cancel the ephemeral attribute by running the program with the R command instead of typing the program name as an EXEC command.

For more information on the ephemeral attribute, see the ERUN command.

R (Cont.)

Hints

Defining SYS:

If you redefine logical name SYS: to be different from the system-wide definition, you should include SYS: in the search list if you want to use the R command to run system programs. For further information, refer to the section entitled, "Redefining System Logical Names," in the DEFINE command description.

| Effect on Memory

| The R command clears any unkept forks, places in memory and
| starts the specified program.

Related Commands

INFORMATION LOGICAL-NAMES	for examining the definition of SYS:
RUN	for running executable user programs

Examples

1. Run the FILCOM system program.

```
@R FILCOM  
*
```

2. Find out what APL programs are available in logical name SYS:. Run one of them.

```
@DIRECTORY SYS:*APL*.EXE
```

```
PS:<FIELD-IMAGE>  
APL.EXE.1  
APLSF.EXE.1  
MAPLFL.EXE.1
```

```
Total of 3 files  
@R APL.EXE
```


RECEIVE

Notifies the system that you are willing to accept communication links, advice, user messages, and system messages.

Format

@RECEIVE argument

where

argument is a keyword, chosen from the list below, naming the kind of communication you are willing to accept

RECEIVE Command Arguments

ADVICE	allows both assistance and communication links initiated by another user's ADVISE or TALK command
LINK	allows communication links established by another user's TALK command
SYSTEM-MESSAGES	allows notices of new mail and messages of interest to all users sent by the operator or other privileged users
USER-MESSAGES	allows messages sent by another user's SEND command

Default - LINKS, SYSTEM-MESSAGES, and USER-MESSAGES

Hint

Typing RECEIVE During Attempted TALK

If your terminal has been set to refuse links and another user tries to talk to you by using the TALK command, both terminals will give a series of CTRL/G signals (ringing bells or beeps) indicating the refused attempt. If you give the RECEIVE LINKS command before these signals are finished, the TALK command will succeed.

Related Commands

ADVISE	for sending commands to another user's job
INFORMATION TERMINAL-MODE	for examining your current terminal settings
REFUSE	for refusing communication links, advice, and system and user messages

RECEIVE (Cont.)

SEND	for sending a message to another user's terminal
TALK	for linking your terminal to another user's terminal
TERMINAL INHIBIT	for refusing all types of terminal communication including links, advice, system messages, user messages, and notices of new mail.

Examples

1. Give the RECEIVE command to accept communication links from other users.

@RECEIVE LINKS

2. Set your terminal to receive links, at the request (sent via the MAIL program, not shown here) of another user. Begin a communication session with this user, during which you give the RECEIVE ADVICE command also, to allow a demonstration of the UDP program. Afterwards, set your terminal again to refuse advice.

@RECEIVE

@

LINK FROM RENQUIST, TTY 127

@;THANKS, BUT IF YOU LET ME DO AN "ADVISE" I CAN SHOW YOU

@;HOW TO RUN THE PROGRAM BY ACTUALLY DOING IT. OKAY?

@;SURE, I'LL FIX MY SETTING.

@RECEIVE ADVICE

@ADVISE LATTA

Escape character is <CTRL>E, type <CTRL>^? for help

LATTA, MISC:<LATTA> Job 33 EXEC

[Advising]

UDP

UDP>LIST/DOCUMENTATION:/CREATED-SINCE:1-1-78 0:0

UDP>EXIT

@;YOU'LL GET A PRINTED LISTING TOMORROW.

@;DO YOU SEE HOW I DID IT?

@;YES, THANKS. GOODBYE.

@

[Advice terminated]

@REFUSE ADVICE

REENTER

| Starts the current fork at its alternate entry point.

Format

@REENTER (PROGRAM)

Characteristics

Using REENTER

The REENTER command starts your program at the address specified by the second word in the program's entry vector. For most programs this address is contained in location 124. Usually the REENTER and START commands start the program at the same point, but another re-entry point can be provided to avoid initialization procedures, perform error recovery, or to use the program in a different way.

Hints

Further Information

For more information about entry vectors, see the TOPS-20 Monitor Calls Reference Manual.

Related Commands

GET	for placing an executable program in memory
LOAD	for loading a source or object program into memory
START	for entering a program at its normal entry point

Examples

1. Give the REENTER command for your current program.

@REENTER

2. Begin running a program, then give a CTRL/C to leave it and obtain a file. Resume execution of the program at the alternate entry point.

```
@R DUMPER
DUMPER>*C
@ACCESS PS:<P.SPECCINI>
Password:
@COPY PS:<P.SPECCINI>USR.FIL
PS:<P.SPECCINI>USR.FIL.1 => USR.FIL.1 [OK]
@END-ACCESS PS:<P.SPECCINI>
@REENTER
DUMPER>
```

REFUSE

Notifies the system that you are not willing to accept communication links, advice, user messages, and system messages.

Format

@REFUSE argument

where

argument is a keyword, chosen from the list below, naming the kind of communication you are not willing to accept

REFUSE Command Arguments

ADVICE prevents assistance initiated by another user's ADVISE command

LINKS prevents both assistance and communication links from being established by another user's ADVISE or TALK command

SYSTEM-MESSAGES prevents notices of new mail and messages of general interest sent to all users by the monitor or by the operator or other privileged users

USER-MESSAGES prevents messages sent by another user's SEND command

Default - ADVISE and LINKS

Hints

Refusing All Communication

Users with Wheel or Operator capabilities enabled can ADVISE, SEND, and TALK to terminals that have refused advice, user-messages, and links. To refuse messages and links from privileged users, use the **TERMINAL INHIBIT** command.

Typing RECEIVE During Attempted TALK

If your terminal has been set to refuse links and another user tries to talk to you by using the TALK command, both terminals will give a series of CTRL/G signals (ringing bells or beeps) indicating the refused attempt. If you give the **RECEIVE LINKS** command before these signals are finished, the TALK command will succeed.

REFUSE (Cont.)

Safeguarding Terminal Output

If you want your terminal to print a long file, without interference, use the `TERMINAL INHIBIT` command to prevent all classes of message from being received. Be sure to use the `TERMINAL NO INHIBIT` command afterwards to restore the previous condition of your terminal.

Special Cases

Implicit Refusal of Advice

If you give the `REFUSE LINKS` command, your terminal will be set to refuse advice also. However, the `INFORMATION TERMINAL-MODE` command may not display this setting unless you give an explicit `REFUSE ADVICE` command as well.

Privileged Disregard of REFUSE

A user with enabled Wheel or Operator capabilities can give the `TALK` or `ADVISE` command for any job.

Related Commands

<code>ADVISE</code>	for sending commands to another user's job
<code>INFORMATION TERMINAL-MODE</code>	for examining your current terminal settings
<code>RECEIVE</code>	for receiving communication links, advice, and system and user messages
<code>SEND</code>	for sending a message to another user's terminal
<code>TALK</code>	for linking your terminal to another user's terminal
<code>TERMINAL INHIBIT</code>	for refusing all types of terminal communication including links, advice, system messages, user messages, and notices of new mail.

Examples

1. Use the `REFUSE` command to prevent other users from advising your job.

`@REFUSE ADVICE`

REFUSE (Cont.)

2. Receive a communication link formed by another user's TALK command. Confer with him briefly, then set your terminal to refuse all classes of message over which you have control.

```
LINK FROM RENQUIST, TTY 127
@!HELLO DAVID. CAN YOU HELP ME WITH EDIT?
@!SORRY, PLEASE BREAK. I'M EXPECTING PRINTOUT AND THIS
@!WILL INTERFERE. WILL GET IN TOUCH LATER.
@!OKAY
@BREAK
@REFUSE LINKS
@REFUSE SYSTEM-MESSAGES
@REFUSE USER-MESSAGES
```

3. As an alternative to giving three REFUSE commands as in the previous example, give the TERMINAL INHIBIT command. This command refuses all types of messages.

```
@TERMINAL INHIBIT
```

REMARK

Tells the system to regard the terminal input that follows as comment only.

Format

@REMARK (MODE)
Type remark. End with CTRL/Z.

Characteristics

Ending Remarks

Until you give a CTRL/Z, the system merely displays what you type, instead of trying to interpret it as commands.

Hints

Useful During TALK or ADVISE Session

If you have already established contact with another user by a TALK or ADVISE command before giving REMARK, his terminal will also display what you type. Give the REMARK command before sending lengthy comments or demonstrating commands that you don't want to take effect.

Related Commands

ADVISE	for sending commands to another user's job
TALK	for sending comments to another user

REMARK (Cont.)

Examples

1. Give the REMARK command.

@REMARK

Type remark. End with CTRL/Z.

2. Receive a communication link from another user. Give the REMARK command to speak with him. Give a CTRL/Z afterwards to end the remarks.

@

LINK FROM P.SPECCINI, TTY 127

@;WHERE ARE THE NOTES FROM THE LAB DEMO THIS A.M.?

@REMARK

Type remark. End with CTRL/Z.

HI, PAUL. THEY'RE IN THE LAB'S LIBRARY AREA.

THAT'S CHEM:<P-CHEM.20.NOTES>. I DON'T KNOW

THE TITLE BUT LOOK AT THE DATES WITH A

TDIRECTORY COMMAND. OKAY?

;YES, THANKS. BYE

@BREAK

~Z

RENAME

Changes the name of a file.

Format

@RENAME (EXISTING FILE) old filespec(s) (TO BE) new filespec

where

old filespec(s) is a single file specification, or a series of them separated by commas and/or indicated by wildcard characters (% and *)

new filespec is the new specification under which you want to store the file(s); the new specification must be on the same structure; you may include an asterisk (*) if you gave more than one old filespec.

Default new filespec - old filespec, but with a generation number higher by 1 than the highest existing generation number

Output

Status of Files

If you use recognition on the new file specification, the system prints !Old Generation!, !New Generation!, or !New File!, to describe its status.

Confirmation of Action

As each file is renamed, the system prints its old and new specification, and the word [Superseding] if it is replacing previous contents, and finally the word [OK]. The delay before you see this [OK] indicates how long it took to rename the file.

Characteristics

RENAME (Cont.)

Hints

Specifying a New Account and Protection Number

You can specify the new file's protection number and the account to which its storage fees will be charged. Follow the new filespec with a semicolon (;) and the letter P before giving a new 6-digit protection number, and with a semicolon and the letter A before giving a new account. Ordinarily these values are set to the default file protection and current account. However, non-default protection numbers will be maintained for higher generations of existing files, unless you specify otherwise in the RENAME command that creates that higher generation.

RENAME Faster Than COPY for Transferring Files

For moving a set of files from one directory to another on the same structure, the RENAME command is a faster and more efficient means than COPY. This is because RENAME only changes the file specifications; it does not copy the contents of the files. Also, a file transfer with the RENAME command leaves only one set of files, while a transfer with the COPY command leaves two sets: the original copies and the destination copies. The original copies are often unnecessary and must be deleted.

Restrictions

Renaming Between Structures

You cannot rename a file from one structure to another, but must use the COPY command to reproduce its contents on the new structure, then the DELETE command to remove it from the old structure.

Renaming Open or Mapped Files

You cannot rename a file that is open or mapped into memory. First give the RESET command, or POP followed by RESET, if this is the case.

Renaming Archived Files

You can rename an archived file by specifying it as the first (or old) argument of a RENAME command. It will then have the second (or new) argument as its specification and will remain an archived file. However, you cannot give the specification of an archived file as the second argument of a RENAME command, as this would replace the file's contents. If you attempt to do so, the file you specify as the first argument will be renamed to a generation higher by 1 than the highest existing generation of the archived file, leaving the archived file intact.

RENAME (Cont.)

Warning

Replacing Previous Contents of Files

If you rename a file into a specification (including generation number) that already exists, the previous contents of the new file are replaced and cannot be recovered. But see Restrictions - Renaming Archived Files, above.

Related Commands

COPY for making copies of files

Examples

1. Rename a file.

```
@RENAME ATM-50.SPC ATM-50.PRL
ATM-50.SPC.1 => ATM-50.PRL.1 [OK]
```

2. Use a wildcard character to rename all files of a given name.

```
@RENAME ATM-50.* 1-ATM-50.*
ATM-50.BAK.1 => 1-ATM-50.BAK.1 [OK]
ATM-50.PRL.1 => 1-ATM-50.PRL.1 [OK]
```

3. Access another user directory and transfer to it the files renamed in Example 2.

```
@ACCESS <ORBEN>
Password:
@RENAME 1-ATM-50.* <ORBEN>
1-ATM-50.BAK.1 => <ORBEN>1-ATM-50.BAK.1 [OK]
1-ATM-50.PRL.1 => <ORBEN>1-ATM-50.PRL.1 [OK]
@END-ACCESS <ORBEN>
```

RESET

| Clears memory of the specified forks.

Format

| @RESET (FORK) argument
|
| where
|
| argument is one of the following: Fork name
| Fork number
| * for all forks
| . (period) for the current
| fork
|
| Default - all unkept forks

Characteristics

Action of RESET

 In addition to clearing memory for the specified forks, the
 RESET command closes all files, mapped and unmapped, opened
 by the specified forks and their inferior forks. RESET also
 simultaneously terminates the specified fork's inferior
 forks.

Effect on Memory

 The RESET command clears the specified forks from memory.

Related Commands

INFORMATION FILE-STATUS	for determining which files are currently open
INFORMATION MEMORY-USAGE	for determining contents of memory
CONTINUE, FORK, FREEZE INFORMATION, FORK-STATUS, INFORMATION PROGRAM-STATUS, KEEP, RESET, SET NAME, SET PROGRAM, and UNKEEP	other multiforking-class commands

RESET (Cont.)

Examples

1. Give the RESET command to clear all unkept forks from memory.

@RESET

2. Clear all forks, including kept forks, from memory.

@RESET *

3. Display the fork status with INFORMATION FORK-STATUS. Then, clear the SORTER fork from memory. Redisplay the fork status to check the result.

@INFORMATION FORK-STATUS

EDT (1): Kept, ^C from IO wait at 413773, 0:00:00.0
=> PASCAL (2): Kept, Background, Running at 324004, 0:00:00.8
SORTER (3): HALT at 400370, 0:00:00.6

@RESET 3

@INFORMATION FORK-STATUS

EDT (1): Kept, ^C from IO wait at 413773, 0:00:00.0
PASCAL (2): Kept, Background, Running 453004, 0:00:01.3

RETRIEVE

Returns an off-line file (magnetic tape copy of a file) to disk.

Format

@RETRIEVE (FILES) filespec,... where

filespec is the specification of any off-line file (archived or not, visible or invisible) to which you have access; you may include wildcard characters (% and *).

,... means that, after a comma, you can give more arguments of the form already shown

Output

Acknowledgment of Request

As soon as you complete a valid RETRIEVE command, the system responds by printing, on your terminal, the specification of each off-line file for which you requested retrieval, followed by [OK].

Notice of Retrieval Sent to Requestor

| Depending on the procedures at your site, when the files for
| which you have requested retrieval have been restored to
| their directory on disk, you may receive a mail message that
| contains the names of each retrieved file. Remember that,
| depending on how frequently your site processes retrieval
| requests, this message may not be sent until one or more
| days after your request.

Characteristics

Invisibility of Retrieved Files

If you retrieve invisible files, they will remain invisible (whether archived or not) when restored to disk. Use the SET FILE VISIBLE command to make invisible files visible. Until you do so, they will be inaccessible to most TOPS-20 commands.

RETRIEVE (Cont.)

Hints

Using Retrieved Archived Files

As long as a retrieved archived file is visible, you can inspect it using the TYPE or PRINT command, or list its specifications using DIRECTORY-class commands. However, you cannot add to it or change it (for example, by using APPEND). To make changes to a copy of a retrieved archived file, first use the COPY command to copy it to a new specification. If you wish, you can then request archival for this new file (using the ARCHIVE command) and delete the old one (using the DELETE command with the ARCHIVED subcommand). You can return an (unchanged) on-line archived file to off-line status by using the DELETE command with the CONTENTS-ONLY subcommand, or withdraw archive status from the file (i.e., make it an ordinary disk file) by using the DISCARD command.

Using Retrieved Non-archived Files

As long as a retrieved non-archived file is visible, you can use TOPS-20 commands with it as with any other disk file. The only difference is that after any command that has changed the file, the tape copy of the file is no longer valid. This means that you cannot give the DELETE command with the CONTENTS-ONLY subcommand to return the file to off-line status.

Special Cases

Implied Retrieval Requests

If your system has enabled the "automatic retrieval-wait" feature (give the INFORMATION SYSTEM-STATUS command to find out whether it has), and the SET RETRIEVAL-WAIT command is in effect for your job, any command that attempts to use an off-line file will create an automatic retrieval request for that file. Under these conditions, commands such as TYPE or COPY for which you specify off-line files will not be executed until those files are retrieved. Implied retrieval requests are most useful in batch jobs.

Related Commands

ARCHIVE	for requesting archival of specified files
CANCEL RETRIEVE	for canceling retrieval requests before they are filled

RETRIEVE (Cont.)

DELETE (with CONTENTS-ONLY subcommand)	for deleting the disk contents only of retrieved (i.e., on-line) files
DIRECTORY (with OFFLINE subcommand)	for listing the specifications of visible off-line files
DIRECTORY (with OFFLINE and INVISIBLE subcommands)	for listing the specifications of invisible off-line files
DIRECTORY (with TIMES TAPE-WRITE subcommand)	for finding out the write date of the tape copy of files
DISCARD	for giving up the tape copy of retrieved files
INFORMATION RETRIEVAL-REQUESTS	for finding out the status of retrieval requests

Examples

1. Retrieve an off-line file.

```
@RETRIEVE BRCHIVE.TXT  
BRCHIVE.TXT.1 [OK]
```

2. Attempt to use a file. Upon discovering that it is off-line, retrieve the file. When it has been restored to your directory, discard the tape copy of the file, and then have it printed on your terminal.

```
@TYPE FILBRK.HLP  
?File is off-line: FILBRK.HLP.1  
@RETRIEVE FILBRK.HLP  
FILBRK.HLP.1 [OK]  
.  
.  
@DISCARD FILBRK.HLP  
FILBRK.HLP.1 [OK]  
@TYPE FILBRK.HLP  
!THIS IS JUST A TEXT FILE TESTER.
```


RETRIEVE (Cont.)

3. Get a listing of your archived files. Retrieve one that is off line, examine it, and return it to off-line status.

@DIRECTORY,
@@ARCHIVE
@@

MISC:<GOLDEN>
ARCHEK.FIL.1
ARCHIVE.ALSO.1;OFFLINE
.NOT.1;OFFLINE
.TOO.1;OFFLINE
MOOBE.TXT.1;OFFLINE
TESTY.BBN.1,2

Total of 6 files
@RETRIEVE BRCHIVE.TXT
BRCHIVE.TXT.1 [OK]

.
.
.

@TYPE BRCHIVE.TXT
!A TEXT FILE TESTER
@DELETE BRCHIVE.TXT,
@@CONTENTS-ONLY
@@
MISC:<GOLDEN>BRCHIVE.TXT.1 [OK]
MISC:<GOLDEN> [1 page freed]

RENAME (Cont.)

4. Get an inclusive listing of your off-line files, including the date the tape copy was written. Retrieve three of them, and check the requests in the retrieval queue. Cancel one of the requests.

@DIRECTORY,
@@OFFLINE

@@TIMES TAPE-WRITE
@@

MISC:<GOLDEN>
Tape-write

ARCHIVE.ALSO.1;OFFLINE 8-Jun-85 07:59:08
.NOT.1;OFFLINE 8-Jun-85 07:59:09
DUMPER.MAC.1;OFFLINE 7-Mar-85 05:19:10

PRODUK.EXE.4;OFFLINE 7-Mar-85 05:19:13
SQUARE.EXE.1;OFFLINE 7-Mar-85 05:19:14

Total of 5 files
@DIRECTORY,
@@OFFLINE
@@INVISIBLE
@@TIMES TAPE-WRITE
@@

MISC:<GOLDEN>
Tape-write

ARCHIVE.TOO.1;OFFLINE 8-Jun-79 07:59:10
BRCHIVE.TXT.1;OFFLINE 27-Jun-79 04:04:58
ERCHIVE.TXT.1;OFFLINE 8-Jun-79 07:59:11
FRCHIVE.TXT.1;OFFLINE 12-Jul-79 03:23:03
MOOBE.TXT.1;OFFLINE 8-Jun-79 07:59:12

Total of 5 files
@RETRIEVE PRODUK.EXE, FRCHIVE.TXT, MOOBE.TXT
PRODUK.EXE.4 [OK]
FRCHIVE.TXT.1 [OK]
MOOBE.TXT.1 [OK]
@INFORMATION RETRIEVAL-REQUESTS

Retrieval Queue:

Name	Req#	Tape 1	Tape 2	User
MOOBE	507	5329	5520	GOLDEN
PRODUK	505	5538	5583	GOLDEN
FOOBAR	407	5845	5856	TOMCZAK
EE155	442	6279	5883	WRIGHT
BRCHIV	504	5543	7138	GOLDEN
FRCHIV	506	7138	7559	GOLDEN

There are 6 jobs in the queue (none in progress)

@CANCEL RETRIEVE 507
[1 Job canceled]

REWIND

Returns a magnetic tape to its load point (logical beginning, the beginning of the first file).

Format

@REWIND (DEVICE) dev: /switch

where

dev: is the name of the tape set or magnetic tape drive that you want to rewind. The colon after the device name is optional.

/switch is one of the following:

/CURRENT-VOLUME-ONLY
rewinds tape set to beginning
of currently mounted volume

/ENTIRE-VOLUME-SET
rewinds tape set to beginning
of first volume
Default - ENTIRE-VOLUME-SET

Note: these switches can be used only for devices of the form MTn:, not MTAn:.

Restrictions

REWIND with Open Files

If you have given a CTRL/C to exit from a program that has opened a magnetic tape set and you then give the REWIND command for that tape set, the system will first ask if you want to close the associated file. You must do so for REWIND to succeed, but will probably be unable to continue the program from that point because the file will now be closed.

Related Commands

BACKSPACE	for moving a magnetic tape backward a specified number of files or records
DIRECTORY	(when used with a magnetic tape device) for rewinding a tape set, printing a directory of its files, and again rewinding the tape set
SKIP	for moving a magnetic tape forward a specified number of files or records
UNLOAD	for rewinding a magnetic tape completely onto the source reel

REWIND (Cont.)

Examples

1. Rewind your magnetic tape.

@REWIND DAY:

2. Mount a tape, and prepare to copy files onto it. (Use the REWIND command to be sure you are at the beginning.) After copying the files, rewind the tape and (using the COPY command) read the first one. Then give TOPS-20 commands to free the resources you have been using.

@MOUNT TAPE DAY:

[Mount Request DAY Queued, Request-ID 183]

[Tape set DAY, volume DAY mounted]

[DAY: defined as MT0:]

@MOUNT STRUCTURE SNARK:

Structure SNARK: mounted

@ACCESS SNARK:

@REWIND DAY:

@COPY SNARK:FIL-1.TAP DAY:

SNARK:FIL-1.TAP.1 => MT0:FIL-1 [OK]

@COPY SNARK:FIL-2.TAP DAY:

SNARK:FIL-2.TAP.1 => MT0:FIL-2 [OK]

@COPY SNARK:FIL-3.TAP DAY:

SNARK:FIL-3.TAP.1 => MT0:FIL-3 [OK]

@REWIND DAY:

@COPY DAY: TTY:

MT0: => TTY:

!THIS IS THE FIRST FILE.!

@DISMOUNT TAPE DAY:

[Tape dismounted, logical name DAY: deleted]

@END-ACCESS SNARK:

@DISMOUNT STRUCTURE SNARK:

Structure SNARK: dismounted

@

RUN

Places an executable program in memory and starts it.

Format

@RUN (PROGRAM) filespec /switch

where

filespec is the file specification of any executable program

Default dev:<dir> - DSK:

Default .typ - .EXE

/switch is /USE-SECTION:n

specifies the memory section (from 0 to 37 octal) in which your program is to run. You can use this switch only if your program can be contained in one section.

Characteristics

Efficiency of RUN

The RUN command does the work of the pair of commands GET and START. It is a faster and less expensive means of executing programs than EXECUTE, or than LOAD and START. Therefore you should store frequently-run programs in .EXE files and run them with this command.

Hints

Alternative to RUN command

When you type only a program name, the system looks for a matching system program. When you precede the program name with the RUN command, the system looks for the program in your connected directory. The RUN command can be eliminated by typing the directory name with the program name. These two commands for example, each run SORTER located in the connected directory:

@RUN SORTER.EXE

@<SMITH>SORTER.EXE

Effect on Memory and Terminal

The RUN command clears any unkept forks, places the specified program in memory, starts it and leaves your terminal at command level in the program (if any), or at TOPS-20 command level.

RUN (Cont.)

Related Commands

EXECUTE	for running source or object programs
GET	for placing an executable program in memory
R	for running executable programs stored on SYS:
SAVE	for saving a program in executable (.EXE) format
START	for starting the program currently in memory

Examples

1. Run one of your executable programs.

@RUN TESTF1.EXE

2. Mount a structure and access a user's directory on the structure. Run one of his programs.

@MOUNT STRUCTURE SNARK:
Structure SNARK: mounted
@ACCESS SNARK:<ELDRIDGE>
Password:
@RUN SNARK:<ELDRIDGE>FT.EXE

SAVE

Stores a copy of memory in an executable file.

Format

@SAVE (ON FILE) filespec (PAGES FROM) loc1 (TO) loc2, loc3 loc4, ...

where

filespec is the file specification under which you want to store the program
Default filespec - program name.EXE

loc1 loc2, are pairs of octal numbers or symbolic expressions
loc3 loc4, that specify the span(s) of memory pages you want to
... save
Default loc1 loc2 - all assigned pages of memory from 0 to the highest page number of the highest existing section

Output

Status of Files

If you use recognition of the file specification, the system prints !Old Generation!, !New Generation!, or !New File!, to indicate its status on disk, or !OK! if saved on a non-disk device.

Hints

Saving Programs Before Running Them

When you load a source or object program using the LOAD command, save it using SAVE before running it. Then you can run it in the future using RUN, without first loading it using a LOAD-class command. This is also true if you save the program after running it, but it will then be in a post-run state.

More Information

For more information about saved files, see the TOPS-20 Monitor Calls Reference Manual.

Restriction

Saving an Execute-only Compiler

It is illegal to use the SAVE command after using the LOAD command for an execute-only compiler. An alternative is to use LINK with the LOAD command and the /SAVE switch.

SAVE (Cont.)

Related Commands

GET	for putting a saved file into memory
LOAD	for putting a source or object file into memory
RUN	for running a saved program
START	for starting the program in memory

Examples

1. Save the program currently in memory.

```
@SAVE
TESTF1.EXE.6 Saved
```

2. Mount a magnetic tape in write-enabled mode. Use the GET command to put an executable program into memory, then save it (specifying a new filename) on tape and on disk. Finally, start the program, which is still in memory.

```
@MOUNT TAPE LAT:/WRITE-ENABLED
[Mount request LAT: queued, request-ID 415]
[Tape set LAT, volume LAT mounted]
[LAT: defined as MT2:]
@GET TESTF1
@SAVE LAT:TAP.EXE
MT2:TAP.EXE Saved
@SAVE
TAP.EXE.1 Saved
@START
```

THIS IS A TEST.

CPU time: 0.04 Elapsed time: 0.17

SEND

Sends a message immediately to another user's terminal.

Format

`@SEND (TO) argument message-text`

where

`argument` is one of the following: a user name
a terminal line number
an asterisk (*) [for all terminals]
(The asterisk argument requires Wheel or Operator privileges.)

`message` is a message of up to six lines of text followed by a carriage return.

Characteristics

Multiple-line Messages

SEND allows you to send multiple-line messages with up to six 80-character lines of text. Type the message past the end of the first line and onto the next line without typing RETURN. SEND will reorganize your message on the receiver's terminal so that words broken across two lines appear on the same line.

Refused SEND

You cannot contact a user with SEND if his terminal is set to refuse messages with the REFUSE USER-MESSAGES command or the TERMINAL INHIBIT command. Normally, if you attempt to SEND to a user who has refused user messages, the system prints the message ?User is refusing messages and/or links.

However, a user with Wheel or Operator capabilities enabled, can SEND messages to users who have given a REFUSE USER-MESSAGES command, but not the TERMINAL INHIBIT command.

Hints

Finding the Receiver's Line Number

To find the terminal line number for the receiver of a SEND message, give the SYSTAT command with the receiver's user name as an argument.

SEND (Cont.)

Sending Terminal Bells

To get the attention of the user at the receiving terminal, type a few CTRL/Gs in your message. This will ring the terminal bell on the receiving terminal.

SEND in a Batch Job

You can place SEND commands in a batch control file to send messages to your terminal on the condition of a running batch job. Since your username is associated with your batch job and your timesharing job, use the line number argument.

SEND as an Alternative to Mail

The SEND command can be used as an alternative to sending a message with one of the mail programs. For short messages, SEND can be more convenient and faster to use than a mail program. For urgent messages, a SEND message is read immediately by the receiver, unlike a mail message, which can be read at the user's leisure.

Special Cases

User Has More Than One Job

If you attempt to SEND a message to a user who is logged-in on more than one terminal, the system responds with a list of the user's terminal line numbers and the programs being run at each terminal. Type your choice of terminal line number (if available, one running the EXEC) after the TTY: prompt.

Related Commands

ADVISE	for sending commands to another user's job
RECEIVE USER-MESSAGES	for receiving another user's SEND message
REFUSE USER-MESSAGES	for refusing another user's SEND message
REMARK	for telling the system to regard your terminal input as comment only
TALK	for linking your terminal to another user's terminal
TERMINAL INHIBIT	for refusing all types of terminal communication including links, advice, system messages, user messages, alerts, and mail notices

SEND (Cont.)

Examples

1. Send a message with the SEND command.

```
@SEND 141 PAUL, DO YOU HAVE THE TCO TAPE?
```

2. Send a multiple-line message. Type the message past the end of the line and onto the next. Press RETURN only at the end of the message.

```
@SEND ASMITH AL, I CAN'T MAKE THE NORTH PROJECT MEETING;  
HERMAN JUST CALLED A STAFF MEETING. I'LL WRITE MY ENGINE  
ERING STATUS AND SEND IT TO YOU BEFORE LUNCH. - BILL
```

3. Enable your Wheel or Operator privileges and send a message to all users.

```
@ENABLE  
$SEND * THE LETTER QUALITY PRINTER IS UP  
From NELSON on line 127:  
[THE LETTER QUALITY PRINTER IS UP]  
$DISABLE  
@
```

4. Place SEND commands in your batch control file to monitor the progress of your batch job.

```
@IF (ERROR) @SEND 122 Error in PROJEC batch run  
:  
:  
:  
14015 @SEND 122 PROJEC batch job almost done
```

5. Send a message to a user who has two jobs on two different terminals. Send the message to the terminal that is running the EXEC.

```
@SEND JOHNSON Ready for lunch?  
TTY20, running EXEC  
TTY4, running PASCAL  
TTY: 20
```

SET

Sets or modifies various characteristics of your job, a directory, a file, a device, or some other entity.

Format

@SET argument(s) setting(s)

where

argument is a keyword, chosen from the list below, indicating your choice of SET command options

setting is a word or number, required to complete the meaning of most SET commands

Summary of SET Command Arguments (defaults in boldface)

ACCOUNT account remark
ADDRESS-BREAK octal or symbolic memory address,
 @@AFTER n Default n - 1
 @@ALL
 @@EXECUTE
 @@NONE
 @@READ
 @@WRITE
ALERT date/time message
AUTOMATIC

CARD-READER-INPUT-SET name of input set n
CONTROL-C-CAPABILITY

DEFAULT [CARDS /switch(es)
 [COMPILE-SWITCHES file type /switch(es)
 [PAPER-TAPE /switch(es)
 [PLOT /switch(es)
 [PRINT /switch(es)
 [SUBMIT /switch(es)
 [TAKE [ALLOW
 [DISALLOW
 [ECHO
 [NO ECHO

SET (Cont.)

	[ACCOUNT-DEFAULT dev:<directory> account password
		ARCHIVE-ONLINE-EXPIRED-FILES
		FILE-PROTECTION-DEFAULT dev:<directory> octal code password Default code - 777700
		DIRECTORY GENERATION-RETENTION-COUNT-DEFAULT dev:<directory> n password Default n - 1
DIRECTORY		NO ARCHIVE-ONLINE-EXPIRED-FILES OFFLINE-EXPIRATION-DEFAULT dev:<directory>date or +n Default n - 90 ONLINE-EXPIRATION-DEFAULT dev:<directory>date or +n Default n - 60 PASSWORD dev:<directory> old password new password new password
		PROTECTION dev:<directory> octal protection code password Default code - 777700
ENTRY-VECTOR	[octal or symbolic octal or symbolic length memory location between 1 and 777 Default length - 1
		ACCOUNT filespecs account
		EPHEMERAL filespecs
		EXPIRED filespecs
		GENERATION-RETENTION-COUNT filespecs n Default n - 1
		INVISIBLE
		EPHEMERAL filespecs
FILE		NO PROHIBIT filespecs
		RESIST filespecs
		OFFLINE-EXPIRATION filespecs date or +n
		ONLINE-EXPIRATION filespecs date or +n
		PROHIBIT filespecs
		PROTECTION filespecs octal protection code Default code - 777700
		RESIST filespecs
		VISIBLE
HOST node-name::	[/CTERM /NRT
		LATE-CLEAR-TYPEAHEAD
		LOCATION node-name Default node-name - your host node
		MAIL-WATCH user-name message-count
		NAME fork-name

SET (Cont.)

NO	[ADDRESS-BREAK		
		ALERT		
		AUTOMATIC		
		CONTROL-C-CAPABILITY		
		DEFAULT	[CARDS
			COMPILE-SWITCHES	file type or *
			PAPER-TAPE	
			PLOT	
			PRINT	
			SUBMIT	
TAKE				
		LATE-CLEAR-TYPEAHEAD		
		MAIL-WATCH	user-name	
		RETRIEVAL-WAIT		
		TIME-LIMIT		
TRAP	[<RET>		
		FILE-OPENINGS		
		/ALL		
		/DEFINED		
		/UNDEFINED		
JSYS	[name		
		number		
		UUO-SIMULATION		

PAGE-ACCESS	octal page numbers	
		[
		COPY-ON-WRITE
		EXECUTE
		[
		COPY-ON-WRITE
		NO WRITE
		NONEXISTENT
		READ
		WRITE

PROGRAM fork-name	[EPHEMERAL	
		KEEP	CONTINUE
			REENTER
			START
		NO-EPHEMERAL	
		NONE	

RETRIEVAL-WAIT

SESSION-REMARK remark of up to 39 characters

SPOOLED-OUTPUT	[IMMEDIATE
	DEFERRED	

STATUS-WATCH,

@@INTERRUPT

@@NO

@@PAGES

@@TOPS-10-PAGES

SET (Cont.)

DENSITY	[200 556 800 1600 6250 SYSTEM-DEFAULT]
TAPE FORMAT	[ANSI-ASCII CORE-DUMP HIGH-DENSITY INDUSTRY-COMPATIBLE SIXBIT SYSTEM-DEFAULT]
PARITY	[EVEN ODD]
RECORD-LENGTH n bytes		Default n - 512	
TERMINAL feature or type			
TIME-LIMIT n			
TRAP	[FILE-OPENINGS []
		JSYS []
		name	
		number	
		<RET>	
		FILE-OPENINGS	
		JSYS []
		name	
		number	
		PROCEED	
		PROCEED	
TYPEOUT MODE	[NUMERIC SYMBOLIC]
UUC SIMULATION	[]

SET Command Arguments

ACCOUNT account remark

begins charging the specified account for the remainder of your current terminal session or until you use the command again. You must supply an alphanumeric account name of 39 or fewer characters valid for your user name. Then you can type an optional session remark, also of 39 or fewer characters, to be inserted in system accounting data for your current terminal session. Check your current account and session remark with INFORMATION JOB-STATUS.

SET (Cont.)

ADDRESS-BREAK octal or symbolic memory location, causes the program in memory to be suspended and a message to be printed on your terminal when the memory location you specify is referenced for the indicated operation - execute, read, write, or any of these (ALL). With the AFTER subcommand you determine how many times it must be referenced before the address break occurs; with NONE you cancel address breaks for the specified location, just as with the SET NO ADDRESS-BREAK command. Each SET ADDRESS-BREAK command cancels any previous address break. Check your current address break with INFORMATION ADDRESS-BREAK.

Default subcommands - ALL, and AFTER 1

ALERT	[date and hh:mm]	message
		hh:mm		
		+hh:mm		
		day-of-week and +hh:mm		
		TODAY and +hh:mm		

causes the system to ring your terminal bell and type a line at the specified date and time. This line contains the time of day and your message. The sign (+), used with the day-of-week and TODAY arguments, adds the time you specify to the beginning of the day (00:00:00 or midnight). For example, the command SET ALERT THURSDAY +10:00 sets an alert for Thursday at 10:00 A.M. If you omit the plus sign after a day-of-week or TODAY argument, the time is interpreted as part of the message. When a time argument is used without a day-of-week or TODAY argument, the plus sign adds the specified time to the current time. For example, the command SET ALERT +1:00 sets an alert for one hour from the time the command is given.

If the SET AUTOMATIC command is in effect, this message is sent no matter what you are doing at your terminal. Otherwise, you are alerted only when your terminal is about to type a TOPS-20 prompt (\$ or @). Alert settings are erased when you log out. Therefore, you should enter this command in your COMAND.CMD file if you want to be alerted in the distant future or on a regular basis. Check the setting of this command with INFORMATION ALERTS. Refer to Example 8.

SET (Cont.)

AUTOMATIC

allows you to be notified by the system (as a result of a SET ALERT or SET MAIL-WATCH command) whether or not your job is at TOPS-20 command level. Every five minutes, the system checks to see if you should be notified. It is recommended that you enter this command in the LOGIN.CMD file to ensure coverage from the time you log in. Check with INFORMATION ALERTS or INFORMATION COMMAND-LEVEL.

CARD-READER-INPUT-SET

name of input set n
is used by the batch system to associate the indicated set of punch cards, beginning with deck n, with system device CDR:

CONTROL-C-CAPABILITY

allows any program executed at the current command level to handle CTRL/C interrupts itself. You cannot use this command in a batch job. Check the current setting with INFORMATION PROGRAM-STATUS.

Default

 	[CARDS /switch(es)
		COMPILE-SWITCHES file-type /switch(es)
		PAPER-TAPE /switch(es)
		PLOT /switch(es)
		PRINT /switch(es)
		PROGRAM [
		EPHEMERAL
		KEEP argument
		NO-EPHEMERAL
		NONE
SUBMIT /switch(es)		
TAKE [
ALLOW		
DISALLOW		
ECHO		
NO ECHO		

sets up, as default global arguments to the command selected, the arguments you specify. CARDS refers to the PUNCH CARDS command, COMPILE-SWITCHES to all the LOAD-class commands, and PAPER-TAPE to the PUNCH PAPER TAPE command. These arguments are any switch or keyword valid for the given command.

For COMPILE-SWITCHES, you must specify the type of file you want the switches applied to by preceding the switches with one of the following: a file type (excluding the period), a period for file specifications with a null extension, or an asterisk (*) for all file types. Check current settings with INFORMATION DEFAULTS.

SET (Cont.)

DIRECTORY ACCOUNT-DEFAULT dev:<directory> default account
PASSWORD:password

sets the account of 39 or fewer characters to charge for your terminal session whenever you log in to this directory without specifying an account. Check with INFORMATION DIRECTORY.

DIRECTORY ARCHIVE-ONLINE-EXPIRED-FILES dev:<directory>
causes on-line files that have expired to be automatically archived. Check with INFORMATION DIRECTORY.

DIRECTORY FILE-PROTECTION-DEFAULT dev:<directory> octal code
PASSWORD:password
sets a default protection code governing access to files subsequently created in the directory. See description of FILE PROTECTION argument for a list of valid protection codes. Check with INFORMATION DIRECTORY.
Default code - 777700

DIRECTORY GENERATION-RETENTION-COUNT-DEFAULT dev:<directory> n
PASSWORD:password
prescribes for the directory a default value for the number of generations of subsequently-created files to save. Check with INFORMATION DIRECTORY.
Default n - 1

DIRECTORY NO ARCHIVE-ONLINE-EXPIRED-FILES
prevents on-line files that have expired from being automatically archived
Default

DIRECTORY OFFLINE-EXPIRATION-DEFAULT dev:<directory> date or +n
sets the tape expiration date for files that are to go off line because of archiving or migration. If you specify "+n", the expiration date is n days from the date the files were moved off line.
Default n - 90

SET (Cont.)

DIRECTORY ONLINE-EXPIRATION-DEFAULT dev:<directory> date or +n
sets the disk expiration date for files
that are to be created in the directory.
If you specify "+n", the expiration date
is n days from the creation date.
Default n - 60

DIRECTORY PASSWORD dev:<directory>
Old password:old password
New password:new password
Retype new password:new password
allows you to change the password of the
directory named. The password can
consist of up to 39 alphanumeric
characters, including hyphens.

DIRECTORY PROTECTION dev:<directory> octal protection code
Password:password
establishes for the directory a
protection code constructed (by
addition) from the values shown below.
Check with INFORMATION DIRECTORY.

77	full access to the directory
40	access to files in the directory (including expunging individual files), consistent with the file protection of the files
10	connect to the directory without giving a password, undelete files, expunge the entire directory, and change times, dates and accounting information for files. All other access is governed by the file protection of each file.
04	create files in the directory
00	no access to the directory

Default code - 777700

See the TOPS-20 User's Guide for more information about protection codes.

ENTRY-VECTOR [octal or symbolic memory location] octal or symbolic length from 1 to 777
lets you change the entry vector of the program in memory. Check the current setting with INFORMATION MEMORY-USAGE.
Default length - 1

FILE ACCOUNT filespecs account
specifies the account to charge for storage of the files named. Check with the DIRECTORY command and the ACCOUNT subcommand.

SET (Cont.)

FILE EPHEMERAL filespec	<p>assigns an ephemeral attribute to a system program. The program is placed in an ephemeral fork only when you run it by typing just the program name as an EXEC command. Running an ephemeral system program with the R command cancels the ephemeral attribute. For a description of an ephemeral fork, see the ERUN command, Characteristics of an Ephemeral Fork.</p> <p>Wheel or Operator privileges are required to set a system program ephemeral. Refer to Example 11 for setting a system program ephemeral. Refer to Example 12 for running your own programs by typing only the program name.</p>
FILE EXPIRED filespecs	<p>establishes today as the expiration date for the specified on-line files. Check with the DIRECTORY command and the DATES ONLINE-EXPIRATION subcommand.</p>
FILE GENERATION-RETENTION-COUNT filespecs n	<p>tells the system how many generations of the specified files to save. Check with the DIRECTORY command and the GENERATION-RETENTION-COUNT subcommand.</p> <p>Default n - 1</p>
FILE INVISIBLE filespecs	<p>makes the specified file inaccessible to most programs and TOPS-20 commands. Check with the DIRECTORY command and the INVISIBLE subcommand.</p>
FILE NO EPHEMERAL filespec	<p>removes the ephemeral attribute from a system program. Wheel or Operator privileges are required to alter a system program.</p> <p>You can cancel the ephemeral attribute for your copy of a system program with the SET PROGRAM NO-EPHEMERAL command or, by running the program with the R command instead of simply typing the system program name as a command.</p>
FILE NO PROHIBIT filespecs	<p>allows the system to migrate the specified file to off-line storage if disk space becomes low. For privileged users only. Check with the DIRECTORY command and the PROHIBIT-MIGRATION subcommand.</p> <p>Default</p>

SET (Cont.)

FILE NO RESIST filespecs

cancels the effect of the SET FILE RESIST command. This switch allows the system to move the specified files to off-line storage without hesitating. Check with the DIRECTORY command and the RESIST-MIGRATION subcommand.

Default

FILE OFFLINE-EXPIRATION filespecs date or +n

specifies when the contents of an off-line file can be expunged from off-line storage. If you specify "+n", the expiration date is n days from the date it was moved off line. Check with the DIRECTORY command and the DATES OFFLINE-EXPIRATION subcommand.

FILE ONLINE-EXPIRATION filespecs date or +n

establishes the date on which the disk contents of the specified files will expire. If you specify "+n", the expiration date is n days from the current date. Check with the DIRECTORY command the DATES ONLINE-EXPIRATION subcommand.

FILE PROHIBIT filespecs

tells the system never to migrate the specified file to off-line storage. For privileged users only. (Nonprivileged users should refer to the description of the SET FILE RESIST command. See also Hints - Alternative to SET FILE PROHIBIT for Non-privileged Users, below.) Check with the DIRECTORY command and the PROHIBIT-MIGRATION subcommand.

FILE PROTECTION filespecs octal protection code

sets, for the specified files, a protection code constructed (by addition) from the octal values shown below. Check with the DIRECTORY command and the PROTECTION subcommand.

77	full access to the file
40	read the file
20	write and delete the file
10	execute the program contained in the file
04	append to the file
02	access the file using wildcarded file specifications
00	no access to the file

Default code - 777700

See the TOPS-20 User's Guide for more information about protection codes.

SET (Cont.)

FILE RESIST filespecs

offers nonprivileged users limited protection against migration. The specified files will be forced off-line only when absolutely necessary. Check with the DIRECTORY command and the RESIST-MIGRATION subcommand.

FILE VISIBLE filespecs

makes the specified file accessible to all programs and TOPS-20 commands. Check with the DIRECTORY command and the INVISIBLE subcommand.

Default

HOST

Due to the number of options in the SET HOST command, it is described separately from the SET command. See the SET HOST command description following the SET command.

LATE-CLEAR-TYPEAHEAD

instructs the system to disregard all terminal input made after a line that causes an error and before the next prompt. Check the setting for your current level of TOPS-20 with INFORMATION COMMAND-LEVEL.

LOCATION node-name::

causes all output device request to be sent to the specified IBM remote station. Two colons (::) following the node name are optional. Check available nodes with INFORMATION DECNET, and check your current setting (if different from your host node [log-in node]) with INFORMATION JOB-STATUS.

Default node-name - your host node

MAIL-WATCH user-name message-count

checks the MAIL file for the specified user immediately and every five minutes thereafter whenever your terminal is about to type a TOPS-20 prompt (@ or \$), and sends a message notifying you that the user has new mail if this file contains unread mail. If you specify your own user-name, you receive the message [You have mail from USER-NAME at 00:00:00]. If you specify a user-name other than your own, you receive the message [RECEIVER-USER-NAME has mail from SENDER-USER-NAME at 00:00:00]. You must have read access to the specified user's mail file.

SET (Cont.)

The message count argument sets the number of times you are notified of unread mail. If the SET AUTOMATIC command is in effect, this message is sent no matter what you are doing at your terminal. The maximum number of users that you can MAIL-WATCH is five. Refer to Example 10.

Default user-name - your user-name
Default message-count - 1000

NAME fork-name

renames the current fork with the specified alphanumeric name. Select the current fork with the FORK command. Check with INFORMATION FORK-STATUS.

If you give a fork the name of a program specified in a SET PROGRAM command, the fork will receive the attributes assigned in the SET PROGRAM command. For example, suppose you have given these two commands:

```
SET PROGRAM COMPUTE KEEP CONTINUE
SET PROGRAM SQUARE EPHEMERAL
```

If only COMPUTE is in memory and you name it SQUARE, the fork will assume the attributes defined in the SET PROGRAM SQUARE command and become an ephemeral fork. The system indicates this with the message [Assuming attributes of SQUARE].

A fork must have a unique name. If you attempt to name a fork with the same name as another fork, the system appends a digit to the new name. For example, if you attempted to name two forks EDIT, the second fork would be named EDIT0.

NO ALERT date/time

removes settings that were established with the SET ALERT command. You can specify date and time in the same formats as with SET ALERT. Additionally, you can enter BEFORE or AFTER the date and time to indicate a time period in which alerts are to be suppressed. If you specify no date or time argument, all alert settings are erased. Alerts are valid only for the current terminal session and are erased automatically when you log out.

Default

SET (Cont.)

NO AUTOMATIC

causes you to be alerted by the system (as a result of a SET ALERT or SET MAIL-WATCH command) only when your terminal is about to type a TOPS-20 prompt (@ or \$). Check with INFORMATION ALERTS or INFORMATION COMMAND-LEVEL.

Default

NO CONTROL-C-CAPABILITY

removes the ability of programs at the current level of TOPS-20 to prevent your terminal from returning to the TOPS-20 command processor whenever you type a CTRL/C; i.e., ensures that CTRL/C will return you to TOPS-20. Check the setting for your current level of TOPS-20 with INFORMATION PROGRAM-STATUS.

NO DEFAULT

CARDS	
COMPILE-SWITCHES	file-type
PAPER-TAPE	
PLOT	
PRINT	
PROGRAM	EPHEMERAL
	KEEP
	NO-EPHEMERAL
	NONE
SUBMIT	

nullifies all default arguments (established with a previous SET DEFAULT command) for the indicated command. For COMPILE-SWITCHES you must specify the type of file for which you want to clear the switches with one of the following: a file type (excluding the period), a period for file specifications with a null extension, or an * to clear the switches for all file types. Check with INFORMATION DEFAULTS.

NO LATE-CLEAR-TYPEAHEAD

instructs the system to accept terminal input made after an error message is sent to your terminal and before the next prompt. Check the setting for your current level of TOPS-20 with INFORMATION COMMAND-LEVEL.

Default

NO MAIL-WATCH user-name

disables periodic checking of the MAIL file associated with the specified user. The notice of new mail is still displayed at log-in time and when you receive mail, unless you have given the REFUSE SYSTEM-MESSAGES or REFUSE LINKS command. You can always check the status of your MAIL file at any time by giving the INFORMATION MAIL command.

Default user-name - your user-name

Default

SET (Cont.)

NO RETRIEVAL-WAIT	tells the system to send an error message if your job attempts to use off-line files. Default
NO STATUS-WATCH	cancels the effect of the SET STATUS-WATCH command, disabling the interrupt character or character sequence that displays the status of all open, mapped pages.
NO TIME-LIMIT	removes any time limit set by a previous SET TIME-LIMIT command. You cannot use this command in a batch job.
NO TRAP	prevents any trapping that would have occurred as the result of a SET TRAP command. Default
NO TRAP FILE-OPENINGS	nullifies the effects of the SET TRAP FILE-OPENINGS command, disabling the TOPS-20 feature that causes you to be notified when a program tries to open a file. Default
NO TRAP JSYS [/ALL /DEFINED /UNDEFINED name number	nullifies the effects of the SET TRAP JSYS command, disabling the TOPS-20 feature that causes traps to occur when a JSYS is executed. Default
NO TRAP PROCEED	same as TRAP NO PROCEED.
NO UO-SIMULATION	disables the feature of the TOPS-20 monitor that makes it possible to use programs originally written for the TOPS-10 operating system. Check the current setting with INFORMATION PROGRAM-STATUS.
PAGE-ACCESS range of octal page numbers	type of access
	Sets the type of access allowed to programs for the specified pages existing in memory.
COPY-ON-WRITE	provides programs with private copies of the specified pages (13:17, 21 specifies pages 13 through 17 and page 21, 6 pages in all) of current memory whenever they try to change (write to) them
EXECUTE	allows programs accessing these pages to execute the instructions they may contain

SET (Cont.)

NO COPY-ON-WRITE
WRITE prevents programs from performing the indicated operation on the specified pages

NONEXISTENT removes the indicated pages from memory

READ permits programs to examine the indicated pages of memory

WRITE permits programs to change as well as examine the indicated pages

Check the status of current memory pages with INFORMATION MEMORY-USAGE.

PROGRAM fork-name EPHEMERAL

tells the system to make the specified fork an ephemeral fork when it is loaded. For a description of an ephemeral fork, see the ERUN command, Characteristics of an Ephemeral Fork.

It is recommended that you enter this command in your COMAND.CMD file for programs that you commonly place in ephemeral forks. Check with INFORMATION PROGRAM-STATUS.

PROGRAM fork-name KEEP CONTINUE
REENTER
START

tells the system to make the specified fork a kept fork automatically when the fork is loaded, or immediately if the fork is already loaded. A kept fork is not reset when another fork is loaded and is not reset by the RESET command unless the kept fork is explicitly named or the asterisk (*), or period (.) argument is specified.

The required KEEP attribute establishes where the program restarts when you type the fork name as an EXEC command. CONTINUE begins the program at the point where it was interrupted. REENTER begins the program at its reentry address (for most programs the reentry address is the same as the start address). START begins the program at its start address. The system informs you when the fork is "kept" with the message [Keeping fork-name]. When you type the kept fork name, the system responds with [CONTINUING], [REENTERING], or [STARTING].

SET (Cont.)

This command automatically keeps forks that are loaded by typing the system program name or one of the following commands: CSAVE, GET, R, RUN, and SAVE.

It is recommended that you enter this command in your COMAND.CMD file for programs that you commonly place in kept forks. Check with INFORMATION PROGRAM-STATUS. Refer to Example 9. For a restriction on the CONTINUE argument, refer to the CONTINUE command description under Restrictions: Continued Programs Do Not Prompt for Input.

PROGRAM fork-name NO-EPHEMERAL

disables the ephemeral attribute for your copy of a system program. Note that you can also cancel a program's ephemeral attribute by running the program with the R command instead of typing just the program name. It is recommended that you enter this command in your COMAND.CMD file. Refer to Example 13.

PROGRAM fork-name NONE

cancels the setting established for the specified fork with the SET PROGRAM command. If the program is in a kept fork, the address used when the fork name is given as a command is changed to the start address. Check with INFORMATION PROGRAM-STATUS.

RETRIEVAL-WAIT

tells the system that your job is willing to wait for retrieval of off-line files. Retrieval is then requested implicitly whenever you or a program you run attempts to access off-line files. Use INFORMATION SYSTEM-STATUS to be sure that automatic retrieval waits are enabled for the system before giving this command.

SESSION-REMARK remark

lets you insert a note or reminder of up to 39 characters into system accounting data. Check with INFORMATION JOB-STATUS.

SET (Cont.)

SPOOLED-OUTPUT IMMEDIATE
DEFERRED

directs the system either to begin processing your spooled output requests as soon as you make them, or to defer them until log-out. You make spooled output requests not with the PLOT, PRINT, or PUNCH commands (these are always processed immediately), but with a command or program that writes files to a spooled output device (for example, a line printer - LPT:, plotter - PLT:, or card punch - CDP:). The COPY commands, the /LIST switch for LOAD class commands, the CREF command, and the LPT and OUTPUT subcommands for DIRECTORY-class and SYSTAT commands may make spooled output requests. Check with INFORMATION SPOOLED-OUTPUT-ACTION.
Default - IMMEDIATE

STATUS-WATCH,
@@INTERRUPT
@@NO
@@PAGES
@@TOPS-10 PAGES

sets an interrupt character that displays the status of all open, non-execute files mapped to the current fork. The display includes:

- the job file number. The JFN identifies a file to the job. The user program uses the JFN in all references to the file.
- the file specification.
- file pages mapped to a process.
- file position and byte size displayed in the form "Byte nn(mm)" where nn is the byte pointer and (mm) is the byte size. Not displayed if file position is zero.
- file size displayed in the form "Page nn of mm" where nn is the page being read and mm is the total number of pages in the file. If a single number is displayed, as in "Page nn", nn is the total number of pages in the file. For example, "Page 5 of 9" represents a 9-page input file where page 5 is currently being read. "Page 11" represents an output file where 11 pages have been created. Note that some programs do not read the input file sequentially.
- The mode of access (read, write and append) for which the file has been opened.

SET (Cont.)

Although much of the above information is also provided by the INFORMATION FILE-STATUS and INFORMATION MEMORY commands, these commands can only display information while your terminal is at EXEC command level. The STATUS-WATCH interrupt character functions from EXEC or program level. In addition, the interrupt character displays the status of an executing EXEC command (for example, COPY).

To check the status of pages mapped to a program, you must specify one of these subcommands: PAGES, or TOPS-10-PAGES. The interrupt character always displays the pages opened by the EXEC, for example the pages opened by a COPY command. When an EXEC command is processing, only the EXEC's pages are checked. If no command is in progress, the current fork's address space is checked. If there is no current fork, no checking takes place.

For efficiency and to reduce the overhead of this command, a maximum of 512 pages (not including EXEC pages) are checked by the interrupt character. These pages do not have to be contiguous or in the same section.

To simplify your typing, SET STATUS-WATCH accepts subcommands as arguments on the command line.

INTERRUPT "^x" is a required subcommand that sets a control character or character sequence that, when typed during program or EXEC command execution, displays the status of all files opened by the current fork. Use the FORK command to select a different current fork.

The interrupt character can be a single control character or a two-character sequence enclosed in double quotes. For example, "^B", "DF", "^QW" are valid interrupt characters. Control characters that are already used by the system, such as CTRL/C and CTRL/T, cannot be redefined by SET STATUS-WATCH. See Appendix D for a list of defined system control characters.

SET (Cont.)

A two-character interrupt sequence is job-wide and can be issued from any EXEC level. If another program in your job defines a two-character interrupt sequence (for example the SET HOST command with the CTERM-SERVER), this sequence supersedes the SET STATUS-WATCH interrupt sequence. A single-character interrupt applies only to the current EXEC level. Also, the interrupt character is not echoed on the terminal.

NO INTERRUPT disables the interrupt characters.

PAGES nn adds the specified octal pages (nn) or range of pages (n:m) to the pages checked by the interrupt character. Multiple pages and ranges of pages can be specified by separating the pages with commas. For example, PAGE 100:40, 350 specifies pages 100 through 140 and page 350.

NO PAGES disables checking for all pages except pages used by the EXEC.

The total number of mapped pages checked by the interrupt character (not including EXEC pages) cannot exceed 512. Generally, programs map pages within the range of 0:777.

TOPS-10-PAGES adds the pages used by PA1050 (for TOPS-10 compatibility) to the address space checked by the interrupt character.

It is recommended that you place the SET STATUS command in your COMAND.CMD file.

See Example 14.

TAPE DENSITY

200
556
800
1600
6250
SYSTEM-DEFAULT

instructs the system to read and write magnetic tapes for your job at the indicated density (in bits per inch). SYSTEM-DEFAULT, one of these values (usually 1600), is established by your system manager. The value set by this command can be superseded by commands within a program. Check with INFORMATION TAPE-PARAMETERS.

Default - SYSTEM-DEFAULT

SET (Cont.)

TAPE FORMAT	<div> <div>ANSI-ASCII</div> <div>CORE-DUMP</div> <div>HIGH-DENSITY</div> <div>INDUSTRY-COMPATIBLE</div> <div>SIXBIT</div> <div>SYSTEM-DEFAULT</div> </div>	<p>advises the system that the format to use in processing tapes is either ANSI-ASCII, which stores each word of data as five 7-bit bytes in five frames of a 9-track type; or CORE-DUMP, which stores each word of data as a single 36-bit byte in five frames of a 9-track tape, partially using the fifth frame; or HIGH-DENSITY, which stores each two words of data as nine 8-bit bytes in nine frames of a 9-track tape; or INDUSTRY-COMPATIBLE, which stores each word of data as four 8-bit bytes in four frames of a 9-track tape; or SIXBIT, which stores each word of data as six 6-bit bytes in six frames of a 7-track tape. SYSTEM-DEFAULT, one of these (usually CORE-DUMP), is chosen by your system manager. See also Restrictions - Using SET TAPE Commands, in the MOUNT command description in this manual. See the <u>TOPS-20 Monitor Calls Reference Manual</u> for more information about hardware data modes for magnetic tapes. Check with INFORMATION TAPE-PARAMETERS.</p> <p>Default - SYSTEM-DEFAULT</p>
TAPE PARITY	<div>EVEN</div> <div>ODD</div>	<p>tells the system which parity to assume when verifying the accuracy of tape records. Check with INFORMATION TAPE-PARAMETERS.</p> <p>Default - ODD</p>
TAPE RECORD-LENGTH n		<p>sets the size, in bytes, for each physical record on a tape. Check with INFORMATION TAPE-PARAMETERS. Not applicable with labeled tapes.</p> <p>Default n - 512</p>
TERMINAL feature or type		<p>same as TERMINAL command.</p>
TIME-LIMIT n		<p>tells the system to stop any program or terminal printout when the given amount of additional CPU time (in seconds) has been used, and to inform you with a fatal error message. This command is used by the batch system to limit the runtime of batch jobs. Display the time limit set for your job with the SYSTAT command and the LIMIT subcommand. Display the CPU time used by your job with CTRL/T or INFORMATION PROGRAM-STATUS.</p>

SET (Cont.)

| TRAP FILE-OPENINGS

displays a message when any program attempts to open a file. Check with INFORMATION PROGRAM-STATUS. Refer to Example 5.

| TRAP JSYS [/ALL
| /DEFINED
| /UNDEFINED
| name
| number

displays a message when any program calls a TOPS-20 JSYS. You can cause trapping to occur for all JSYSs, for defined JSYSs only (JSYSs known to the Monitor), for undefined JSYSs only (JSYSs not known to the Monitor), or for the JSYS(s) specified by name or number. You can specify multiple JSYSs separated by commas. Check with INFORMATION PROGRAM-STATUS. Refer to Example 6.

Default - /DEFINED

NOTE

The SET TRAP command is ineffective for execute-only programs (those with a protection code that prohibits reading and writing the file). Attempts to run such programs after a SET TRAP command has been specified will result in error messages.

| TRAP NO

same as SET NO TRAP.

| TRAP NO FILE-OPENINGS

same as SET NO TRAP FILE-OPENINGS.

| TRAP NO JSYS [/ALL
| /DEFINED
| /UNDEFINED
| name
| number

same as SET NO TRAP JSYS.

| TRAP NO PROCEED

directs the system to terminate the program after a trap has occurred as a result of a SET TRAP command. Check with INFORMATION PROGRAM-STATUS. Refer to Example 7.

| TRAP PROCEED

directs the system to continue a program after a trap has occurred as a result of a SET TRAP command. Check with INFORMATION PROGRAM-STATUS.

Default

SET (Cont.)

TYPEOUT MODE NUMERIC
SYMBOLIC

establishes the mode in which memory addresses and contents are to be typed on your terminal in response, for example, to a CTRL/T or the commands: INFORMATION ADDRESS-BREAK, INFORMATION FORK-STATUS, INFORMATION PROGRAM-STATUS, and EXAMINE. Note that only NUMERIC typeout is displayed for execute-only programs. Check with INFORMATION PROGRAM-STATUS.

Default - NUMERIC

UUO-SIMULATION

allows the system to execute programs originally written for the TOPS-10 operating system, by calling the TOPS-10 compatibility package, PA1050.EXE. Check the current setting with INFORMATION PROGRAM-STATUS.

Default

Characteristics

Affect Only Current Terminal Session

The SET command, except for SET DIRECTORY and SET FILE, applies to the current terminal session only, and in most cases only to the current level of TOPS-20 in that session. Therefore put SET DEFAULT, SET CONTROL-C-CAPABILITY, SET PROGRAM, and other SET commands into your COMAND.CMD file if you want them to be in effect every time you log in or give the PUSH command. Place commands that apply to any level of TOPS-20 in your LOGIN.CMD file.

Hints

Using SET PAGE-ACCESS

A SET PAGE-ACCESS command can take several arguments on the same line, with cumulative effect; contradictions are resolved in favor of the last item given. So SET PAGE-ACCESS 6 EXECUTE NO COPY-ON-WRITE NO WRITE allows a user to execute page 6 but not to change it; SET PAGE-ACCESS 7 NO WRITE WRITE allows changes to page 7.

To Make Modifiable Copies of Write-protected Programs

Because the SAVE command preserves the write protection of files, you should use the SET PAGE ACCESS WRITE or SET PAGE-ACCESS COPY-ON-WRITE command before giving SAVE if you want to save a modifiable copy of a program.

SET (Cont.)

Using SET TIME-LIMIT

Although the SET TIME-LIMIT command is ordinarily used by the batch system to limit the runtime of jobs, you can employ it as a timesharing user to give you a fatal error message when the specified amount of CPU time has been spent. To find out how much of this time you have left, give the SYSTAT . LIMIT and INFORMATION PROGRAM-STATUS commands. The difference between the SYSTAT . LIMIT time and the "Used" time reported by INFORMATION PROGRAM-STATUS tells you the approximate time remaining.

SET Commands Useful for Debugging Programs

SET ADDRESS-BREAK

SET ADDRESS-BREAK shows you how often and for what purpose a memory address is referenced. When an address break occurs, a message will show the memory location at which execution of your program will resume.

SET NO CONTROL-C-CAPABILITY, SET UUO-SIMULATION, SET PAGE-ACCESS

If you are debugging a program, use the SET NO CONTROL-C-CAPABILITY command to ensure that you can use CTRL/C to leave the program. Test a program that traps CTRL/Cs by having it trap, say, CTRL/As instead during debugging. Also, setting NO CONTROL-C-CAPABILITY, NO UUO-SIMULATION, or PAGE-ACCESS NO WRITE NO COPY-ON-WRITE will show you what part of the program (if any) is attempting to use these features.

Alternative to SET FILE PROHIBIT for Non-privileged Users

Even if you do not have sufficient privileges to use the SET FILE PROHIBIT command, you can still do something to delay the removal of important files to off-line storage. Create a file named MIGRATION.ORDER in each directory for which you wish to control migration. The contents of this file should be the specifications of files that you want to be migrated first, when migration is performed. You may use wildcard characters (* and %) to specify more than one file. To protect source programs, for example, you could specify that executable programs and binary files be migrated first, by listing "*.EXE, *.REL" in MIGRATION.ORDER. To protect edited files, you could list "*.Q*" (this ensures that unedited back-up files produced by the EDIT program be migrated before the edited versions). Any files not listed in MIGRATION.ORDER will be protected from migration until all listed files have been migrated. Remember that, even without being listed in MIGRATION.ORDER, files are not usually migrated to off-line storage if they have been used or changed within a period of time specified by your system manager.

The SET FILE RESIST command also offers limited protection against involuntary migration.

SET (Cont.)

Restrictions

Using SET Commands in Batch Jobs

Put SET commands into a BATCH.CMD file in your log-in directory if you want them to apply to the first (highest) level of TOPS-20 in batch jobs you submit; put them into COMAND.CMD in your log-in directory if you want them to apply to all levels of TOPS-20 in both batch and interactive jobs. Remember, though, that you must not give SET CONTROL-C-CAPABILITY, SET NO TIME-LIMIT, or SET TIME-LIMIT (or the ATTACH command) within any batch job.

Using SET DIRECTORY Commands

You will be able to use the SET DIRECTORY commands only if your system is instructed at system start-up time to allow them. Otherwise, the system will send you error messages in response to SET DIRECTORY commands.

Examples

1. Set the LATE-CLEAR-TYPEAHEAD parameter for your job.

```
@SET LATE-CLEAR-TYPEAHEAD
```

2. Find out the placement of your program in memory; set an address break to occur at location 2412 when the instruction it contains has been executed six times. Then give the INFORMATION ADDRESS-BREAK command to see the location and operation for which the current address break has been set.

```
@INFORMATION MEMORY-USAGE
```

```
5. pages, Entry vector loc 400010 len 254000
```

```
0-3          Private   R, W, E
400          Private   R, W, E
```

```
@SET ADDRESS-BREAK 2412,
```

```
@@AFTER 6
```

```
@@EXECUTE
```

```
@@
```

```
@INFORMATION ADDRESS-BREAK
```

```
Address break at 2412 on execute.
```

3. Set defaults for PRINT command switches, then print a file immediately by explicitly supplying an /AFTER switch with an early hour as argument.

```
@SET DEFAULT PRINT /LOWERCASE/AFTER:17:00
```

```
@PRINT /AFTER:+0 4-UPED.TXT
```

```
[Job 4-UPED Queued, Request-ID 346, Limit 200]
```

```
@INFORMATION OUTPUT-REQUESTS /USER
```

```
Printer Queue:
```

```
Job Name Req# Limit User
```

```
-----
```

```
* 4-UPED 346 200 LATTA
```

```
Started at 16:11:11, printed 0 of 200 pages
```

```
On Unit:0
```

```
There is 1 Job in the Queue (1 in Progress)
```

SET (Cont.)

- Put an executable program into memory and set the page access of its first page to NO COPY-ON-WRITE; try to deposit a value (32) in memory location 500 of the page (this fails). Then set its page access to COPY-ON-WRITE and try once more, succeeding this time. Give the INFORMATION MEMORY-USAGE command again. Notice that you now have your own copy of the page in memory; it is no longer mapped from the file TESTF1.EXE in your connected directory.

```
@GET TESTF1
@INFORMATION MEMORY-USAGE
```

```
1. pages, Entry vector loc 145 len 254000
```

```
0 TESTF1.EXE.3 1 R, CW, E
```

```
@SET PAGE-ACCESS 0 NO COPY-ON-WRITE
```

```
@DEPOSIT 500 32
```

```
?Can't write that page
```

```
@SET PAGE-ACCESS 0 COPY-ON-WRITE
```

```
@DEPOSIT 500 32
```

```
[Shared]
```

```
@INFORMATION MEMORY-USAGE
```

```
1. pages, Entry vector loc 145 len 254000
```

```
0 Private R, W, E
```

- Learn what files are opened when you edit a file.

```
@SET TRAP FILE-OPENINGS
```

```
@EDIT LOGIN.CMD
```

```
[Fork EDIT opening SWITCH.INI.3 for reading]
```

```
[Fork EDIT opening LOGIN.CMD.33 for reading]
```

```
Edit: LOGIN.CMD.33
```

```
[Fork EDIT opening EDIT-BUFFER.OUT.100042 for writing]
```

```
*EU
```

```
[Fork EDIT opening EDIT-BUFFER.OUT.100042 for reading]
```

```
[Fork EDIT opening LOGIN.CMD.34 for writing]
```

```
[LOGIN.CMD.34]
```

- Cause a trap to occur whenever the GTFDB JSYS is executed. Then edit a file. The EDIT command invokes the GTFDB JSYS and causes a line to type out in the following format:

```
[fork "trap" <location>/<jsys name> "Ac's 1-4:" -
<ac contents>]
```

Note that the location is in symbolic form if you so specified in the SET TYPEOUT MODE command.

```
@SET TRAP JSYS GTFDB
```

```
@EDIT LOGIN.CMD
```

```
[EDIT trap 3515/ GTFDB Ac's 1-4: 11 1000004 20321 424153000000]
```

```
[EDIT trap 3562/ GTFDB Ac's 1-4: 11 2000011 4 424153000000]
```

```
Edit: LOGIN.CMD.42
```

```
*EU
```

```
[LOGIN.CMD.43]
```

SET (Cont.)

7. Specify that program execution is to halt whenever a GTFDB JSYS causes a trap. Then edit a file. The EDIT command invokes the GTFDB JSYS, causing a trap to occur, which causes the EDIT process to immediately halt.

```
@SET TRAP NO PROCEED
@SET TRAP JSYS GTFDB
@EDIT LOGIN.CMD
[EDIT trap 3515/ GTFDB Ac's 1-4: 10 1000004 20321 424153000000]
```

8. Arrange for the system to remind you of a future obligation. Then verify that you will be reminded.

```
@SET ALERT MONDAY +11:00:00 Turn in time card
@SET AUTOMATIC
@INFORMATION ALERTS
Next alert at 8-Jun-84 16:55:00 - Almost time to go home!!
Other alerts set for:
  11-Jun-84 08:55:00 - Project meeting at 9:00
  14-Jun-84 11:00:00 - Turn in last week's time card by noon
```

Alerts are automatic

9. Set the CHANGE and RADIUS programs to be automatically placed in kept forks when they are run. Then give the INFORMATION PROGRAM-STATUS command to display all the SET PROGRAM settings. Finally, run the CHANGE program. Note that the message [Keeping CHANGE] indicates that the program is being loaded into a kept fork.

```
@SET PROGRAM RADIUS KEEP CONTINUE
@SET PROGRAM CHANGE KEEP CONTINUE
@INFORMATION (ABOUT) PROGRAM
Used 0:00:35 in 0:24:09
TOPS-20: 0:00:00.8
SET UUC-SIMULATION (FOR PROGRAM)
SET TYPEOUT MODE NUMERIC
SET PROGRAM RAD KEEP (AND) CONTINUE (WHEN INVOKED AS A COMMAND)
SET PROGRAM CAN KEEP (AND) CONTINUE (WHEN INVOKED AS A COMMAND)
SET PROGRAM MS KEEP (AND) START (WHEN INVOKED AS A COMMAND)
SET PROGRAM DSRPLUS KEEP (AND) START (WHEN INVOKED AS A COMMAND)
=> MS (1): Kept, C from IO wait at 104062, 0:00:01.6
@RUN CAN
[Keeping CAN]
CAN>
```

10. Arrange for the system to check for new mail in your MAIL file and in the MAIL file of user AI.GROUP. Notice the two messages indicating that you and AI.GROUP have new mail. Then, cancel mail watching for user AI.GROUP.

```
@SET MAIL-WATCH
@SET MAIL-WATCH AI.GROUP
[You have mail from SMITH at 10:12:11]
[AI.GROUP has mail from NELSON at 10:12:14]
@SET NO MAIL-WATCH AI.GROUP
```

SET (Cont.)

11. Use the DIRECTORY command to learn the name of the directory that contains a system program. Then enable your Wheel or Operator privileges and set the system file ephemeral.

```
@DIRECTORY SYS:ISPELL
    RANDOM:<UNSUPPORTED>
    ISPELL.EXE.1
@ENABLE
$SET FILE EPHEMERAL RANDOM:<UNSUPPORTED>ISPELL.EXE
    RANDOM:<UNSUPPORTED>ISPELL.EXE.1 [OK]
$DISABLE
@
```

12. Add one of your own directories to the definition of SYS: so that you can run programs in that directory by typing just the program name.

```
@DEFINE SYS: => SYS:, STUDENTS:<DBONIN.TOOLS>
```

Next, set ephemeral a file in this directory. Run the program in an ephemeral fork by typing the program name. Then CTRL/C from the program. Give the INFORMATION FORK-STATUS command and note that the ephemeral fork CHANGE has been reset.

```
@SET FILE EPHEMERAL CHANGE.EXE
@CHANGE
CHANGE>^C
@INFORMATION FORK-STATUS
=> EDIT (1): HALT at 6253, 0:00:00.6
```

13. Run an ephemeral system program and disable the program's ephemeral attribute.

```
@SET PROGRAM CHANGE NO-EPHEMERAL
@CHANGE
CHANGE>
```

or

```
@R CHANGE
CHANGE>
```

14. Give the SET STATUS-WATCH command with the INTERRUPT subcommand to specify CTRL/B as the interrupt character. Then give the PAGES subcommand to specify the range of pages to be checked by the interrupt character. Display both settings with the LIST-PARAMETERS subcommand:

```
@SET STATUS-WATCH,
@INTERRUPT "^B"
@@PAGES 0:777
@@LIST-PARAMETERS
Enabled on "^B", Checking pages: 1-512
@@
```

SET (Cont.)

Next run the DSRPLUS program and check its status by typing CTRL/B. This program reads the input file MEMO.RNO and creates the output file MEMO.MEM. Note that the ^B is not displayed on the terminal.

```
@DSRPLUS  
DSRPLUS>MEMO.RNO
```

```
^B  
Connected to BLAZE:<ROBBERTS>  
6 PUBLIC:MEMO.RNO.1 [Page 1 of 9. Byte 128(36). Read]
```

```
^B  
Connected to BLAZE:<ROBBERTS>  
7 MEMO.MEM.1 [Page 3. Byte 512(36). Read Write]  
6 PUBLIC:MEMO.RNO.1 [Page 4 of 9. Byte 1280(36). Read]
```

```
^B  
Connected to BLAZE:<ROBBERTS>  
7 MEMO.MEM.1 [Page 8. Byte 3840(36). Read Write]  
6 PUBLIC:MEMO.RNO.1 [Page 8 of 9. Byte 3968(36). Read]
```

```
DSRPLUS>
```

Now look at the above display. The first time CTRL/B is typed, DSRPLUS is reading the first page of the nine page input file MEMO.RNO. The second CTRL/B shows that DSRPLUS is reading page four of the input file and has created three pages of the output file MEMO.MEM. Nearing its completion, DSRPLUS has read eight of the nine input pages and has created an eight page output file.

SET HOST

Function

Connects your terminal to another system.

Format 1

@SET HOST node-name:: /switch

Format 2

(Omitting the node name on the command line allows you to define an interrupt sequence)

@SET HOST /switch

Two character interrupt sequence (^\Node name: node-name::

where

node-name:: is the name of the remote host that you want to connect your terminal to. Two colons (::) following the node name are optional.

/switch is an optional keyword that selects the service used to connect your terminal to a remote node.
Default - /CTERM

interrupt-sequence is the characters that switch control of the terminal back to the local host. You are prompted for an interrupt sequence only if you give the /CTERM switch.
Default - CTRL\

NOTE

This command description assumes you are connecting to another TOPS-20 system. For information on accessing other operating systems, see the DIGITAL Networking Pocket Guide. This command description also assumes that you are establishing a connection with the CTERM program.

SET HOST Command Switches

/CTERM connects your terminal to the remote node by running the CTERM communications program. Both processors must be running DECnet Phase 4 software (available under a separate license). The SET HOST command runs the CTERM communications program by default. If the remote node does not support the CTERM protocol, SET HOST attempts the connection again. In the second attempt however, SET HOST runs the communications program defined by the logical name NRT: (Network Remote Terminal).
Default

SET HOST (Cont.)

/NRT runs the communications service program defined by the logical name NRT: (Network Remote Terminal). NRT: can be a system or job logical name. When both exist, the job definition takes precedence.

Characteristics

Logging into the Remote Node

Once your terminal is connected to the remote node, the system responds by identifying itself and prompting you to log in. You can then log in to the system.

Path of Terminal Input and Output

The SET HOST command passes terminal input through the local host to the remote host. Output from the remote host passes through the local host to your terminal.

Making a Series of Host Connections

Once you have logged in to a remote node, you can give EXEC commands and run programs just as you would on your local node. You can then establish a connection to another remote node. For example, if your local host is AURORA, you can give the command SET HOST BOSTON to connect to the node BOSTON; after logging in to BOSTON, you can use the command SET HOST DENVER to connect to node DENVER.

Returning to Your Local Host

To return your terminal to your local host, type the interrupt sequence to temporarily break the connection to the remote host. Note that the connection to the remote host remains intact until you reset the CTERM program. You can reconnect your terminal to the remote host by giving the CONTINUE command.

When you log out of the remote host, the connection is broken and you are returned to your local host.

If you have established a series of connections, the interrupt character defined in your first SET HOST command returns you to your local host. For example, your local host is AURORA and you SET HOST to BOSTON, specifying the CTRL\<RET> interrupt sequence to return to AURORA. Then from BOSTON you connect to DENVER. Typing the CTRL\<RET> interrupt to DENVER returns you to AURORA, not BOSTON.

SET HOST (Cont.)

Specifying the Interrupt Sequence

- The interrupt sequence can be a combination of two characters or control characters. For example, KL ^KL, K^L, and ^K^L are valid interrupt sequences.
- If you specify only one interrupt character, the second character is ^J. For example if you specify only ^N as the interrupt sequence, the actual interrupt sequence is ^N^J. If you type only F, the interrupt sequence is F^J.
- Each interrupt character must be different. For example, ^K^K is invalid, while ^KK is a valid interrupt sequence.
- Do not type a comma or a space between interrupt characters as it will be interpreted as the second character in the sequence.
- The RETURN key can only be used in the default interrupt sequence, ^\- The interrupt sequence cannot contain predefined TOPS-20 control characters. For example, if you attempt to specify an interrupt sequence as ^T^I, the ^T will print the run status and the ^I will print a tab. See Appendix D in this manual for a list of TOPS-20 control characters.

Controlling Scrolling on a Remote Host

On your local host, <CTRL/S> and <CTRL/Q> are the default control characters that pause and continue scrolling. Typing <CTRL/Q> continues scrolling whether scrolling paused because you typed <CTRL/S> or the output paused on an end-of-page.

However, CTERM does not pass these characters to the remote host. When using <CTRL/S> and <CTRL/Q>, it is the local host that actually controls scrolling. Therefore if output from the remote host has paused on an end-of-page, <CTRL/Q> will not continue scrolling. Other pause and continue characters are passed to the remote host. You can use <CTRL/A> to both pause and resume scrolling or you can use the TERMINAL PAUSE command to assign any two characters of your choosing to control scrolling. For consistency, it is recommended that you define the same pause and continue characters on your local and remote node.

Hints

Listing Available Nodes

Use the INFORMATION DECNET command to display the names of DECnet nodes accessible to your node.

SET HOST (Cont.)

Effect on Terminal

The SET HOST command connects your terminal to the remote system. After the remote system's herald message is printed, you can log in.

Related Commands

CONTINUE	for resuming a connection that was broken with an escape sequence.
INFORMATION DECNET	for displaying the names of nodes reachable from your node.
INFORMATION JOB-STATUS	for displaying the name of the host node and other information about your job.
INFORMATION LOGICAL-NAMES NRT:	for displaying the name of the communications program run by /NRT.
SYSTAT	for displaying (in the ORIGIN column) the name of the local system (the system you connected to before connecting to the current remote system).

Examples

1. Connect your terminal to a remote TOPS-20 node named AURORA and then login.

@SET HOST AURORA

[Attempting a connection, connect OK,]
[Remote host is a TOPS-20 system]
[TYPE ^\,<RET> to return to node ROMAX]

AURORA - Claims Tracking System, TOPS-20 Monitor 6.1(7)

@LOGIN RSMITH

Job 4 on TTY315 15-Nov-84 09:35:03, Last Login 15-Nov-84 08:18:48

SET HOST (Cont.)

2. Give the INFORMATION DECNET command to find out if node BOSTON is reachable from your host node. Then give the SET HOST command without typing the node name on the command line. Omitting the node name causes the system to prompt you for an interrupt sequence. After typing your own interrupt sequence, the system prompts you for the name of the remote node.

```
@INFORMATION DECNET BOSTON
```

```
Node BOSTON is reachable
```

```
@SET HOST
```

```
Two character interrupt sequence (^\): ^ED
```

```
Node name: BOSTON
```

```
[Attempting a connection, connect OK, ]
```

```
[Remote host is a TOPS-20 system]
```

```
[TYPE ^E,D to return to node AURORA]
```

```
BOSTON, AI Engineering Center, TOPS-20 Monitor 6.1(7)
```

```
@
```

3. Connect to a remote node named TEAL. After logging in and doing some work on TEAL, type the ^\

```
@SET HOST TEAL
```

```
[Attempting a connection, connect OK, ]
```

```
[Remote host is a TOPS-20 system]
```

```
[TYPE ^\
```

```
TEAL - Migratory Bird Banding, TOPS-20 Monitor 6.1(7)
```

```
@LOGIN LOWELL
```

```
Job 4 on TTY315 15-Nov-84 09:35:03, Last Login 15-Nov-84 08:18:48
```

```
.
```

```
^\
```

```
[Connection interrupted, back at node FLYWAY,
```

```
Type CONTINUE to resume connection]
```

After working on node FLYWAY, type the CONTINUE command to reconnect your terminal to node TEAL. Then give the INFORMATION JOB-STATUS command to verify that you are connected to TEAL.

```
@CONTINUE
```

```
@INFORMATION JOB-STATUS
```

```
Host TEAL
```

```
Job 17, TTY4, User LOWELL, REPORTS:<LOWELL>
```

```
Account 341
```

SET HOST (Cont.)

4. Attempt a connection using the CTERM program. The system attempts the connection and finds that the remote node does not support CTERM. It then attempts another connection using the program defined by NRT:

@SET HOST ROMAX

[Attempting a connection,
Connect failed -

Host did not accept CTERM connection, trying NRT:

[Attempting a connection, connect OK]
[Remote host is a TOPS-20 system]
[TYPE ^P to return to node AURORA]

ROMAX - Acme's Timesharing System, TOPS-20 Monitor 6.1(7)
@

SKIP

Moves a magnetic tape set forward over a specified number of files or records, or to the logical end of the tape set.

Format

@SKIP (DEVICE) dev: n units

where

dev: is the name of the tape set or magnetic tape drive that you want to move forward

n is the number of files or records over which you want to skip. The colon after the device name is optional.

units is either FILES or RECORDS, where records are sections of a file; or LEOT, to skip to the logical end of the tape set, which is the next point on the tape set having two adjacent EOF (end-of-file) marks.
Default units - FILES

Restrictions

SKIP With Open Files

If you have given a CTRL/C to exit from a program that has opened a file in a magnetic tape set and you then give the SKIP command for that tape set, the system will first ask if you want to close the associated file. You must do so for SKIP to succeed, but you will probably be unable to continue the program from that point because the file will now be closed.

RECORDS Argument Used for Unlabeled Tapes Only

You cannot use the RECORDS argument to the SKIP command when using a labeled tape, because read and write operations for labeled tapes always move the tape to the beginning of a file.

Warning

Skipping Past LEOT (Unlabeled Tapes Only)

If you specify too large a value for n in the SKIP command line, you can move past the logical end of tape (LEOT). In this case, the operator may have to intervene before your tape control commands will have effect again. You must be sure how many files you have in the tape set if you use SKIP n rather than SKIP LEOT. This problem can occur for any tapes mounted on drives of the form MTAn:, or for unlabeled tapes mounted on drives of the form MTn:.

SKIP (Cont.)

Related Commands

UNLOAD for rewinding a magnetic tape completely onto the source reel (only for tapes mounted on drives having device names of the form MTn:)

Examples

1. Skip over the next 2 files on the magnetic tape you are using (mounted on magnetic tape drive MT0: in this case).

@SKIP MT0: 2 FILES

2. Skip over the next two records on an unlabeled tape.

@SKIP MTA0: 2 RECORDS

3. Use the MOUNT command to ask the operator to mount your tape in write-enabled mode, then copy 3 files to the tape from your directory on structure SNARK:. Use the REWIND command to go back to the beginning, and the SKIP command to skip over the first file. Use the COPY command to have the next file (FIL-2) printed on your terminal, then give the SKIP command again to skip to the logical end-of-tape. You are skipping only one file, FIL-3, in this case.

@MOUNT TAPE DAY:/WRITE-ENABLED
[Mount Request DAY Queued, Request-ID 187]
[Tape set DAY, Volume DAY mounted]
[DAY: defined as MT0:]
@REWIND DAY:
@MOUNT STRUCTURE SNARK:
Structure SNARK: mounted
@ACCESS SNARK:
@COPY SNARK:FIL-1.TAP DAY:
SNARK:FIL-1.TAP.1 => MT0:FIL-1 [OK]
@COPY SNARK:FIL-2.TAP DAY:
SNARK:FIL-2.TAP.1 => MT0:FIL-2 [OK]
@COPY SNARK:FIL-3.TAP DAY:
SNARK:FIL-3.TAP.1 => MT0:FIL-3 [OK]
@REWIND DAY:
@SKIP DAY: 1
@COPY DAY: TTY:
T0: => TTY:

! THIS IS THE SECOND FILE. !
@SKIP DAY: LEOT

START

Begins execution of the program in the current fork.

Format

| @START (PROGRAM) location/switch

where

location is the octal or symbolic address where you want
 the program to start
 Default location - the normal starting address,
 that is, the first word in the
 program's entry vector

/switch is a keyword, chosen from the list below,
 indicating your choice of START command options

START Command Switches

| /BACKGROUND keeps your terminal at TOPS-20 command level and starts
 execution of the program in a "background" fork. When
 the program attempts to do terminal input or output, it
 halts and displays the message [FORK-NAME wants the
 TTY].

| /NORMALLY restores your terminal to command level (if any) within
 the program
 Default

| /STAY keeps your terminal at TOPS-20 command level. Output
 from the program is sent to the terminal and is
 intermixed with whatever output is currently displayed.
 When the program attempts to read from the terminal, it
 can randomly intercept input intended for the EXEC or
 another program. Therefore, use this switch with
 programs that, once started, do not request further
 terminal input.

Characteristics

Starting a Noncurrent Fork

When you START a noncurrent fork, the fork becomes your
current fork.

START (Cont.)

Hints

Further Information

The START command is one of the TOPS-20 multiforking-class commands. For more information about multiforking, see the section named Running Multiple Programs in the TOPS-20 User's Guide.

For more information about entry vectors, see the TOPS-20 Monitor Calls Reference Manual.

Special Cases

Running COBOL Programs a Second Time

After running a program (with a RUN or EXECUTE command, or with a GET and START or LOAD and START combination) you can usually run it again using START. COBOL programs are an exception: to run them again you must reload them.

Restrictions

Programs Competing for Terminal Input

If you use START /STAY to run a program in a background fork, either at the current or at a lower EXEC command level, (see Hints - Using PUSH to Get a New TOPS-20 Command Level, above), the program can request input from the terminal while you are giving input to the EXEC or another program. This input can be randomly intercepted by the background program when it requests terminal input. Usually though, the EXEC or the current program receives the input.

When terminal input is intercepted by the background program, the program usually types input error messages. To give input to the program, stop the program by typing two CTRL/Cs or the program's exit command. Then, if the background program is at a higher EXEC command level, give POP commands to return to the EXEC level that holds the background program. (POP terminates the current EXEC and erases programs in its memory.) Finally, give the CONTINUE /NORMALLY command; this puts you at program command level so that you can give the requested input.

Input is intercepted by the background program randomly. Therefore, you may have to type extra CTRL/Cs, program exit commands, and POPs. To reduce confusion about the direction of terminal input, it is recommended that you use START /STAY only when you plan to work at the current EXEC level while a program runs in a background fork. Use START /BACKGROUND when you plan to work at a lower EXEC level or at another program command level.

When a program started with START BACKGROUND requests terminal input, it sends the message, [FORK-NAME wants the TTY]. No input is taken by the background program until you return to program command level with CONTINUE /NORMALLY.

START (Cont.)

No I/O Control with Some Programs

Most programs read and write data to the terminal through standard input and output designators. Some programs however, use different methods of communicating with the terminal. Therefore, when you use /BACKGROUND and /STAY to control terminal input and output from a background fork, the input and output behavior of programs with nonstandard designators can be unpredictable.

Execute-only Programs

Programs that are execute-only can only be started at their normal starting address.

Related Commands

CONTINUE	for resuming execution of a halted program in memory
FORK	for changing the current fork
FREEZE	for halting a program in a background fork
GET	for placing executable programs in memory
INFORMATION FORK-STATUS	for displaying the number and the status of each fork in your job
KEEP	for giving a fork a kept status
LOAD	for loading source or object programs into memory
REENTER	for starting the program in memory at its alternate entry point (if any)
SAVE	for saving a loaded program in an .EXE file
ERUN, RESET, SET NAME, SET PROGRAM, UNKEEP	other multiforking-class commands for performing related functions

Examples

1. Start the program currently in memory.

@START

START (Cont.)

2. Put an executable program in memory and start it. Then run it again.

```
@GET TESTF1.EXE
```

```
@START
```

```
THIS IS A TEST.
```

```
END OF EXECUTION
```

```
CPU TIME: 0.04 ELAPSED TIME: 0.23
```

```
EXIT
```

```
@START
```

```
THIS IS A TEST.
```

```
END OF EXECUTION
```

```
CPU TIME: 0.02 ELAPSED TIME: 0.02
```

```
EXIT
```

3. Begin using the FILCOM program to compare two files. Give a CTRL/C to halt FILCOM, then a CTRL/T to determine the location where it was stopped. Give the DDT command, and do some work within the DDT program; leave DDT with a CTRL/Z, returning to TOPS-20 command level. Give the START command to start FILCOM again, using as argument the address reported by CTRL/T above.

```
@FILCOM
```

```
*TTY:=DUMPER.MAC, BACKUP.MAC
```

```
^C
```

```
^T 14:49:03 FILCOM ^C from Running at 400543 Used 0:00:03.1 -  
in 0:04.39, Load 2.44 in 0:01:33
```

```
@DDT
```

```
DDT
```

```
3/ PAT..+361,,3066
```

```
4/ 56
```

```
^Z
```

```
@START 400543
```

```
No differences encountered
```

4. Place the CLOCK program (not DIGITAL supported) in memory. KEEP the CLOCK program so that it will remain in memory when you run other programs. Then, start the CLOCK program in the background. CLOCK will display the time every half hour while you run other programs and EXEC commands.

```
@GET CLOCK.EXE
```

```
@KEEP
```

```
@START CLOCK.EXE /STAY
```

```
@
```

```
.
```

```
.
```

```
.
```

```
[11:30 AM]
```

SUBMIT

Enters a command procedure into the batch job queue.

Format

@SUBMIT (BATCH JOB) /switch(es) filespec/switch(es),...

where

switches are keywords, chosen from the list below, indicating your choice of SUBMIT command options. These switches have different effects according to their position in the command line: placed before all files in the command, they act as defaults for all; otherwise they affect only the nearest preceding file.

Defaults are shown in the list of switches

filespec is the specification of a batch control file (see the TOPS-20 User's Guide), containing batch commands and the commands with which you would have done the job as a timesharing user instead of as a batch user
Default file type - .CTL

,... means that after a comma you can give more arguments (filespec and switches) of the form already shown

Summary of SUBMIT Command Switches (defaults in boldface)

/ACCOUNT:account	Default account - your current account
/AFTER:date and/or time YES	
/ASSISTANCE:NO APPEND	
/BATCH-LOG:SUPERSEDE SPOOL	
/BEGIN:n	Default n - 0
/CARDS:n	Default n - 1000
/CONNECTED-DIRECTORY:dev:<directory>	
/DELETE	
/DEPENDENCY-COUNT:n	Default n - 0
/DESTINATION-NODE:node name	
/FEET:n	Default n - 200
/JOBNAME:6-character name	Default name - first six characters of control filename
KEEP	
/LOGDISPOSITION:DELETE	
/LOGNAME:filespec	Default filespec - control filename, file type .LOG

SUBMIT (Cont.)

```

        YES
/NOTIFY:NO
        ALWAYS
/OUTPUT:ERRORS
        NOLOG
/PAGES:n                Default n - 200
/PRIORITY:n             Default n - 10
/PRESERVE
/PROCESSING-NODE:node name
/READER
        NO
/RESTARTABLE:YES        Default argument (if switch is
                        given) - YES

/SEQUENCE:n
/TAG:6-character label
/TIME:hh:mm:ss          Default time limit (if switch is
                        omitted) - 00:05:00
                        Default hh:mm:ss (if switch is
                        given without colon or
                        argument) - 60 (minutes)
                        Default n - 200

/TPLOT:n
        NO or 0
/UNIQUE:YES or 1
/USER:user name

```

SUBMIT Command Switches

```

/ACCOUNT:account        specifies the account of 39 or fewer
                        characters to charge for your batch
                        request. This account must be valid
                        for your user name.
                        Default account - your current
                        account (check
                        with
                        INFORMATION
                        JOB-STATUS)

/AFTER:date and/or time, or
        day of week (or TODAY)
        and/or time      ensures that the job will not be
                        started until after the date and/or
                        time specified. NOV-12-79, and
                        18:00:00 illustrate two arguments to
                        this switch. If you give both date
                        and time, separate them with a space.
                        When given alone, the time may be
                        preceded with a plus sign (+), which
                        will delay processing by the
                        indicated length of time from the
                        present.

```

SUBMIT (Cont.)

Alternatively, you may give a day of the week (e.g., MONDAY) or TODAY as argument; then the batch job will not be started until the beginning of the following day. If you follow this argument with a plus sign and a time, the job will be further delayed by this amount.

YES
/ASSISTANCE:NO

tells the system whether your job will require the assistance of the operator (e.g., to mount a structure or magnetic tape) when it is run
Default - YES

APPEND
/BATCH-LOG:SUPERSEDE
SPOOL

tells the system either to append the log file of the batch job to any existing log file of the same name, or to write a new generation of the log file, or to send the log file to the spool area only
Default - APPEND

/BEGIN:n

starts processing the control file at line n of the file. Use this switch for a control file that can fit different applications depending on where processing begins. (See also the /TAG switch.)
Default n - 0

/CARDS:n

limits to n the maximum number of cards to be punched by the job
Default n - 1000

/CONNECTED-DIRECTORY:dev:<directory>

specifies the connected directory for the batch job. For privileged users only.

/DELETE

tells the system to delete the control file after the batch job has run. Opposite of /PRESERVE.

/DEPENDENCY-COUNT:n

sets the job's dependency count to n. Because a batch job does not get processed until its dependency count is 0, you can delay a job by assigning it a positive dependency count and then using the MODIFY command to bring the count to 0 at the proper time.
Default n - 0

SUBMIT (Cont.)

	/DESTINATION-NODE:node-name	specifies the IBM remote job entry station on whose line printer the log file of your batch job is to be printed. Two colons (::) following the node name are optional.
	/FEET:n	limits to n the maximum number of feet of paper tape to be punched by the job Default n - 200
	/JOBNAME:name	assigns a name (of six or fewer characters) to the batch job Default name - first six characters of control filename
	KEEP /LOGDISPOSITION:DELETE	tells the system whether to delete the log file after it has been printed Default - KEEP
	/LOGNAME:filespec	specifies where to place the log file of the batch job Default dev:<directory> - your connected directory at the time of the SUBMIT command Default filename - control filename Default type - .LOG
	YES /NOTIFY:NO	tells the system whether to send a message to your terminal /xp /NOTIFY switch when the batch job has been completed Default argument - NO Default argument (if switch is given) - YES
	ALWAYS /OUTPUT:ERRORS NOLOG	says whether you want the log file to be printed always, or only in the case of unhandled errors occurring within the job, or never. No matter which option you choose, the log file is always written. Default - ALWAYS
	/PAGES:n	limits to n the maximum number of pages of line printer output to be printed by the job Default n - 200

SUBMIT (Cont.)

/PRESERVE

tells the system not to delete the control file after the batch job has run. Opposite of /DELETE.

Default

I-28 /PRIORITY:n assigns a decimal number n to the job, reflecting the urgency of the batch request. This n must be from 0 to 63, with larger numbers receiving earlier treatment. The system acknowledges this switch by displaying the message [Priority has been modified].

Default n - 10

/PROCESSING-NODE:node name::

specifies the IBM host system on whose CPU the JCL batch job is to be run. Two colons (::) following the node name are optional.

/READER

tells the system that your control file is composed of card images, including control cards, on disk. For details see the TOPS-10/20 Batch Reference Manual.

NO

/RESTARTABLE:YES

decides whether the job should be started again if the system crashes and is restarted

Default argument - NO

Default argument (if switch is given) - YES

/SEQUENCE:n

specifies that n, instead of a number supplied by the system, is to be the sequence number of the job

/TAG:label

starts processing the control file at the line beginning with label::, where label is an alphanumeric name of six or fewer characters. Use this switch for a control file that can fit different applications depending on where processing begins.

/TIME:hh:mm:ss

limits the maximum amount of CPU time available to the job; given in hours, minutes, and seconds.

Default time limit (if switch is omitted) - five minutes

Default hh:mm:ss (if switch is given without colon or argument) - 60 (minutes)

SUBMIT (Cont.)

/TPLOT:n limits to n the maximum number of minutes of plotter time allowed for plotter time allowed for the job
Default n - 200

NO (or 0)
/UNIQUE:YES (or 1) when submitting multiple batch jobs, tells the system whether to run the jobs concurrently or at separate times. The control files must be submitted while connected to the same directory; the control files can be located in any directory. This switch applies to batch jobs submitted with a single or multiple SUBMIT commands. Refer to Example 5.
Default - YES

/USER:user name specifies the user who is to be the owner of the batch request. For privileged users only.

Output

Jobname, Request ID, and Time Limit

As soon as you complete a valid SUBMIT command, the system responds by printing, on your terminal, the jobname, request ID, and time limit for the job. Each control file you submit is a separate batch request, and is described on a separate line.

Characteristics

Switch Defaults Set by System Manager

The defaults shown in the list of switches are correct for most user sites. However, your system manager can change some of these default settings. The changes go into effect during system installation. The switches most commonly affected are: /CARDS, /FEET, /OUTPUT, /PAGES, /PRIORITY, /TIME, and /TPLOT.

Disposition of Log Files

The three SUBMIT command switches /BATCH-LOG, /LOGDISPOSITION, and /OUTPUT, control what happens to the log file of your batch job.

SUBMIT (Cont.)

Where Written

The log file is always written as the job runs, either to the batch job's connected directory, or to a directory specified as argument to the /LOGNAME switch, or to the system's output spooling area (it is written to the spooling area only if you give the /BATCH-LOG:SPOOL switch). If the /DESTINATION-NODE switch is also given, the log file will be written into a directory or spooling area at the specified node. Remember that a batch job's connected directory is ordinarily defined to be your connected directory at the time of the SUBMIT command; privileged users may specify a batch job's connected directory by using the /CONNECTED-DIRECTORY switch.

How Written, When Printed

The /BATCH-LOG switch's APPEND and SUPERSEDE arguments describe the manner in which the log file is to be written: either it is appended to any existing file of the same name (usually produced by a previous running of the batch job) or it is written as a new generation of the file. The /LOGDISPOSITION switch tells the system whether to keep this file, wherever it is written, once the batch job is finished. The /OUTPUT switch specifies when you want a listing of the log file to be printed: either always, or never, or only if errors occur when the batch job is run. By using combinations of these switches you can cause any desirable action. Giving /OUTPUT:ALWAYS along with /LOGDISPOSITION:DELETE allows a record of your batch job with only a temporary use of your disk area, and permits you to monitor the progress of the job while it is running (give TYPE commands to view the file at your terminal). Giving just the /BATCH-LOG:SPOOL switch allows a record without any use of your disk area, although then you must wait for the printed output to see this record.

Execution of Command Files

As soon as one of your batch jobs logs in, the system processes your login directory's command files and the system's command files. The files are processed in this order:

1. SYSTEM:BATCH.CMD
2. BATCH.CMD
3. SYSTEM:COMAND.CMD
4. COMAND.CMD

If a LOGOUT command is included in the batch control file, the system processes your login directory's LOGOUT.CMD file followed by the system's SYSTEM:LOGOUT.CMD file. These files are not processed if the batch job is logged out automatically.

Automatic Logout

If the batch control file is not terminated by a LOGOUT command, the batch job is logged-out automatically and the message "KILLED BY OPERATOR TTYnn" is printed in the log file.

SUBMIT (Cont.)

Hints

Using SET DEFAULT SUBMIT

If there are switches that you always or usually supply when using SUBMIT, give the SET DEFAULT SUBMIT command to establish them as defaults for the remainder of your terminal session. The switches will then behave as if you had typed them directly after the word SUBMIT. You can supersede any of these default switches by actually supplying the switch, with another value, when you give the SUBMIT command.

For Future Terminal Sessions

Put SET DEFAULT SUBMIT commands into a file named COMAND.CMD or LOGIN.CMD in your log-in directory if you want these default switches to be in effect for batch jobs you submit during future terminal sessions as well. If both files exist, the system reads LOGIN.CMD first.

For Nested Batch Jobs Only

Put SET DEFAULT SUBMIT commands into a file named BATCH.CMD in your log-in directory if you want them to be in effect at the log-in time of a "nested" batch job only, that is, a batch job started by a SUBMIT command within the control file of another of your batch jobs. Note, however, that the system also reads COMAND.CMD at the log-in time of a batch job if the file exists in your log-in directory. It reads this file after BATCH.CMD.

Monitoring the Progress of a Batch Job

You can include the SEND command or the commands that run the MAIL or DECmail/MS mail programs in your batch control file. Use these commands to send messages to your terminal informing you of the status of your batch job. Since a batch job creates a job in addition to your timesharing job, use the terminal line number argument instead of the user name argument in the SEND command.

More Information

For more information about batch jobs, see the TOPS-10/20 Batch Reference Manual.

SUBMIT (Cont.)

Restrictions

Access Rights for Batch Jobs

For Specifying Control Files and Log Files

You cannot use the ACCESS command to obtain the right to submit control files from another directory, because your batch jobs are logged in with rights only to your connected directory and to directories to which you (through your login directory name) have access as a group member. The control file, if not in your connected directory, must be in one to which you have read access as a group member; the log file specification, if you give one, must be for your connected directory or for one to which you have write access as a group member.

For Use Within the Batch Job

Although it is possible to give CONNECT and ACCESS commands within a batch job to obtain rights beyond those mentioned above, you may then have to include passwords in the job's control file. Because this practice could endanger system security, it is generally best to establish and rely on appropriate group rights when preparing batch jobs for submission.

PUSH During Batch Job Execution

Note that a PUSH command reads the COMAND.CMD file. Therefore, if your batch control file contains a PUSH command, only the defaults set in COMAND.CMD are in effect while in the inferior EXEC.

Editing a Queued Control File

The batch system processes the exact version of the control file specified in your SUBMIT command. Therefore, if you edit a file while it is in the batch queue, the new version of the file will not be processed.

To change the request to process the latest version of the control file, CANCEL the request and resubmit the job.

Related Commands

CANCEL	for withdrawing SUBMIT requests
INFORMATION BATCH-REQUESTS	for examining in the batch input queue
MODIFY	for changing SUBMIT requests before processing has begun
SET DEFAULT SUBMIT	for establishing default switches for subsequent SUBMIT commands

SUBMIT (Cont.)

Examples

1. Submit a control file to begin a batch job.

```
@SUBMIT DIFS.CTL
[Batch job DIFS queued, request-ID 461, limit 0:05:00]
```

2. Submit two control files (specifying only the filenames) in the same command. then use the information batch-requests command (with the /USER switch) to examine your entries in the batch input queue.

```
@SUBMIT SUMS, DIFS
[Batch job SUMS queued, request-ID 629, limit 0:05:00]
[Batch job DIFS queued, request-ID 630, limit 0:05:00]
@INFORMATION BATCH-REQUESTS /USER
```

Batch Queue:

Job Name	Req#	Run Time	User
* SUMS	629	00:05:00	C.BURKE In Stream:2
Started at 15:21:01			
DIFS	630	00:05:00	C.BURKE

There are 2 jobs in the queue (1 in progress)

3. Connect to another user's directory, then submit two of his control files. Prevent the printing of a log file for one job, and allow the second job's to be printed only if errors occur within the job; make both jobs restartable. Request an inclusive listing of your entries in the batch queue - notice that the jobs are logged in under your own user name, although the log files will be stored in user Holland's directory. Note also that an asterisk (*) indicates a job currently in progress.

Connect back to your directory and submit one of your own control files, specifying a particular jobname, then check on it.

```
@CONNECT <HOLLAND>
```

Password:

```
@SUBMIT /RESTARTABLE:YES FLDTST.CTL/OUTPUT:NOLOG, LODT.CTL =
/OUTPUT:ERRORS
```

```
[Batch job FLDTST queued, request-ID 464, limit 0:05:00]
[Batch job LODTST queued, request-ID 465, limit 0:05:00]
@INFORMATION BATCH-REQUESTS /ALL/USER
```

Batch Queue:

Job Name	Req#	Run Time	User
* FLDTST	464	00:05:00	C.BURKE In Stream:2 /Uniq:Yes
/Restart:Yes /Assist:Yes /Seq:1993			
Started at 8:40:38			
LODTST	465	00:05:00	C.BURKE /Uniq:Yes /Restart:Yes
/Assist:Yes /Seq:1994			

There are 2 Jobs in the Queue (1 in Progress)

SUBMIT (Cont.)

```
@CONNECT MISC:<C.BURKE>
@SUBMIT SUMS/JOBNAME:1-SUMS
[Batch job 1-SUMS queued, request-ID 466, limit 0:05:00]
@INFORMATION BATCH-REQUESTS /ALL/USER
```

Batch Queue:

Job Name	Req#	Run Time	User
* 1-SUMS	466	00:05:00	C.BURKE In Stream:2 /Uniq:Yes /Restart:No /Assist:Yes /Seq:1995

Started at 8:41:29
There is 1 job in the queue (1 in progress)

4. Give a SET DEFAULT command to ensure that your batch jobs will be run after 5:00 P.M. unless you specify otherwise. Submit a batch job and check that this default is in effect. Then use a MODIFY command to delay the starting time of this job till 11:00 P.M. Finally, give the CANCEL command to withdraw the batch request entirely.

```
@SET DEFAULT SUBMIT /AFTER:17:00
@SUBMIT SUMS
[Batch job SUMS queued, request-ID 467, limit 0:05:00]
@INFORMATION BATCH-REQUESTS /USER
```

Batch Queue:

Job Name	Req#	Run Time	User
SUMS	467	00:05:00	C.BURKE /After: 9-Nov-85 17:00

There is 1 Job in the Queue (None in Progress)
@MODIFY BATCH 467 /AFTER:23:00
[1 Job modified]
@INFORMATION BATCH-REQUESTS /USER

Batch Queue:

Job Name	Req#	Run Time	User
SUMS	467	00:05:00	C.BURKE /After: 9-Nov-85 23:00

There is 1 Job in the Queue (None in Progress)

```
@CANCEL BATCH 467
[1 Job canceled]
```

5. Submit two control files, one located in your connected directory and the other in a directory you are accessing. Use the /UNIQUE:NO switch to allow the jobs to run simultaneously. Display the status of the batch queue and note that both jobs are running.

SUBMIT (Cont.)

```
@SUBMIT NETCOM.CTL, RANDOM:[LOWELL]CLEAN.CTL /UNIQUE:NO  
[Batch job CLEAN queued, request 58, limit 0:05:00]  
[Batch job NETCOM queued, request 59, limit 0:05:00]  
@INFORMATION BATCH-REQUESTS
```

```
Batch Queue:  
Job Name      Req#    Run Time      User  
-----  
* CLEAN        58    00:05:00    DBONIN          In Stream:0  
  Job# 156 Running EXEC Runtime 0:00:16  
* NETCOM        59    00:05:00    DBONIN          In Stream:1  
  Job# 156 Running EXEC Runtime 0:00:08  
  GTSTK         2    00:15:00    PURRETTA  
  CIGIDN         3    01:00:00    CSSE.WAIBLE  
There are 4 jobs in the queue (2 in progress)
```

SYSTAT

Displays information about the jobs on the system.

Format*

@SYSTAT,

where

@@subcommand means that, after a comma, you can give one or more subcommands on successive lines

Summary of SYSTAT Command Subcommands (defaults in boldface)

ALL
CLASS
CONTROLLING
DIRECTORY
HEADER
JOB job number n
LIMIT
LINE octal line number, or DETACHED
LPT
NO subcommand name, or OPERATOR, or .
ORIGIN
OUTPUT file specification
PROGRAM
STATE
SYSTEM
TIME
USER user name
WHAT
WHERE
WHO

SYSTAT (Cont.)

* For information on the in-line subcommand format, refer to the "Hints" section below.

SYSTAT Command Subcommands

ALL	gives all available SYSTAT information
CLASS	prints the scheduler class in which each job is running; the share of total CPU time allotted to the job, expressed as a decimal fraction; and the fraction of total CPU time actually used by the job. A job's actual use may be larger than its allotted share if some jobs in its class are inactive; it can be larger still if other classes are inactive and this unused fraction of CPU time is being allocated among active jobs.
CONTROLLING	prints, in the column headed CJB, the number of the controlling job (if any), that is, a job owning a PTY (pseudo-terminal) that controls the job being described; when used in a SYSTAT command requesting descriptions of particular jobs, this subcommand causes jobs controlled by these jobs to be described also.
DIRECTORY	requests the name of the directory to which each job is connected, if not the job's log-in directory
HEADER	calls for a headline identifying the columns of information printed Default (unless you are requesting information about specific users, jobs, or lines only; in such cases the default is NO HEADER.)
JOB n	restricts output to description of job number n; can be used more than once.
LIMIT	prints any time limit set for each job with the SET TIME LIMIT command. Print the amount of CPU time used by your job with CTRL/T or INFORMATION PROGRAM-STATUS.
LINE octal line number or DETACHED	restricts output to description of the job attached to the given line number, or to descriptions of all detached jobs; can be used more than once.

SYSTAT (Cont.)

LPT	sends output to the line printer instead of to your terminal
NO	<div> <div> . (period) CLASS CONTROLLING DIRECTORY HEADER LIMIT OPERATOR ORIGIN STATE SYSTEM TIME WHAT WHERE WHO </div> <div> eliminates the indicated category of information, when used with one of the keywords shown (. refers to your own job) </div> </div>
ORIGIN	displays the job's originating system, that is, the system from which the user connected to this system. Default
OUTPUT filespec	sends the output information to the file you specify, instead of to your terminal Default filespec - SYSTAT.LST
PROGRAM program name	restricts SYSTAT output to descriptions of jobs using the program (or TOPS-20 command) specified. The argument you supply must be of six or fewer characters.
STATE	prints the current state of each job, i.e., RUN (running), or TI (waiting for terminal input)
SYSTEM	begins output with system-wide information, i.e., the first two lines of regular output. If SYSTEM is the only subcommand given, SYSTAT output is restricted to this. Default (unless you give subcommands requesting information about specific users, jobs, or lines only; in such cases the default is NO SYSTEM.)
TIME	prints the accumulated runtime (CPU time) for each job
USER user name	restricts output to descriptions of jobs logged in under the given user name; can be used more than once.
WHAT	prints the name of the program that each job is running; given explicitly only with subcommand NO, to restrict SYSTAT output. Default

SYSTAT (Cont.)

WHERE prints the line number associated with each job; given explicitly only with subcommand NO, to restrict SYSTAT output.
Default

WHO prints the user name under which each job is logged in; given explicitly only with subcommand NO, to restrict SYSTAT output.
Default

Output

Sample of SYSTAT Output

The SYSTAT command displays on your terminal columns of information about all the jobs on the system. Below is a sample of the output you would receive in response to a SYSTAT command that eliminates the two rightmost columns (User and <Directory>):

@SYSTAT ALL NO WHO NO DIRECTORY

Tue 14-Aug-79 15:48:37 Up 1:12:59

45+11 Jobs Load av (class 0) 3.70 3.54 3.71

Job	CJB	Line	Program	State	Time	Cls	Shr	Use	Limit
5		25	TV	RUN	0:01:02	0	0.01	0.03	
7		6	TV	TI	0:00:35	0	0.01	0.02	
13	35	217	EXEC	RUN	0:01:02	1	0.15	0.00	
.
.
.

First you see the current date and time (in 24-hour notation: the sample above was obtained 37 seconds after 3:48 P.M.), and the length of time since the system was started (here, just over 1 hour).

The second line displays the number of user jobs (45) and operator jobs (11) currently running. The next three numbers are the "load averages" for the system: these are weighted averages of the number of runnable processes on the system over the last minute, 5 minutes, and 15 minutes, respectively. (If class scheduling is enabled, the three load averages are the average number of jobs having at least one runnable process, and apply to the class in which your job is running.) If you are about to start a job requiring 5 minutes of CPU time, and the load average remains stable over the period in question, i.e., becomes 4.54 (3.54 + your job = 4.54), then you can count on your job's getting about 1/4.54 of your class's share of the system's attention. If your class is assigned one third of the system's CPU time and you do not receive any windfall (unclaimed CPU time), your job will be finished in a little over one hour.

SYSTAT (Cont.)

After this comes the line of headings labeling each column of data that follows. All but the User, Origin and <Directory> columns of information appear in the sample above, describing all jobs (rows). The unmodified command SYSTAT displays the Job, Line, Program, User and Origin columns. The Origin column displays the job's originating host followed in parentheses by the network terminal type. For example, AURORA (CTM) means that the user logged in to node AURORA and then used the CTERM-SERVER protocol to connect his terminal to this system. The definitions of the network terminal types are:

CTM	CTERM-SERVER protocol terminal
LAT	Local Access Terminal
NRT	Network Remote Terminal
TCP	Advanced Research Project Agency Network (ARPANET) terminal

By using appropriate subcommands you can select the categories of information, as well as the specific jobs. (The Class (Cls) and Share (Shr) categories appear only if class scheduling is enabled.) User jobs, both timesharing and batch, are listed first (in ascending order by job number), and then, after a blank line, operator jobs. The number of the job attached to your own terminal appears with an asterisk (*) next to it in the Job column.

Sending Output Elsewhere

By giving the OUTPUT subcommand you can direct SYSTAT information to a file instead of to your terminal. The subcommand LPT sends the information to the printer instead of to your terminal.

Characteristics

Log-in Not Necessary

You do not have to be logged in to give the SYSTAT command.

Hints

Giving Subcommands as Arguments on the Command Line

To simplify your typing, SYSTAT accepts subcommands as arguments given on the same line as the command, subject to these rules:

There will be no @@ prompt: simply type a space between successive subcommands and between subcommand names and arguments.

SYSTAT (Cont.)

To get information about one or more specific job numbers, give the numbers only; do not type JOB.

To get information about one or more specific user names, give the names only; do not type USER. But if the user name is by coincidence the same as a SYSTAT command argument, you must use the subcommand mode to request information about his job.

To get information about one or more specific log-in directories, give the directory names.¹

To get information about your own (attached) job only, give a period (.) as argument.

To get information about all other jobs logged in under your user name, give your user name and NO . as arguments.

The system will not accept the OUTPUT subcommand in this format; use the subcommand mode instead.

Special Cases

OPERATOR as a User Name

You can request or refuse information about operator jobs by treating OPERATOR as a user name. The system accepts these commands:

@SYSTAT OPERATOR

and

@SYSTAT,
@@USER OPERATOR

as well as the special commands

@SYSTAT NO OPERATOR

and

@SYSTAT,
@@NO OPERATOR

Related Commands

INFORMATION for finding out other information about the system

¹ For specific connected directories, specify the directory names (and structures, if not the public structure) along with either the ALL or DIRECTORY subcommand.

SYSTAT (Cont.)

Examples

- Find out the status of all jobs on the system. (Your current (attached) job is marked with an asterisk (*).)

```
@SYSTAT
Fri 1-Mar-84 12:28:25 Up 33:36:17
7+2 Jobs Load av (class 0) 1.97 2.12 2.60
| Job Line Program User Origin
| 3 44 EXEC R.CRISS
| 5 56 MACRO D.SCHEIFLER AURORA(NRT)
| 8 DET NVTMP Not logged in
| 9 103 TV FORTMILLER MAX(LAT)
| 11 57 TV SCOHEN
| 14* 207 EXEC LATTA MAX(LAT)
| 20 114 TV HARDY
| 51 41 NEWRUN LATTA

7 DET PERF OPERATOR
46 3 DUMPER OPERATOR
```

- Determine how much CPU time has been charged to the jobs of two users on the system.

```
@SYSTAT,
@@TIME
@@USER KONEN
@@USER ALUSIC
@@
27 66 EXEC 0:00:01 ALUSIC
43 11 EXEC 0:00:02 KONEN
```

- Repeat Example 2 by giving the subcommands as arguments on the same line.

```
@SYSTAT TIME KONEN ALUSIC
27 66 EXEC 0:00:01 ALUSIC
43 11 EXEC 0:00:02 KONEN
```

- Find out who is using line 11.

```
@SYSTAT LINE 11
43 11 EXEC KONEN
```

- Ask for information about jobs 5 and 45.

```
@SYSTAT 5 45
5 56 MACRO D.SCHEIFLER
45 205 PTYCON OPERATOR
```

SYSTAT (Cont.)

- Set a time limit of 4 seconds for your attached job, then ask for complete information, including headings, for the job. (The period (.) specifies your attached job.) The value reported under the Limit heading is actually the sum of the time limit you set (4 seconds) and the amount of CPU time already used at the time of your SET command (2 seconds). This CPU time is reported as 2 seconds under the Time heading because you gave the SYSTAT command immediately after SET.

```
@SET TIME-LIMIT 4
```

```
@SYSTAT ALL HEADER .
```

Job	CJB	Line	Program	State	Time	Cls	Shr	Use
Limit	User,	<Directory>	Origin					
14*	51	207	EXEC	RUN	0:00:02	0	0.02	0.02
0:00:06 LATTA, MISC:<LATTA>								

- Ask for system-wide SYSTAT information only.

```
@SYSTAT SYSTEM
```

```
Fri 1-Mar-84 12:35:44 Up 33:43:36
18+15 Jobs Load av (class 0) 5.19 3.36 2.92
```

- Find out only which programs are in use.

```
@SYSTAT NO WHO NO WHERE NO SYSTEM
```

Job	Program
2	EXEC
3	EXEC
4	EXEC
5	MACRO
6	VTECO
8	NVTTMP
9	EXEC
13	OPLEAS
16	LPTSPL
26	OPR
28	BATCON

- Ask for a list of jobs controlled by job 51. (Your attached job, marked with an asterisk (*), happens to be one of these; job 51 itself is the other.)

```
@SYSTAT 51 CONTROLLING
```

14*	51	207	EXEC	LATTA
51		41	NEWRUN	LATTA

TAKE

Processes a TOPS-20 command file. TOPS-20 commands in files

Format

```
| @TAKE (COMMANDS FROM) filespec,  
| @@subcommand  
  
| where  
  
| filespec      is the specification of the file containing the  
|               commands to be processed  
|               Default file type - .CMD  
  
| @@subcommand  means that after a comma you can type one of the  
|               following subcommands:  
  
|               ALLOW      tells the current level of TOPS-20, for  
|                           the remainder of the terminal session  
|                           (not merely the current command), to  
|                           continue processing a command file if  
|                           it encounters errors  
  
|               DISALLOW  tells the current level of TOPS-20, for  
|                           the remainder of the terminal session  
|                           (not merely the current command), to  
|                           ignore any remaining commands in a  
|                           command file after it encounters an  
|                           error in the file  
|                           Default  
  
|               ECHO      tells the system to print (on your  
|                           terminal or in the specified file) the  
|                           commands that it carries out while  
|                           executing the current TAKE command.  
|                           Ordinarily only the output, if any,  
|                           produced by the commands is printed.  
  
|               NO ECHO   tells the system not to print the  
|                           commands that it carries out while  
|                           executing the current TAKE command. A  
|                           final message is sent, however,  
|                           indicating whether all the commands  
|                           were executed. See also  
|                           Hints - Suppressing the Final Message,  
|                           below.  
|                           Default  
  
|               LOG-FILE filespec  
|                           tells the system to save the output  
|                           from the current TAKE command in the  
|                           specified file.
```

Output

The output from a TAKE command consists of the output for each command in the command file you specify as argument, followed by the message, End of filespec, that indicates successful execution of all the commands in this file.

TAKE (Cont.)

Characteristics

Running Programs From a Command File

If you put commands that run programs (including the PUSH command) into a command file, and these programs ask for arguments, you must be ready to type in these arguments at your terminal. Only TOPS-20 commands and command arguments can be put into a command file executed by the TAKE command.

Hints

Suppressing the Final Message

If you want to suppress the final message (of the form, End of filespec) that indicates successful execution of a command file by TAKE, give a TAKE command with no arguments as the last line of your command file.

Special Cases

Nested TAKE Commands

In the case of nested TAKE commands (those given as commands within command files), the destination for output of commands given in an inner command file will default to that specified or assumed for the output of commands given in the nearest surrounding command file.

Effect on Memory and Terminal

The TAKE command affects memory and your terminal according to the commands stored in the command file you specify as argument.

Related Commands

INFORMATION commands	(when put into a command file) for tracing the progress of TAKE
LOGIN	for logging in; reads LOGIN.CMD then COMAND.CMD, in your log-in directory.
PUSH	for obtaining a new level of TOPS-20; reads COMAND.CMD in your log-in directory.
SUBMIT	for processing command files that run programs and contain program commands as well as TOPS-20 commands; reads BATCH.CMD, then COMAND.CMD, in your log-in directory.

TAKE (Cont.)

Examples

1. Process a command file.

```
@TAKE BACKUP.CMD
End of BACKUP.CMD.1
```

2. Type a command file that reports system statistics, then give the TAKE command with this filename as argument; send the output to the line printer. Check for this listing as it is being printed.

```
@TYPE STATUS.CMD
INFORMATION DISK-USAGE
INFORMATION MONITOR-STATISTICS
INFORMATION SYSTEM-STATUS
INFORMATION MEMORY-USAGE
SYSTAT ALL
```

```
@TAKE STATUS LPT:
End of STATUS.CMD.1
@INFORMATION OUTPUT-REQUESTS /USER
```

Printer Queue:

Job	Name	Req#	Limit	User
-----	----	----	----	-----
	EXEC	507	27	LATTA

There is 1 Job in the Queue (None in Progress)

TALK

Allows you to converse with other users on your system by linking terminals.

Format

@TALK (TO) argument

where

| argument is a user name or terminal line number

Characteristics

Typing TALK Conversation

| During a TALK session, you must tell the system to regard
| your conversation as comments. Otherwise, the system
| interprets your input as attempts to give EXEC commands and
| responds with the message ?Unrecognized command. To signal
| your input as comments, begin each line with the exclamation
| point (!) or semicolon (;) comment character. Or, if your
| comment is several lines long, use the REMARK command.

Other Job Not Affected

As soon as you give a successful TALK command, both terminals begin printing both users' input as well as the system's responses to that input. Each job, however, will receive input from its own terminal only.

Ending TALK

To end a conversation link between terminals, either user can give the BREAK command.

Refused TALK

| Terminals can be set to refuse links with other terminals
| with the REFUSE LINKS or TERMINAL INHIBIT command. If you
| attempt to TALK to a user who has refused links from another
| terminal, the system rings the bells on both terminals six
| times, and then prints the message, ?Refused, Send mail to
| user instead. If the user has refused all terminal
| communication with the TERMINAL INHIBIT command, the system
| does not ring the bell on his terminal.

| If you have Wheel or Operator capabilities enabled, you can
| TALK to any user who has given the REFUSE LINKS command, but
| not the TERMINAL INHIBIT command.

TALK (Cont.)

Maximum of Four Terminals

| By using TALK commands, you can link up to four terminals at
| once. For all terminals to share the same display, each
| pair of terminals must establish a link. For example, if
| terminal A is linked to B and C, terminals B and C will
| display only A's input. B and C must establish a link to
| display each other's input.

Hints

Signaling a Linked User

Once you have established links with another user's terminal via the TALK command, you can get his attention by typing a series of CTRL/Gs. Depending on the kind of terminal he has, these will be reproduced as ringing bells or high-pitched beeps. This action can be especially useful when establishing links with the owner of a display terminal, as display terminals are silent in ordinary operation.

Special Cases

User Has More Than One Job

| If more than one job is logged in under the user name you
| specify, the system responds with a list of that user's
| terminal line numbers and the programs being run. Type your
| choice of terminal line number (if available, the one
| running the EXEC) after the TTY: prompt.

Talking to a Batch Job or PTYCON Job

When you link to a PTY (pseudo-terminal) to talk to the owner of a batch job or PTYCON job, the system informs you of this with a message, to which you must reply with a carriage return to confirm the link. To decline the link, give a CTRL/C. See also Warning, Talking to a Batch Job, below.

Warning

Talking to a Batch Job

Use caution when communicating through a PTY (pseudo-terminal) that is controlling a batch job: do not send a question mark (?) or percent sign (%), because these characters can be attributed to errors occurring within the job. Also, if an error actually does occur in the batch job and the batch system's question mark is displaced (by your remarks) from the beginning of a line, the system may not recognize it as an error.

TALK (Cont.)

Talking Between a VT100 and a VT52

If links between VT100 and VT52 terminals are established using a TALK (or ADVISE) command, the VT52 may function improperly during or after the linked interval (e.g., by requiring frequent CTRL/Q commands to print multiple lines of output). Turning the terminal off and then on again (after the linked interval) will correct this problem.

Related Commands

ADVISE	for sending commands to another user's job
BREAK	for ending communications links involving your terminal
RECEIVE LINKS	for allowing other users to talk to you
REFUSE LINKS	for preventing other users from talking to you
REMARK	for telling the system to regard your terminal input as comment only
SEND	for sending a message to another user's terminal
TERMINAL INHIBIT	for refusing all types of terminal communication including advice, links, system messages, user messages, and notices of new mail.

Examples

1. Give the TALK command to establish links to another user.

@TALK H.DAVIES

LINK FROM LATTA, TTY 230

2. Try to talk to a user who has given the REFUSE LINKS command, then use the MAIL program to send your message.

@TALK GEBHARDT

?Refused, use "MAIL" to send mail to user

@MAIL

To: GEBHARDT

CC: LATTA

Subject: HUNCH

.
.
.

TALK (Cont.)

3. Talk to another user, giving the REMARK command immediately after TALK. (The other user's reply must still be preceded by semicolons (;) or exclamation marks (!).) Give a CTRL/Z to end REMARK before typing the BREAK command to end the conversation.

@TALK CARNAVON

LINK FROM LATTA, TTY 230

@REMARK

Type remark. End with CTRL/Z.

WHERE DO I PUT "REQMD" RECORDS AFTER EXTRACTING THE ID'S?

@;in <accts>deft-77.cbl

@;you should have group access there...

THANKS

*Z

@BREAK

4. Give the TALK command to establish links to a user who has 3 jobs on three different terminals; choose one of the terminals running the TOPS-20 command processor.

@TALK MCKAY

TTY19, DUMPER

TTY26, EXEC

TTY27, EXEC

TTY: 27

LINK FROM LATTA, TTY 230

TDIRECTORY

The TDIRECTORY (Time-ordered DIRECTORY) command is equivalent to the DIRECTORY command with the subcommands CHRONOLOGICAL WRITE, REVERSE, and TIMES (AND DATES OF) WRITE. Use the same format and subcommands with TDIRECTORY as with DIRECTORY. For further information, see the DIRECTORY command description in this manual.

When used with magnetic tapes, the TDIRECTORY command is equivalent to DIRECTORY for magnetic tapes.

Examples

1. Give a TDIRECTORY command, cancel the command with a CTRL/C after the first few (most recent) files are displayed.

@TDIRECTORY

Write

```
MISC:<LATTA>
TBATCH.CMD.1  10-May-79 13:11:57
B.DIRECTORY.1  9-May-79 12:54:00
A.DIRECTORY.1  2-May-79 13:14:52
T.CMD.1 ^C
```

2. Access another user's directory, and request a time-ordered directory listing of all his files of a certain name.

@ACCESS <DEVRIES>

Password: _____

@TDIRECTORY <DEVRIES>SYSTEM.*

Write

```
MISC:<DEVRIES>
SYSTEM.MEM.1  19-May-79 09:03:48
.TXT.1        19-May-79 09:02:08
.RNO.1        19-May-79 09:02:00
```

Total of 3 files

@END-ACCESS <DEVRIES>

TERMINAL

Sets the characteristics of your terminal.

Format

| @TERMINAL (FEATURE or TYPE) argument

where

argument is a keyword, chosen from the list below, representing your choice of TERMINAL command options; some arguments further require a decimal number to complete their meaning.

Summary of TERMINAL Command Arguments (defaults in boldface)

| The TERMINAL command arguments are divided into two categories,
| feature and type. Feature arguments set individual terminal
| characteristics and type arguments set a group of characteristics that
| are defined for the model of your terminal.

| Feature Arguments

FLAG
FORMFEED
FULLDUPLEX
HALFDUPLEX
HELP
IMMEDIATE
INDICATE
INHIBIT
LENGTH n Default n - 66
LINE-HALFDUPLEX
LOWERCASE
NO [FLAG
FORMFEED
IMMEDIATE
INDICATE
INHIBIT
LOWERCASE
PAGE
PAUSE [CHARACTER x y
COMMAND
END-OF-PAGE
RAISE
RECEIVE
TABS

TERMINAL (Cont.)

PAGE
PAUSE
RAISE
RECEIVE
SPEED
TABS
TYPE 0-36
WIDTH n Default n - 72

	50
	75
	110
	134
	150
	200
	300
	600
	1200
	1800
	2400
	4800
	9600

Type Arguments

33
35
37
EXECUPORT
LA120
LA30
LA36
LA38
SYSTEM-DEFAULT
TERMINET
TI
VK100
VT05
VT100
VT102
VT125
VT200-SERIES
VT50
VT52

TERMINAL (Cont.)

Feature Arguments

FLAG	instructs the system to print a single quotation mark (') before it prints an uppercase character. This takes effect only if you set the NO LOWERCASE parameter.
FORMFEED	informs the system that your terminal has a form feed mechanism; otherwise, the system simulates form feeds by printing the correct number of line feeds (set by the TERMINAL LENGTH command) if you have set TERMINAL NO INDICATE, or by printing an ^L if you have set TERMINAL INDICATE.
FULLDUPLEX	instructs the system to send to your terminal each character as the program reads it. Your terminal does not print what you type until the system sends the character back to the terminal. See also IMMEDIATE. Default
HALFDUPLEX	inhibits the system from sending to your terminal each character, and assumes that your terminal prints each character itself; causes echoing of format control characters (for example, TAB and line feed). Be sure also to set any corresponding switch physically located on your terminal.
HELP	prints information about the TERMINAL command.
IMMEDIATE	instructs the system to echo each character as soon as you type it, instead of waiting until the program receives the character. Immediate echoing has effect only when the FULLDUPLEX parameter is also set.
INDICATE	instructs the system to print a ^L instead of advancing the proper number of lines whenever encountering a form feed or CTRL/L (ASCII character 14). Default
INHIBIT	notifies the system that you are not willing to receive links, advice, system messages, and user messages. Also stops beep or bell signals from users attempting to TALK to your terminal. Only output from your own job is displayed on your terminal. This command disables the settings established with the RECEIVE and REFUSE commands. Reestablish the RECEIVE and REFUSE settings with NO INHIBIT.

TERMINAL (Cont.)

LENGTH n	sets the number of lines printed on each page. (If you have TERMINAL PAUSE END-OF-PAGE set as well, the system stops after printing n lines and continues only when you type CTRL/Q.) If you set the page length to 0, the system stops printing only when you type CTRL/S (as long as TERMINAL PAUSE COMMAND is in effect also); it does not automatically stop at the end of a page. Default n - 66
LINE-HALFDUPLEX	inhibits the system from sending to your terminal each character, and assumes that your terminal prints each character itself; does not cause echoing of format control characters (for example, TAB and line feed).
LOWERCASE	tells the system that your terminal handles lowercase output characters properly, by printing either the lowercase character or the corresponding uppercase character. When NO LOWERCASE is set, the system converts lowercase output characters to the appropriate uppercase characters before sending them. See also the FLAG and RAISE parameters. Default
NO argument	reverses any of the arguments FLAG, FORMFEED, IMMEDIATE, INDICATE, INHIBIT, LOWERCASE, PAGE, PAUSE, RAISE, RECEIVE, and TABS Defaults - NO FLAG, NO FORMFEED, NO IMMEDIATE, NO INHIBIT, NO PAUSE END-OF-PAGE, NO TABS
PAGE n	instructs the system to stop printing when it reaches the end of a page, or when you type a CTRL/S. Continue the output by typing a CTRL/Q. To set the page length, give the number n or give a TERMINAL LENGTH command. If you set the page length to 0, the system stops printing only when you type a CTRL/S. Default n - argument of any TERMINAL LENGTH command given in the current terminal session, or the default page length for your terminal type
PAUSE [CHARACTER x y END-OF-PAGE COMMAND	instructs the system to stop sending output whenever it has sent a full page (END-OF-PAGE), or whenever you type CTRL/S (COMMAND) or x (CHARACTER). For argument END-OF-PAGE to stop your output, argument COMMAND must also be in effect. You continue the output by typing CTRL/Q or the y parameter of the CHARACTER argument.

TERMINAL (Cont.)

For argument CHARACTER to stop your output, the COMMAND and END-OF-PAGE arguments must be in effect. With the CHARACTER argument, you continue output by typing the y parameter. You can specify x and y in various ways: as the octal ASCII code for any character or control key; as any printing character in double quotes (" "); as the word "control" followed by the printing representation of a control character in double quotation marks (for example, CONTROL "A"); and as the word "space" to specify the space bar. If you specify x and y to be the same, or if you omit y, you get a toggle effect. You can specify CTRL/S and CTRL/Q as x and y parameters, respectively, only on local terminals. (Network terminal connections do not allow for CTRL/S and CTRL/Q.) But even some local terminals require that you select characters other than CTRL/S and CTRL/Q, for example, the VT125 and the VT100 with the printer port option.

The default values for x and y are CTRL/S and CTRL/Q for local terminals, and CTRL/A/CTRL/A for network terminals. You can achieve consistency between local and network terminals by placing the same TERMINAL PAUSE CHARACTER command in your LOGIN.CMD files on the various TOPS-20 systems.

To set the page length, use the TERMINAL LENGTH command. If you set the page length to 0, the system stops sending output only when you type CTRL/S or the x parameter of the CHARACTER argument.

Default - COMMAND	(for all terminal types)
- END-OF-PAGE	(for display terminals, for example, VT05, VT50, VT52, VT100)
- CHARACTER	(for all terminal types)

RAISE

instructs the system to interpret all lowercase terminal input as the corresponding upper characters. (This setting converts the tilde (~) and right brace {) to the <ESC> key.)

Default

RECEIVE

same as the RECEIVE command. NO RECEIVE is the same as the REFUSE command.

TERMINAL (Cont.)

SPEED n1 n2 sets the baud rate at which the TOPS-20 monitor receives characters from your terminal (n1) and sends characters to your terminal (n2). Be sure also to set any corresponding switch physically located on your terminal.
Default n1 - 300
n2 - n1

TABS informs the system that your terminal has mechanical tab stops. Causes the TAB key to advance the cursor according to the tab stops on your terminal. (Some terminals let you select tab stops while others have tab stops every eight spaces). If NO TABS is set, the system simulates a tab by printing eight spaces.

TYPE n instructs the system to treat your terminal as terminal type n, in accordance with the table below:

Terminal Type	Characteristics
0	Model 33
1	Model 35
2	Model 37
3	EXECUPORT and TI
4-7	reserved for customer use
8	TERMINET
9	IDEAL (has a TAB and FORMFEED mechanism, prints lower case, has infinite line width and infinite page length)
10	VT05
11	VT50
12	LA30
13	VT52, except for not having tabs, and having a page length of 30; used for a Digital Equipment Corporation GT40.
14	LA36
15	VT52
16	VT100
17	LA38
18	LA120
19-34	reserved for customer use
35	VT125
36	VK100
Default - 8	

WIDTH n tells the system the width, in number of characters, of your terminal line. When the system prints a line longer than your terminal width, it prints the first n positions and advances a line to print the rest.
Default width - 72

TERMINAL (Cont.)

Type Arguments

- 33 informs the system that your terminal is a Teletype Model 33, which
- does not have a form feed or tab mechanism
 - prints lowercase letters as uppercase
 - needs extra time to print tabs and certain paper-moving characters (form feed and vertical tab)
 - has a line width of 72
 - has a page length of 66
- 35 informs the system that your terminal is a Teletype Model 35, which has the same characteristics as a Model 33, except that it has a form feed and tab mechanism.
- 37 informs the system that your terminal is a Teletype Model 37, which has the same characteristics as a Model 33, except that it prints lowercase letters.
- EXECUPORT informs the system that your terminal is an EXECUPORT, which
- does not have a form feed or tab mechanism
 - prints lowercase letters
 - needs extra time to perform a carriage return
 - has a line width of 80
 - has a page length of 66
- H19 informs the system that your terminal is a Heath Kit H19 terminal. The system assumes the same characteristics as for the VT52.

TERMINAL (Cont.)

LA30 informs the system that your terminal is a Digital Equipment Corporation LA30, which

- does not have a form feed or tab mechanism
- prints lowercase letters as uppercase
- needs extra time to perform a carriage return, line feed, tab, and form feed
- has a line width of 80
- has a page length of 66

LA36 informs the system that your terminal is a Digital Equipment Corporation LA36, which

- does not have a form feed or tab mechanism
- prints lowercase letters
- has a line width of 132
- has a page length of 66

LA38 informs the system that your terminal is a Digital Equipment Corporation LA38, which

- does not have a form-feed mechanism
- prints lowercase letters
- has a line width of 132
- has a page length of 66

LA120 informs the system that your terminal is a Digital Equipment Corporation LA120, which

- prints lowercase letters
- has a line width of 132
- has a page length of 66

TERMINAL (Cont.)

SYSTEM-DEFAULT informs the system that your terminal has these characteristics (ensuring an acceptable minimum level of performance for all terminal types):

- does not have a form feed or tab mechanism
- prints lowercase letters
- needs extra time to perform a carriage return, line feed, tab, and form feed
- has a line width of 72
- has a page length of 66

Default for terminal type

TERMINET informs the system that your terminal is a TERMINET, which

- does not have a form feed or tab mechanism
- prints lowercase letters
- needs extra time to perform a carriage return, line feed, tab, and form feed
- has a line width of 72
- has a page length of 66

TI informs the system that your terminal is a Texas Instruments terminal, which has the same characteristics as an EXECUPORT.

VK100 informs the system that your terminal is a Digital Equipment VK100 with the same characteristics as the VT52 and VT100, plus graphics capability (both black-and-white and color).

VT05 informs the system that your terminal is a Digital Equipment Corporation VT05, which

- does not have a form-feed mechanism
- has a tab mechanism
- prints lowercase letters as uppercase
- needs extra time to perform a linefeed or formfeed
- has a line width of 72
- has a page length of 20

TERMINAL (Cont.)

VT50	informs the system that your terminal is a Digital Equipment Corporation VT50, which does not have a form feed mechanism prints lowercase letters as uppercase has a line width of 80 has a page length of 12
VT52	informs the system that your terminal is a Digital Equipment Corporation VT52. The system assumes the same characteristics as for a VT50 except that it prints lowercase letters, and has a page length of 24 lines instead of 12.
VT100	informs the system that your terminal is a Digital Equipment Corporation VT100. The system assumes the same characteristics as for a VT52.
VT102	informs the system that your terminal is a Digital Equipment Corporation VT102. The system assumes the same characteristics as for a VT100.
VT125	informs the system that your terminal is a Digital Equipment Corporation VT125, which has full compatibility with the VT100 and the capability of business, laboratory, and scientific graphics in black-and-white or color.
VT200-SERIES	informs the system that your terminal is a Digital Equipment Corporation VT220, VT240, or VT241. The system assumes the same characteristics as a VT100.

Characteristics

TERMINAL Commands Before Log-in

You can use TERMINAL commands, after an initial CTRL/C or RETURN but before logging in, to adjust your terminal's characteristics.

Hints

Setting Your Terminal's Speed

If the initial speed setting of your terminal line is not what you want but your terminal will function at that speed, you can give a TERMINAL SPEED command even before log-in to set the proper value. If your terminal will not work at the initial speed, ask the operator to set an appropriate value.

TERMINAL (Cont.)

Using Split Speeds

If you have a terminal that allows split speeds, you can set the input and output speeds to different values. This will allow you to take advantage of fast system response, for example, without providing a needlessly fast input line. A setting of 150 2400 will accomplish this. Note that you cannot use split speeds on a terminal that is part of a DECSYSTEM-2020 system. Note also that using split speeds on VT100, VT125, or VK100 terminals may cause the "smooth scrolling" feature to function improperly. Refer to the appropriate terminal manual, for example, the VT100 User's Guide, for details.

Special Cases

Terminal Types and Defaults Peculiar to Your System

The preceding pages describe terminal types and system defaults as they are shipped with TOPS-20. However, by making changes to the monitor and the TOPS-20 command processor, your installation can add different terminal types and change the default characteristics associated with terminals. Check with your system manager to find out what changes, if any, are in effect for your system.

Terminal Speed Retained from Last Session

Although most terminal characteristics revert to default settings when you log in, the terminal line will retain the value for speed set by the last user of the line, even if he was using a different kind of terminal. However, if the system failed and was restarted after the terminal line was last used, the initial speed will be determined by the appropriate `TERMINAL SPEED` command in the system configuration file. Also, dial-up lines return to the speed specified in this file after every use.

Restrictions

CTRL/S and CTRL/Q Not Passed to Remote Nodes

CTRL/S and CTRL/Q are always processed by your host node; they are not sent to a remote node. Therefore, when you are connected to a remote node with the `SETHOST` program and `TERMINAL PAUSE (ON) END-OF-PAGE` is set on the remote node, CTRL/Q will not continue scrolling. CTRL/A is the default control character recognized by the remote node for pausing and continuing scrolling. You can use the `TERMINAL PAUSE (ON) CHARACTER` command to specify the pause and continue characters of your choosing - except CTRL/S and CTRL/Q. It is recommended that you define the same pause and continue scrolling characters on your host and the remote node.

TERMINAL (Cont.)

Disabling CTRL/S and CTRL/Q on High Speed Terminals

Some terminal models, when set to a high receive baud rate, such as 9600, require that the CTRL/S and CTRL/Q pause and continue characters be enabled in order to correctly format terminal output. If you must disable CTRL/S and CTRL/Q with the `TERMINAL NO PAUSE COMMAND`, manually set the terminal to fast or "jump" scroll. If the output is still not correctly formatted, set a slower receive baud rate with the `TERMINAL SPEED` command. Then, manually set the same baud rate on the terminal.

Warning

Setting an Improper Terminal Speed

If you set an incorrect speed for your terminal, for example, one that is too high, you will be unable to use it further. A `TERMINAL SPEED` command in the `LOGIN.CMD` file in your log-in directory can cause the same problem. In such a case, obtain your terminal line number if possible (the second column of `SYSTAT` command output consists of line numbers) and ask the operator to set an appropriate value.

Related Commands

<code>INFORMATION</code>	<code>TERMINAL-MODE</code>	for examining your current terminal settings
--------------------------	----------------------------	--

Examples

1. Declare that your terminal is an VT100.
`@TERMINAL VT100`
2. Do the same thing, using the corresponding numerical type.
`@TERMINAL TYPE 16`
3. Prepare your LA36 terminal for you to type in some upper- and lowercase text files on narrow paper.
`@TERMINAL LA36
@TERMINAL NO RAISE
@terminal width 72`

TERMINAL (Cont.)

4. Find out your terminal's characteristics, then give the command that causes it to print a full page of blank lines when you type a CTRL/L (or when it encounters an ^L in a file it is printing on your terminal).

@INFORMATION TERMINAL-MODE

TERMINAL LA36

TERMINAL SPEED 300

TERMINAL NO INHIBIT (NON-JOB OUTPUT)

RECEIVE LINKS

REFUSE ADVICE

RECEIVE SYSTEM-MESSAGES

RECEIVE USER-MESSAGES

TERMINAL PAUSE (ON) COMMAND

TERMINAL NO PAUSE (ON) END-OF-PAGE

TERMINAL LENGTH 66

TERMINAL WIDTH 132

TERMINAL LOWERCASE

TERMINAL RAISE

TERMINAL NO FLAG

TERMINAL INDICATE

TERMINAL NO FORMFEED

TERMINAL NO TABS

TERMINAL NO IMMEDIATE

TERMINAL FULLDUPLEX

@TERMINAL NO INDICATE

TRANSLATE

Displays the project-programmer number corresponding to a directory name, or the directory name corresponding to a project-programmer number.

Format

@TRANSLATE (DIRECTORY) dev:<directory>

or

@TRANSLATE (DIRECTORY) dev:[project-programmer number]

where

dev:<directory>

is the name of the directory,
enclosed in angle brackets,
that you want translated

Default dev: - your
connected
structure

dev:[project-programmer number]

is the project-programmer
number, enclosed in square
brackets, that you want
translated

Default dev: - your
connected
structure

Hints

Using Project-programmer Numbers

Use project-programmer numbers instead of directory names when giving file specifications to programs written for the TOPS-10 operating system. These include the assembler MACRO; the FORTRAN, COBOL, and ALGOL compilers; the linking loader LINK; and utility programs CREF (providing cross-reference information) and FILCOM (for comparing files). If you are unsure whether a system program requires project-programmer numbers, load it into memory (using the R command), give a CTRL/C to return to TOPS-20 command level, and then examine memory with the INFORMATION MEMORY-USAGE command. If the file PA1050.EXE (the TOPS-10 compatibility package) is present in memory, then the program was originally written for TOPS-10 and may require a project-programmer number where you would ordinarily give a directory name.

TRANSLATE (Cont.)

Avoiding Project-programmer Numbers

To avoid project-programmer numbers, define a logical name (of 6 or fewer characters) as the directory in question. Then use this logical name in place of the directory when giving file specifications. The system program will accept the logical name as a device name, and will then be using the correct directory.

Related Commands

DEFINE for defining a logical name as a directory, to avoid using a project-programmer number

Examples

1. Find out the project-programmer number associated with your connected directory.

```
@TRANSLATE <LATTA>  
PS:<LATTA> (IS) PS:[4,261]
```

2. Verify that the project-programmer number reported in Example 1 does correspond to your directory on PS:.

```
@TRANSLATE PS:[4,261]  
PS:[4,261] (IS) PS:<LATTA>
```

TYPE

Displays the contents of one or more files on your terminal.

Format

```
| @TYPE (FILE) filespec,...,  
| @@subcommand
```

where

filespec is the specification of the file you want to display on your terminal

,... means that, after commas, you can give more file specifications

@@subcommand means that after a final comma you can enter the following optional subcommand:

UNFORMATTED	Disables the formatting of control characters contained in the file. Normally, the TYPE command displays the graphic equivalent for certain control characters, for example, ESCAPE as \$ and CTRL/C as ^C. The UNFORMATTED subcommand causes characters to be displayed literally, allowing graphic text (for example REGIS files) to be displayed on the terminal.
-------------	--

Output

Entire Contents of Files

In response to the TYPE command the system prints the entire contents of a file (up to the EOF (end-of-file) pointer), including blank lines and line numbers if there are any. If you specify more than one file, the filespec precedes the contents of each file.

Hints

Stopping TYPE Output

To stop the TYPE command, type two CTRL/Cs. A CTRL/O will also stop the output, but will not stop the processing of the command or the accumulation of CPU charges. Note that a pair of CTRL/Os causes the system to skip over part of the output and continue printing.

TYPE (Cont.)

Related Commands

	COPY	for copying files to any device
	EDIT	for examining specific parts of a file
	PERUSE	for editing files in read-only mode
	PRINT	for printing files on the line printer

Examples

1. Have the system print a file on your terminal.

```
@TYPE TEST.TXT  
| This is file TEST.TXT |
```


UNATTACH

Disengages another job from its terminal.

Format

@UNATTACH (USER) name (JOB #) number
PASSWORD:password

where

name is the user name of the job's owner

number is the job number
Default number - the only job, or only job
besides your current
(attached) job, logged in
under the user name you give

password is the associated password (not requested if you are
currently logged in under the same user name as the
job that you are disengaging)

Characteristics

Log-in Not Necessary

You do not have to be logged in to give the UNATTACH
command.

Hints

Freeing Hung Terminals

The UNATTACH command is useful for freeing a terminal that,
because of program or hardware errors, is no longer under
control of the user. The command UNATTACH n can be more
effective than LOGOUT n for this purpose.

Effect on Memory and Terminal

The UNATTACH command does not affect memory and leaves your own
terminal at TOPS-20 command level. The other job is left in its
current state (usually suspended) and the disengaged terminal is
left in the state before log-in.

Related Commands

ADVISE for sending commands to another job
ATTACH for joining another job to your terminal
DETACH for disengaging your own job from its terminal

UNATTACH (Cont.)

Examples

1. Disengage another user's job from its terminal.

```
@UNATTACH KANE  
Password: _____
```

2. From a terminal on which you have not yet logged in, give the UNATTACH command to disengage your only logged-in job from its terminal.

```
BOSTON (KL2871) Development system, TOPS-20 Monitor 6.1(7)  
@UNATTACH LATTA  
Password: _____
```

3. Give a SYSTAT command to find out what jobs you have running. Give the UNATTACH command for two of them (you must specify a job number for the first one so the system will know which one you mean), and check them with another SYSTAT command.

```
@SYSTAT LATTA  
28 26 EXEC LATTA  
36* 230 EXEC LATTA  
40 27 EXEC LATTA  
@UNATTACH LATTA 28  
[Attached to TTY26, confirm]  
@UNATTACH LATTA  
@SYSTAT LATTA  
28 DET EXEC LATTA  
36* 230 EXEC LATTA  
40 DET EXEC LATTA
```

UNDELETE

Restores deleted files.

Format

@UNDELETE (FILES) filespec,...

where

filespec is the specification of the file you want to restore
 Default .gen - all generations of the specified
 files

,... means that, after commas, you can give more file
 specifications

Restrictions

Erasure of Deleted Files

Ordinarily an UNDELETE command given during the same terminal session as an original deletion will recover the deleted files, unless you included the EXPUNGE subcommand to DELETE or gave a subsequent EXPUNGE command. However, if any user or a batch job logs out while connect to your directory, all deleted files are permanently erased. Also, if available disk space is low on the system, the operator or the system itself may expunge all deleted files. A system warning message is usually sent before this happens.

Special Cases

Restoring Files Deleted With CONTENTS-ONLY Subcommand.

Any files deleted by a DELETE command with a CONTENTS-ONLY subcommand are immediately expunged. You must use the RETRIEVE command to restore these to disk.

Related Commands

DELETE	for deleting files
DIRECTORY-CLASS commands, with the DELETED subcommand	For obtaining lists of deleted files
EXPUNGE	for permanently erasing deleted files
RETRIEVE	for restoring off-line files to disk

UNDELETE (Cont.)

Examples

1. Undelete a file.

```
@UNDELETE TEST.FIL
TEST.FIL.1 [OK]
TEST.FIL.2 [OK]
```

2. Access another user's directory, then restore all his deleted files of type .FIL.

```
@ACCESS <CARSON>
Password:
@UNDELETE <CARSON>*.FIL
<CARSON>MEMO.FIL.1 [OK]
<CARSON>SEARCH.FIL.1 [OK]
<CARSON>TEST.FIL.1 [OK]
<CARSON>VERFY.FIL.1 [OK]
@END-ACCESS <CARSON>
```

UNKEEP

Cancels the kept status of a fork.

Format

UNKEEP (FORK) fork

where

fork is one of the following: Fork name
Fork number
Default - the current fork

Characteristics

Unkept Forks

An unkept fork is a fork that is cleared from memory when another program is loaded or when the RESET command is given. Forks are normally unkept unless kept with the KEEP or SET PROGRAM KEEP commands.

Inferior Forks

The UNKEEP command simultaneously cancels the kept status of a superior fork and its inferior forks.

Hints

More Information

The UNKEEP command is one of the TOPS-20 multiforking-class commands. For more information about multiforking, see the section named Running Multiple Programs in the TOPS-20 User's Guide.

Effect on Memory

The UNKEEP command does not immediately affect memory. It does, however, allow a fork in memory to be cleared when another program is loaded or the RESET command is given.

Related Commands

INFORMATION FORK-STATUS	for displaying the fork status
KEEP	for changing an unkept fork to a kept fork
RESET	for clearing forks from memory
CONTINUE, FORK, FREEZE, KEEP, INFORMATION FORK-STATUS, SET NAME, and SET PROGRAM	other multiforking-related commands

UNKEEP (Cont.)

Examples

1. Give the INFORMATION FORK-STATUS command to display the fork status. Then, give the UNKEEP command to cancel the kept status of the current fork and redisplay the fork status.

```
@INFORMATION FORK-STATUS
```

```
=> EDIT (1): Kept, HALT at 6254, 0:00:00.6
```

```
FILCOM (2): Kept, ^C from IO wait at 700272, 0:00:00.2
```

```
@UNKEEP
```

```
@INFORMATION FORK-STATUS
```

```
=> EDIT (1): HALT at 6254, 0:00:00.6
```

```
FILCOM (2): Kept, ^C from IO wait at 700272, 0:00:00.2
```

2. Display the fork status, and UNKEEP a noncurrent fork. Then, verify the new fork status.

```
@INFORMATION FORK-STATUS
```

```
=> EDIT (1): HALT at 6254, 0:00:00.6
```

```
FILCOM (2): Kept, ^C from IO wait at 700272, 0:00:00.2
```

```
@UNKEEP FILCOM
```

```
@INFORMATION FORK-STATUS
```

```
=> EDIT (1): HALT at 6254, 0:00:00.6
```

```
FILCOM (2): ^C from IO wait at 700272, 0:00:00.2
```

UNLOAD

| Rewinds a magnetic tape until it is returned completely to the source reel, and puts the associated tape drive offline. Use UNLOAD only for tapes mounted on drives having device names of the form MTAn:.

Format

@UNLOAD (DEVICE) dev:

where

dev: is the name of the magnetic tape drive that you want to unload

Restrictions

UNLOAD With Open Files

If you have given a CTRL/C to exit from a program that has opened a magnetic tape drive and you then gave the UNLOAD command for that tape drive, the system will first ask if you want to close the associated file. You must do so for UNLOAD to succeed, but you will probably be unable to continue the program from that point because the file will now be closed.

UNLOAD Not for MOUNTed Drives

| Use the UNLOAD command for tape drives obtained with the ASSIGN command. Use DISMOUNT for a tape drive obtained with MOUNT.

Warning

Cannot Access Tape Again

The UNLOAD command makes it impossible to access your tape again unless it is reloaded by the operator.

Related Commands

| ASSIGN for assigning a tape drive to your job

DISMOUNT for unloading tapes mounted on devices of the form MTn:

REWIND for rewinding a magnetic tape volume or tape set to its load point (logical beginning)

UNLOAD (Cont.)

Examples

1. Unload your magnetic tape from drive MTA0:.

@UNLOAD MTA0:

VDIRECTORY

The VDIRECTORY (Verbose DIRECTORY) command is equivalent to the DIRECTORY command with the subcommands LENGTH, NO HEADING, PROTECTION, SIZE, and TIMES (AND DATES OF) WRITE. Use the same format and subcommands with VDIRECTORY as with DIRECTORY. For further information see the DIRECTORY command description in this manual.

When used with magnetic tapes, the VDIRECTORY command is equivalent to the DIRECTORY command for magnetic tapes.

Examples

1. Give the VDIRECTORY command, then cut off the output with a CTRL/C.

@VDIRECTORY

```

MISC:<LATTA>
4-UPED.TXT.14;P777700      0 0(7)          25-Apr-85 09:58:21
A.DIRECTORY.1;P20200       1 0(0)          2-May-85 13:14:52
ARTIFI.CTL.7;P777700       1 215(7)        24-Apr-85 10:10:10
B.DIRECTORY.1;P20200       1 0(0)          9-May-85 12:54:00
C.EXE.1;P777700           3 1536(36)       13-Apr-85 04:27:59
CONFAB.CTL.1;P777700       1 115(7)        3-May-85 13:34:37
DIVIDE.FOR.4;P777700       1 260(7)        8-Mar-85 15:47:41
DUMPER.MAC.1;P777700      53 134442(7)      8-Nov-85 10:47:04
MAGNIF.CTL.2;P777700      1^C

```

2. Ask for a VDIRECTORY listing of certain files; include a line of headings.

@VDIRECTORY TEST.FOR,
@@HEADING
 @@

```

                                PGS Bytes(SZ)      Write
MISC:<LATTA>
TESTF1.FOR.8;P777700       1 115(7)          25-Apr-85 09:44:50
TESTF2.FOR.1;P777700       1 115(7)          20-Apr-85 10:01:56
TESTF3.FOR.1;P777700       1 115(7)          20-Apr-85 10:02:19

```

Total of 3 pages in 3 file

APPENDIX A

FUNCTIONAL GROUPING OF TOPS-20 COMMANDS

This appendix lists and briefly explains all non-privileged commands in the TOPS-20 command language, grouping them in categories of similar use.

A.1 SYSTEM ACCESS COMMANDS

These commands allow you to gain and relinquish access to the system, to activate and deactivate any special capabilities you have been given, and to disengage and engage jobs to your terminal.

ATTACH	Engages a designated job to your terminal.
DETACH	Disengages your current job from your terminal.
DISABLE	Deactivates any special capabilities you have been granted.
ENABLE	Activates any special capabilities you have been granted.
LOGIN	Gains access to the TOPS-20 system.
LOGOUT	Relinquishes access to the TOPS-20 system.
UNATTACH	Disengages another job from its terminal.

A.2 FILE SYSTEM COMMANDS

The file system commands allow you to create, examine, change, and delete files.

ACCESS	Obtains ownership rights to the specified directory, as well as the group rights of the directory's owner.
APPEND	Adds contents of one or more files to another file.
ARCHIVE	Makes a permanent off-line copy of files.
BUILD	Creates, modifies, or deletes a subdirectory.
CLOSE	Closes files left open by a program, and releases unopened JFNs.

FUNCTIONAL GROUPING OF TOPS-20 COMMANDS

CONNECT	Connects you to the specified directory.
COPY	Duplicates files.
CREATE	Invokes your defined editor to create a file.
DEFINE	Associates a logical name with one or more filespecs.
DELETE	Marks files for eventual erasure (disk files only), or erases the files (all other devices).
DIRECTORY	Gives information about the files in a directory.
DISCARD	Gives up the tape copy of specified on-line files.
EDIT	Invokes your defined editor to modify a file.
END-ACCESS	Relinquishes ownership rights to the specified directory.
EXPUNGE	Permanently erases any deleted files.
FDIRECTORY	Lists all the information about files.
PERUSE	Edits files in read-only mode.
RENAME	Changes one or more parts of an existing file specification.
RETRIEVE	Restores off-line files to disk.
TDIRECTORY	Lists the names and write dates of files in the order of the date and time they were last changed.
TYPE	Prints files on your terminal.
UNDELETE	Restores files marked for erasure.
VDIRECTORY	Lists the names of files, as well as their protection, size, and the date and time they were last changed.

A.3 DEVICE-HANDLING COMMANDS

These commands allow you to reserve a device prior to using it, to manipulate the device, and to release it once it is no longer needed.

ASSIGN	Reserves a device for use by your job.
BACKSPACE	Moves a magnetic tape backward.
DEASSIGN	Releases a previously assigned device.
DISMOUNT	Gives up access to the specified structure or tape set.
EOF	Writes an end-of-file mark on a magnetic tape.
MOUNT	Requests use of the specified structure or tape set.

FUNCTIONAL GROUPING OF TOPS-20 COMMANDS

REWIND	Moves a magnetic tape backward to its load point.
SKIP	Moves a magnetic tape forward.
UNLOAD	Rewinds a magnetic tape until the tape is wound completely on the source reel.

A.4 PROGRAM CONTROL COMMANDS

The following commands help you run and debug your own programs.

COMPILE	Translates a source program using the appropriate compiler.
CONTINUE	Resumes execution of a program (e.g., one interrupted by a CTRL/C).
CREF	Runs the CREF program, which produces a cross-reference listing and automatically sends it to the line printer.
CSAVE	Saves in a compressed executable format the program currently in memory. (Usually SAVE is better for most purposes.)
DDT	Merges the loaded debugging program (or if none, DDT) with the current program and then starts the debugging program.
DEBUG	Compiles a source program, loads it with a compatible debugging program, and starts the debugging program.
DEPOSIT	Sets the contents of the specified memory location.
ERUN	Runs a system program in an ephemeral fork.
EXAMINE	Checks the contents of the specified memory location.
EXECUTE	Compiles, loads, and begins execution of a program.
FORK	Selects the current fork to which TOPS-20 commands apply.
FREEZE	Stops a running fork.
GET	Places an executable program in memory.
KEEP	Protects a fork from being cleared from memory.
LOAD	Compiles a program and loads it into memory.
MERGE	Places an executable program in memory and merges it with the current contents of memory.
POP	Finishes a level of TOPS-20 and returns control to the previous level of TOPS-20.
PUSH	Starts a new level of TOPS-20.

FUNCTIONAL GROUPING OF TOPS-20 COMMANDS

R	Runs a system program.
REENTER	Starts the program currently in memory at the alternate entry point specified in the program's entry vector.
RESET	Clears memory for the specified fork of your job and its inferiors.
RUN	Places an executable program in memory and starts it.
SAVE	Copies the contents of memory into a file in executable format.
START	Begins execution of the program in memory.
UNKEEP	Cancels the kept status of a fork.

A.5 INFORMATION COMMANDS

These commands return information about TOPS-20 commands, your job, and the system as a whole.

DAYTIME	Prints the current date and time of day.
HELP	Gives an explanatory message about specific system programs.
INFORMATION	Provides information about your job and its use of available computing resources, and about the system.
SYSTAT	Gives a summary of information about current jobs on the system.
TRANSLATE	Tells you what project-programmer number is associated with a directory name, and vice versa.

A.6 TERMINAL COMMANDS

The terminal commands allow you to declare the characteristics of your terminal, to clear your video screen, and to control linking to another user's terminal.

ADVISE	Sends whatever you type on your terminal as input to a job engaged to another terminal.
BLANK	Clears your display screen and moves the cursor to line 1.
BREAK	Clears communication links.
RECEIVE	Allows your terminal to receive communication links, advice, or system messages from other users.
REFUSE	Denies links, advice, or system messages to your terminal.

FUNCTIONAL GROUPING OF TOPS-20 COMMANDS

REMARK	Notifies the system that your terminal is not sending commands but only comments.
SET	Establishes certain job-wide characteristics for your terminal session.
SET HOST	Connects the terminal to another system.
SEND	Sends messages to terminals.
TAKE	Executes commands contained in the specified file.
TALK	Links two terminals so that each user can observe what the other user is doing, without affecting his job.
TERMINAL	Informs the system of your terminal type, and lets you determine the setting of its variable parameters.

A.7 OUTPUT COMMANDS

These commands allow you to request output listings of files on the plotter, line printer, card punch, or paper tape punch, and to examine, modify, or withdraw these requests.

CANCEL	Withdraws requests from an output queue (waiting list).
INFORMATION OUTPUT-REQUESTS	Lists entries in the output queues.
MODIFY	Changes entries in an output queue.
PLOT	Places requests in a plotter output queue.
PRINT	Places requests in a line printer output queue.
PUNCH	Places requests in a card punch or paper tape punch output queue.

A.8 BATCH COMMANDS

The TOPS-20 system also has a batch system to which you can submit jobs for execution.

CANCEL BATCH	Withdraws entries from the batch input queue (waiting list).
INFORMATION BATCH-REQUESTS	Lists entries in the batch input queue.
MODIFY BATCH	Changes entries in the batch input queue.
SUBMIT	Places a batch control file in the batch input queue.

APPENDIX B

ALPHABETICAL LIST OF TOPS-20 COMMANDS

This appendix consists of an alphabetical list of TOPS-20 commands and short descriptions of each. The varieties of argument needed to complete each command are shown next, in the order that you give them; parentheses indicate that the argument is optional or can be defaulted. Last comes the effect of the command on memory - whether it clears memory (by loading a program or by other means) or otherwise alters it, or leaves it unaffected. Use this appendix along with the question mark and recognition features to refresh your memory once you have become familiar with the contents of this manual.

Command	Function	Arguments	Effect on Memory
ACCESS	gets ownership rights to a directory	dev:<directory>, password	---
ADVISE	sends commands to another user's job	user name or terminal number	---
APPEND	adds files onto end of another file	filespecs, (subcommands)	---
ARCHIVE	requests off-line storage of files	filespecs, (subcommand)	---
ASSIGN	allocates a device for your job	device name	---
ATTACH	engages a job to your terminal	user name, (job number) (password)	---
BACKSPACE	moves a magnetic tape backward	device name, number of records or files	---
BLANK	clears your video terminal screen	---	---
BREAK	ends links made by a TALK command	(user name or line number)	---
BUILD	creates, modifies, or deletes a subdirectory	dev:<directory>, subcommands	---
CANCEL	withdraws output or batch requests	queue, jobname	---

ALPHABETICAL LIST OF TOPS-20 COMMANDS

CLOSE	closes open files	JFN	---
COMPILE	translates source programs into object programs	filespecs, switches	loads compiler
CONNECT	connects your job to a directory	dev:<directory>, password	---
CONTINUE	continues a halted program	NORMALLY or STAY	---
COPY	makes copies of a file	filespec,filespec (subcommands)	---
CREATE	creates a file	(switches), filespec	loads EDIT
CREF	translates .CRF files into listings	(filespec)	loads CREF
CSAVE	stores a copy of memory in a file (in compressed format)	(filespec, memory locations)	---
DAYTIME	tells the date and time	---	---
DDT	starts a debugging program	(switches)	merges debugging program with existing memory (if necessary)
DEASSIGN	gives up a previously assigned device	device name	---
DEBUG	debugs a program	filespec, switches	loads program and debugging program
DEFINE	establishes or withdraws a logical name	logical name, search list	---
DELETE	marks files for later erasure	filespecs, (subcommands)	---
DEPOSIT	changes contents of a memory location	memory location, octal number	changes one location
DETACH	disengages a job from your terminal	(argument)	---
DIRECTORY	gives information about files	(dev:<directory>, filespecs), subcommands	---

ALPHABETICAL LIST OF TOPS-20 COMMANDS

DISABLE	deactivates capabilities	---	---
DISCARD	gives up tape copy of on-line files	filespecs	---
DISMOUNT	gives up access to structure or tape set	alias or setname, switches	---
EDIT	edits existing files	(switches), filespec	loads EDIT
ENABLE	activates capabilities	---	---
END-ACCESS	terminates ownership rights to a directory	dev:<directory>	---
EOF	writes an end-of-file mark on a magnetic tape	device name	---
ERUN	runs a system program in an ephemeral fork	name of system program (switches)	loads program
EXAMINE	inspects a memory location	memory location	---
EXECUTE	compiles, loads and starts a program	filespec, switches	loads compiler and/or program
EXPUNGE	erases all deleted files from a directory	(dev:<directory>, subcommands)	---
FDIRECTORY	DIRECTORY command with subcommands CRAM, EVERYTHING, and NO HEADING	(dev:<directory>, filespecs), subcommands	---
FORK	specifies what fork is current	fork name or number	---
FREEZE	stops a running fork	fork name or number	---
GET	places an executable program in memory	filespec, (switches)	loads program
HELP	presents a short description of a system program	name of system program	---
INFORMATION	gives information about system and job parameters	arguments	---
KEEP	protects a fork from being reset	fork name or number	---

ALPHABETICAL LIST OF TOPS-20 COMMANDS

LOAD	compiles and loads a program	filespec, switches	loads compiler and/or program
LOGIN	begins a job	user name, password, account	---
LOGOUT	ends a job	---	clears memory
MERGE	merges an executable program with current memory	filespec, (switches)	adds program to existing memory
MODIFY	changes output or batch requests	queue, jobname, switches	---
MOUNT	requests use of structure or tape set	alias or setname, switches	---
PERUSE 	edits files in read-only mode	(switches), filespec	loads editor
PLOT	plots files on plotter	filespecs, switches	---
POP	returns to superior TOPS-20 command level, ending inferior TOPS-20 command level	---	clears memory of inferior process
PRINT	prints files on line printer	filespecs, switches	---
PUNCH	punches files on card punch or paper tape punch	filespecs, switches	---
PUSH	begins an inferior TOPS-20 command level	---	preserves superior memory
R	runs a system program	name of system program, (switches)	loads program
RECEIVE	allows communication with your terminal	argument	---
REENTER	starts program in memory at the restart address	---	---
REFUSE	disallows communication with your terminal	argument	---
REMARK	informs the system that you are typing only comments, not commands	---	---

ALPHABETICAL LIST OF TOPS-20 COMMANDS

RENAME	changes the specification of a file	filespec, filespec	---
RESET 	clears the specified fork from memory	fork name or number	clears fork
RETRIEVE	restores off-line files to disk	filespecs	---
REWIND	rewinds a magnetic tape to its load point	device name	---
RUN	places an executable program in memory and starts it	filespec, (switches)	loads program
SAVE	stores a copy of memory in a file	(filespec)	---
SEND 	sends messages to terminals	line number	---
SET	sets various job parameters	arguments	---
SET HOST 	connects the terminal to another system	system name, switches	
SKIP	moves a magnetic tape forward	device name, number of records or files	---
START	starts program in memory at start address	(memory location)	---
SUBMIT	submits entries (jobs) to the batch system	filespecs, switches	---
SYSTAT	gives information about system and job status	arguments, (subcommands)	---
TAKE	starts processing of a command file	filespec, (subcommands)	---
TALK	makes communication links with another user	user name or terminal number	---
TDIRECTORY	DIRECTORY command with subcommands CHRONOLOGICAL WRITE, REVERSE, and TIMES WRITE	(dev:<directory>, filespecs), subcommands	---
TERMINAL	sets various terminal characteristics	argument	---

ALPHABETICAL LIST OF TOPS-20 COMMANDS

TRANSLATE	gives directory names for ppn's and vice versa	dev:<directory> or [project-programmer number]	---
TYPE	prints files on your terminal	filespecs	---
UNATTACH	disengages another job from its terminal	user name, (job number) (password)	---
UNDELETE	restores deleted files	filespec	---
UNKEEP 	cancels the kept status of a fork	fork name or number	---
UNLOAD	unloads a magnetic tape and deassigns the drive	device name	---
VDIRECTORY	DIRECTORY command with subcommands LENGTH, NO HEADING, PROTECTION, SIZE, and TIMES WRITE	(dev:<directory>, filespecs), subcommands	---

APPENDIX C

FILE ATTRIBUTES

This appendix lists the attributes that you can include in a file specification. The DECnet-related attributes are described in detail in the DECnet documentation. Information on file attributes is also contained in the TOPS-20 User's Guide, the TOPS-20 Monitor Calls Reference Manual, and the TOPS-20 Tape Processing Manual.

;A:account	System manager defined account string
;BDATA:user data	DECnet optional binary data
;BLOCK-LENGTH:n 	Maximum size of a physical block on a labeled tape.
;BPASSWORD:password	DECnet binary password
;CHARGE:account	DECnet account string
;DATA:user data	DECnet optional data
;EXPIRATION-DATE:date	Date the magnetic tape file can be overwritten
;FORMAT:F,D,S, or U	Magnetic labeled tape record format: F=fixed-length D=variable-length S=spanned U=undefined
;OFF-LINE	Designation for a file that is off-line because of migration or archiving
;P:n	File protection value
;PASSWORD:password	DECnet password
;POSITION:n	File sequence number for magnetic tape positioning
;RECORD-LENGTH:n 	Maximum size of a magnetic labeled tape record
;T	Designation for a file that is to be deleted at log-out time (a temporary file). Only for files in log-in and/or connected directories.
;USERID:id	DECnet user ID string

FILE ATTRIBUTES

Note that you can issue TOPS-20 commands as an alternative to specifying many of the file attributes. For example, SET FILE PROTECTION, rather than the P attribute, can be used to set the file protection. Also, such commands as INFORMATION FILE-STATUS and DIRECTORY (with the EVERYTHING subcommand) display your file attribute settings.

APPENDIX D

CONTROL CHARACTERS

This appendix lists the TOPS-20 control characters. To type a control character, use the CTRL key like the SHIFT key. Hold down the CTRL key and at the same time type the character key.

CTRL CHARACTER	FUNCTION
CTRL/C	<p>Cancels a command when typed during command entry.</p> <p>Cancels command execution when typed twice during command execution. (The first ^C does not echo.)</p> <p>Halts a program and returns to TOPS-20 command level. Generally, type two CTRL/Cs to halt a program that is executing; type one CTRL/C to stop a program that is waiting for input.</p>
CTRL/E	Ends an ADVISE command link between two terminals.
CTRL/F	Provides recognition input for file specifications and command names and arguments. Similar to the ESCAPE key, except that it completes only one field at a time with file specifications and it does not supply guidewords with commands.
CTRL/G	Rings the terminal bell. Use with SEND and TALK commands to signal another user.
CTRL/H	Reprints a command line up to the field that is in error. Type immediately after the input error message. Duplicates the function of the BACKSPACE key.
CTRL/I	Duplicates the function of the TAB key.
CTRL/L	Advances the paper on a hard-copy terminal to the top of the next page. To stop the ^L from printing, give the TERMINAL NO INDICATE command.
CTRL/O	<p>Stops output to the terminal while the program or command continues to execute.</p> <p>Output resumes when:</p> <ul style="list-style-type: none"> another CTRL/O is typed the program or command finishes the program prompts for input

CONTROL CHARACTERS

CTRL/Q	Continues scrolling terminal output that was paused by CTRL/S or a pause on an end of page. Use the TERMINAL PAUSE (ON) CHARACTER command to define alternate pause and continue characters. Use the TERMINAL NO PAUSE (ON) END-OF-PAGE command to stop pause on an end of page. Use the TERMINAL LENGTH command to set the page length.
CTRL/R	Reprints the current command line, incorporating the corrections made with the DELETE key or CTRL/W. Use on hard-copy terminals when backslashes and underscores caused by editing with DELETE and CTRL/W make the command line difficult to read. Use on video terminals when a system message covers the command line.
CTRL/S	Pauses scrolling of terminal output until CTRL/Q is typed. Input, though not displayed, is accepted into the input buffer and processed after a CTRL/Q. Use the TERMINAL PAUSE (ON) CHARACTER command to define alternate pause and continue characters.
CTRL/T	Displays a line of information that includes: the time the name and status of the current fork the amount of CPU time used the time elapsed since login the system's load average
CTRL/U	Erases the current command line. On hard-copy terminals, cancels the command and prints three Xs at the end of the command line.
CTRL/V	Allows special characters (any character other than an alphanumeric, or the special characters - _ . or \$) in file specifications and directory names. Type CTRL/V before typing the special character any time you type the file specification. Special characters are not accepted by the following system programs: ALGOL COBOL CREF FILCOM ISAM LIBRARY LINK MAKLIB RERUN
CTRL/W	Erases the previous word. On hard-copy terminals, cancels the previous word and types an underscore.
CTRL/Z	Signals an end-of-file for data entered from the terminal. Use when: COPYing from your terminal (device TTY:) to a file. Sending a message with one of the mail programs.

INDEX

-A-

ABORT subcommand, 24
 /ABORT switch, 47, 90, 148, 193
 ABSOLUTE-ARPANET-SOCKETS
 subcommand, 24
 ACCESS command, 1
 Account, 201
 setting default, 304
 setting file storage, 305
 ACCOUNT argument, 301
 ACCOUNT subcommand, 114
 /ACCOUNT switch, 242, 250, 258,
 339
 ACCOUNT-DEFAULT subcommand, 24
 ADDRESS-BREAK argument, 169, 302
 Advice
 receiving, 271
 refusing, 274
 ADVICE argument, 271, 274
 ADVISE command, 4
 /AFTER switch, 213, 242, 250, 258,
 339
 ALERT argument, 302
 Alerts
 checking, 169
 removing, 309
 setting, 309
 ALERTS argument, 169
 /ALGOL switch, 47, 90, 148, 193
 ALL subcommand, 351
 ALLOW subcommand, 358
 ALPHABETICALLY subcommand, 114
 APPEND command, 8
 ARCHIVE argument, 170
 ARCHIVE keyword, 37
 ARCHIVE subcommand, 101
 ARCHIVE-ONLINE-EXPIRED-FILES
 subcommand, 25
 Archived files
 appending to, 10
 copying, 68
 deleting, 101
 discarding, 122
 keeping disk copies of, 12
 renaming, 280
 retrieving, 285
 status of, 170
 ARCHIVED subcommand, 114
 Archiving
 on-line files for, 25
 preventing automatic, 304
 setting automatic, 304
 Arguments, Intro-1
 removing default, 310
 ARPANET
 information about, 170
 ARPANET argument, 170
 ARPANET-ACCESS subcommand, 25

ARPANET-WIZARD subcommand, 25
 ASCII subcommand, 8, 9, 64, 65
 ASSIGN command, 15
 /ASSISTANCE switch, 340
 ATTACH command, 16
 AUTOMATIC argument, 303
 AVAILABLE argument, 170

-B-

/BACKGROUND switch, 57, 334
 BACKSPACE command, 19
 /BAK switch, 72, 131
 Batch
 access rights for, 346
 account charge for, 339
 assistance during, 340
 card punch for, 340
 control file, 338
 date for job, 339
 deleting control file, 340
 dependency count
 modifying, 214
 setting, 340
 job name for, 343
 labels in control file, 342
 line number for, 340
 log destination node
 modifying, 214
 setting, 341
 log file, 340, 341, 343
 preserving control file, 342
 processing order, 219
 restarting after error, 342
 SET commands with, 321
 time-limit
 modifying, 218
 setting, 342
 Batch dependency count
 setting, 340
 Batch destination-node for, 341
 Batch jobs
 nested, 345
 submitting, 338
 talking to, 362
 BATCH keyword, 37
 BATCH-LOG switch, 340
 Batch-requests
 information about, 171
 BATCH-REQUESTS argument, 171
 BATCH.CMD file, 203, 344
 BEFORE subcommand, 114
 /BEGIN switch, 214, 244, 253, 340
 BINARY subcommand, 8, 9, 64, 65
 /BINARY switch, 47, 91, 148, 193
 BLANK command, 21
 /10-BLISS switch, 47, 90, 148,
 193

/36-BLISS switch, 47, 90, 148,
193
BREAK command, 22
BUILD command, 23
BYTE subcommand, 8, 9, 64, 65

-C-

/C128 switch, 72, 131
/C64 switch, 72, 131
CANCEL command, 37
Capabilities
 disabling, 121
 displaying assigned, 137
 enabling, 137
Card images for
 batch, 342
CARD-READER-INPUT-SET argument,
 303
Cards
 punching, 257
CARDS keyword, 37
/CARDS switch, 214, 340
Characters
 double at-sign, Intro-4
 plus sign, 51, 95
 question mark, Intro-6
/CHECK-SETNAME switch, 223, 227
CHECKSUM subcommand, 114
CHRONOLOGICAL subcommand, 114
CLASS subcommand, 351
CLOSE command, 44
CLUSTER argument, 171
.CMD
 file type, 358
COBDDT program, 85
/68-COBOL switch, 47, 90, 148,
 193
/74-COBOL switch, 47, 90, 148,
 193
/COBOL switch, 47, 91, 149, 193
COMAND.CMD file, 201, 202, 203,
 344
Command default
 setting, 304
Command files
 BATCH.CMD, 203, 344
 COMAND.CMD, 201, 202, 203, 344
 executing, 358
 LOGIN.CMD, 201, 202
 LOGOUT.CMD, 206, 207
 order of processing with LOGIN,
 202
 order of processing with SUBMIT,
 344
 running programs from, 359
 SYSTEM:BATCH.CMD, 203, 344
 SYSTEM:COMAND.CMD, 202, 203,
 344
 SYSTEM:LOGIN.CMD, 202
COMMAND-LEVEL argument, 171
Commands, Intro-1
 abbreviating, Intro-5

Commands (Cont.)
 continuing, Intro-3
 DIRECTORY-class, Intro-3
 guidewords in, Intro-5
 help with, Intro-6
 LOAD-class, Intro-3
 Queue-class, Intro-3
Commas between
 filespecs, 197
Comments
 typing on terminal, 277
Common File System, 171
Compilation
 forcing, 47, 91, 149, 194
 preventing, 49, 92, 150, 195
COMPILE command, 46
/COMPILE switch, 47, 91, 149, 194
Compiled programs
 listing, 48, 92, 194
Compiled programs preventing
 listing, 50
Compilers
 passing language-switches to,
 48, 91, 149, 194
Compiling files together, 51, 152,
 197
Compiling multiple programs, 95,
 152
COMPLETE subcommand, 114
Confidential access capabilities,
 25
CONFIDENTIAL subcommand, 25
CONNECT command, 54
Connected directory, Intro-2, 54
/CONNECTED-DIRECTORY switch, 340
CONTENTS-ONLY subcommand, 101
CONTINUE argument, 109
CONTINUE command, 57
Control characters, D-1
CONTROL-C-CAPABILITY argument,
 303
CONTROLLING subcommand, 351
/COPIES switch, 214, 244, 253,
 260
COPY command, 64
CPU time-limit
 setting, 317
CRAM subcommand, 114
CREATE command, 71
CREF command, 77
CREF program, 77
/CREF switch, 91, 149, 194
Cross-reference files, 48, 77, 91,
 149, 194
Cross-reference listing, 77
/CROSS-REFERENCE switch, 48, 91,
 149, 194
CSAVE command, 81
/CTERM switch, 326
CTRL-C
 removing capability of, 310
Current fork, 159
/CURRENT-VOLUME-ONLY switch, 289

-D-

Date
 to display, 83
Date arguments
 formats of, Intro-7
DATES subcommand, 115
DAYTIME command, 83
DDT command, 84
DDT Program
 loading, 91
DDT program
 loading, 194
/DDT switch, 91, 194
DEASSIGN command, 87
DEBUG command, 89
/DEBUG switch, 48, 91, 194
Debugging
 SET commands with, 320
 specifying debugging program,
 95
Debugging information
 excluding, 50, 91, 194
Debugging programs, 84
/DECIDE switch, 72, 131
DECnet nodes
 displaying accessible, 171
 setting, 308
DECNET NODES argument, 171
DECNET-ACCESS subcommand, 25
DEFAULT argument, 303
Default arguments, Intro-4
DEFAULT-FILE-PROTECTION
 subcommand, 25
Defaults
 displaying, 171
DEFAULTS argument, 171
DEFINE command, 98
DELETE command, 101
DELETE subcommand, 155
/DELETE switch, 214, 244, 253,
 260, 340
Deleted archived files
 recovering, 102
Deleted files
 restoring, 385
DELETED subcommand, 115
Deletion
 of archive requests, 37
 of batch requests, 37
 of files, 101, 385
 of files at logout, 206
 of logical names, 98
 of mount requests, 37
 of paper-tape requests, 37
 of plot requests, 37
 of print requests, 37
 of punch card requests, 37
 of subdirectories, 27
/DENSITY switch, 223
/DEPENDENCY-COUNT switch, 214,
 340
DEPOSIT command, 105

/DESTINATION-NODE switch, 214,
 242, 251, 259, 341
DETACH command, 109
Detaching jobs, 383
dev:, Intro-1
Device defaults, Intro-2
Devices
 assigning, 15
 changing to generic, 215
 deassigning, 87
 displaying available, 170
Directories
 deleting, 34
 displaying characteristics of,
 172
 permanent disk storage, 29
Directory
 accessing, 1
 connecting to a, 54
 connecting to log-in, 201
 defaults, Intro-2
 display contents of, 112, 158,
 391
 displaying contents of, 365
 files-only, 33
 group rights, 202
 ownership rights, 1, 202
 protection code, 29
 setting options, 298
 setting protection, 305
DIRECTORY Argument, 304
DIRECTORY argument, 172
DIRECTORY command, 112
Directory for
 batch, 340
Directory name
 corresponding
 project-programmer number,
 379
DIRECTORY subcommand, 101, 351
DIRECTORY-class commands, Intro-3
DIRECTORY-GROUP subcommand, 26
DISABLE command, 121
DISABLE subcommand, 26
DISALLOW subcommand, 358
DISCARD command, 122
Discard command
 undoing, 122
Disk storage quotas
 infinite, 32
Disk-usage
 information about, 173
DISK-USAGE argument, 173
DISMOUNT STRUCTURE command, 124
DISMOUNT TAPE command, 124
DOUBLESPEACE subcommand, 115
/DPY switch, 131
/DRIVE-TYPE switch, 223

-E-

ECHO subcommand, 358

- ^ECREATE
 - command, 31
- EDIT command, 130
- EDIT program, 71, 130
 - backup files, 72, 74, 133
 - controlling error messages, 72, 73, 131, 132
 - line numbers in, 72, 73, 131, 132
 - read-only mode, 73, 132, 238
 - SWITCH.INI file, 75, 134
- Edit program
 - backup files, 131
- EDITOR: logical name, 75, 134
- ENABLE command, 137
- ENABLE subcommand, 26
- END-ACCESS command, 139
- ENQ-DEQ subcommand, 26
- /ENTIRE-VOLUME-SET switch, 289
- Entry vector, 334
 - changing, 305
- ENTRY-VECTOR argument, 305
- EOF command, 141
- Ephemeral file, 306
- Ephemeral fork
 - characteristics of, 143
- Ephemeral program, 312
 - canceling ephemeral attribute, 269
- Erasing
 - deleted files, 385
- Error messages, Intro-9
- ERUN command, 143
- ESC key, Intro-2
- EVERYTHING subcommand, 115
- EXAMINE command, 145
- EXEC
 - creating an inferior, 30, 265
 - returning to superior, 247
- EXECUPORT argument, 372
- EXECUTE command, 147
- /EXPERT switch, 72, 131
- Expiration date
 - setting default file, 304
 - setting file, 306
- EXPUNGE command, 155
- EXPUNGE subcommand, 101

-F-

- /FAIL switch, 48, 91, 149
- /FAST switch, 206
- FDIRECTORY command, 158
- /FEET switch, 214, 341
- File
 - attributes, Intro-2, C-1
 - setting expiration date, 306
 - setting protection, 307
- FILE argument, 305
- File protection
 - setting default, 304
- File specifications, Intro-1

- File structures
 - see structures
- /FILE switch, 215, 253
- File type .CRF, 77
- File types with
 - LOAD, 197
- File types with COMPILE, 51
- FILE-STATUS argument, 174
- Files
 - See also Command files
 - appending, 8
 - archiving, 12
 - changing text type of, 215
 - closing, 44
 - compressed format, 81
 - copying, 64
 - copying from TTY:, 67
 - creating, 71
 - cross-reference, 77
 - default generation, 26
 - deleting, 101
 - displaying, 381
 - displaying status of, 174
 - editing with EDIT program, 130
 - erasing, 101, 155
 - erasing deleted, 385
 - indirect, 95
 - making ephemeral, 306
 - mapped, 44
 - offline expiration date, 28
 - online expiration date, 28
 - printing, 249
 - punching on paper tape and cards, 257
 - renaming, 279
 - replacing contents of, 281
 - restoring deleted, 385
 - retrieving offline, 284
 - SWITCH.INI, 238
 - trapping openings, 318
- FILES argument, 20, 332
- Files-only directories, 33
- FILES-ONLY subcommand, 26
- Filespecs, Intro-1
 - plus signs between, 51
- FIND subcommand, 115
- FLAG argument, 368
- /FLAG-NON-STANDARD switch, 48, 91, 149, 194
- FORGET subcommand, 101
- FORK command, 159
- FORK-STATUS argument, 174
- Forks
 - continuing, 190
 - displaying status of, 174
 - keeping, 189, 312
 - limited number of, 190
 - making current, 159
 - name and number of, 159
 - renaming, 309
 - running ephemeral, 143
 - stopping, 162
- FORMFEED argument, 368

/FORMS switch, 215, 243, 251, 259
/FORTRAN switch, 48, 91, 149, 194
FREEZE command, 162
FULLDUPLEX argument, 368

-G-

.gen, Intro-1
Generation number, Intro-2
 defaults, Intro-2
 highest, Intro-2
Generation-retention-count
 setting default, 304
GENERATION-RETENTION-COUNT
 subcommand, 115
GENERATIONS subcommand, 26
Generic device
 changing to, 215
/GENERIC switch, 215, 243, 251,
 259
GET command, 164
Group rights, 54

-H-

H19 argument, 372
HALFDUPLEX argument, 368
HEADER subcommand, 351
/HEADER switch, 215, 244, 253,
 260
Headers
 changing to no, 216
HEADING subcommand, 115
HELP argument, 368
HELP command, 166
Hyphen character
 -, Intro-3

-I-

IBM-node for
 batch, 342
IMAGE BINARY subcommand, 8, 65
IMAGE subcommand, 8, 64, 65
IMMEDIATE argument, 368
/INCREMENT switch, 72, 131
INDICATE argument, 368
Indirect files, 51, 152, 197
Inferior process, 265
INFORMATION command, 168
INHIBIT argument, 368
Interrupt sequence, 326, 328
Interrupts
 displaying, 180
Invisible files, 13, 306
INVISIBLE subcommand, 115
IPCF subcommand, 26
/ISAVE switch, 72, 131

-J-

JFNS, 44

Job
 displaying runtime, 352
 setting options, 298
Job class
 displaying, 351
Job file numbers, 44
JOB subcommand, 351
Job time limit
 displaying, 351
JOB-STATUS argument, 174
/JOBNAME switch, 38, 40, 212, 243,
 251, 259, 341
Jobs
 attaching, 16
 detaching, 109
JSYS trapping, 318

-K-

KEEP subcommand, 102
Kept fork
 characteristics, 189
Kept forks
 see Forks
Key
 escape, Intro-6
Keywords, Intro-4
KILL subcommand, 26

-L-

LA120 argument, 373
LA30 argument, 373
LA36 argument, 373
LA38 argument, 373
/LABEL-TYPE switch, 223
/LANGUAGE-SWITCHES switch, 48, 91,
 149, 194
LARGER subcommand, 115
Late-clear-typeahead
 displaying status of, 171
LATE-CLEAR-TYPEAHEAD argument,
 308
LENGTH argument, 369
LENGTH subcommand, 116
LEOT argument, 332
/LIBRARY switch, 91, 149, 194
LIMIT subcommand, 351
/LIMIT switch, 215, 243, 251, 259
LINE subcommand, 351
LINE-HALFDUPLEX argument, 369
Line-printer
 spacing
 changing, 218
Links
 breaking, 22
 receiving, 271
 refusing, 274
LINKS argument, 271, 274
LIST subcommand, 27
/LIST switch, 48, 92, 149, 194
LOAD command, 192
LOAD switches, 193

LOAD-class commands, Intro-3
 Loader maps, 91, 150
 LOCATION argument, 308
 LOG-FILE subcommand, 358
 Log-in directory, Intro-2
 /LOGDISPOSITON switch, 341
 Logical names
 defining, 98
 displaying defined, 174
 removing, 98
 LOGICAL-NAMES argument, 175
 LOGIN command, 201
 LOGIN.CMD file, 201, 202, 203
 /LOGNAME switch, 341
 LOGOUT command, 206
 LOGOUT.CMD file, 206, 207
 /LOWER switch, 72, 131
 Lowercase
 changing to, 216
 LOWERCASE argument, 369
 /LOWERCASE switch, 215, 251
 LPT subcommand, 116, 352

-M-

/M33 switch, 72
 /M37 switch, 72
 /MAC switch, 48, 149, 194
 /MACHINE-CODE switch, 48, 149, 194
 MACRO
 assembling using, 50, 149
 /MACRO switch, 48, 92, 149, 195
 Magnetic tapes
 See Tapes, 19
 Mail, 175
 notice of new, 175
 watching for new, 308
 MAIL Argument, 175
 MAIL-WATCH argument, 308
 MAINTENANCE subcommand, 27
 .MAP files, 91, 150, 195
 /MAP switch, 92, 150, 195
 Mapped files, 44
 renaming, 280
 MAXIMUM-SUBDIRECTORIES subcommand, 27
 Memory
 clearing, 282
 displaying status of, 175
 modifying, 105
 preserving state of, 189
 putting an executable program into, 164
 Memory locations
 examining, 145
 Memory sections, 84, 164, 209, 269, 291
 MEMORY-USAGE argument, 175
 MERGE command, 209
 Messages
 error, Intro-9
 sending, 295

Messages (Cont.)
 warning, Intro-9
 /METERS switch, 259
 Migrating files
 delaying, 320
 off-line, 307
 preventing, 307
 /MODE switch, 216, 244, 253, 261
 Modification
 of card requests, 211
 of paper-tape requests, 211
 of plot requests, 211
 of print requests, 211
 of queue and batch requests, 211
 of queue priority, 217
 MODIFY command, 211
 Monitor statistics
 information about, 177
 MOUNT command, 222
 Mount count, 125
 MOUNT keyword, 37
 MOUNT switches, 223
 Mount-requests
 displaying, 177
 MOUNT-REQUESTS argument, 177

-N-

NAME argument, 309
 /NEW switch, 224
 NO argument, 309, 369
 NO ECHO subcommand, 358
 NO subcommand, 116, 352
 /NOBAK switch, 72, 132
 /NOBINARY switch, 48, 195
 /NOCOMPILE switch, 49, 92, 150, 195
 /NOCREF switch, 48, 92, 150, 195
 /NOCROSS-REFERENCE switch, 49, 150, 195
 /NODEBUG switch, 49, 92, 195
 /NODECIDE switch, 73, 132
 Nodes
 displaying accessible, 171
 /NOFLAG-NON-STANDARD switch, 49, 92, 150, 195
 /NOHEADER switch, 216, 245, 254, 261
 /NOLIBRARY switch, 92, 150, 195
 /NOLIST switch, 49, 92, 150, 195
 /NOMACHINE-CODE switch, 49, 92, 150, 195
 /NONUMBER switch, 73, 132
 /NOOPTIMIZE switch, 49, 93, 150, 195
 /NORMALLY switch, 57, 334
 /NOSEARCH switch, 93, 150, 195
 /NOSEPARATORS switch, 73, 132
 /NOSTAY switch, 49, 93, 150, 195
 /NOSYMBOLS switch, 93, 196
 NOT subcommand, 27
 /NOTE switch, 216, 243, 252, 259

- /NOTIFY switch, 243, 252, 260
- /NOUNLOAD switch, 224
- /NOVICE switch, 132
- NOVICE switch, 73
- /NOWAIT switch, 124, 224
- /NOWARNINGS switch, 49, 150, 196
- /NRT switch, 327
- NUMBER subcommand, 28
- /NUMBER switch, 73, 132

-O-

- Object file
 - libraries, 91, 94, 194
- Object files, 46, 147
 - generating, 47, 193
 - libraries, 150
 - optimized, 50
 - preventing generating of, 50
- Off-line expiration date
 - setting, 307
- Off-line files
 - waiting for, 313
- OFFLINE subcommand, 116
- OFFLINE-EXPIRATION-DEFAULT subcommand, 28
- /OLD switch, 73, 132
- On-line expiration date
 - setting, 307
- ONLINE subcommand, 116
- ONLINE-EXPIRATION-DEFAULT subcommand, 28
- Open files
 - displaying status of, 314
 - renaming, 280
- OPERATOR subcommand, 28
- /OPTIMIZE switch, 49, 93, 150, 196
- Optimized
 - object files, 91
- /OPTION switch, 73, 132
- Output mode
 - changing, 216
- Output queue
 - changing, 217
- OUTPUT subcommand, 116, 352
- /OUTPUT switch, 341
- Output-requests
 - displaying, 178
- OUTPUT-REQUESTS argument, 178
- /OVERLAY switch, 84, 209

-P-

- PAGE argument, 369
- PAGE-ACCESS argument, 311, 319
- /PAGES switch, 217, 341
- Paper tape
 - changing amount of, 215
 - punching, 257
- PAPER-TAPE keyword, 37
- /PASCAL switch, 49, 93, 151, 196

- Password
 - assigning directory, 28
- PASSWORD subcommand, 28
- Passwords
 - assigning directory, 305
- PAUSE argument, 369
- PERMANENT subcommand, 29
- PERUSE command, 238
- /PLINES switch, 73, 132
- PLOT command, 241
- PLOT keyword, 37
- Plotting
 - copies for, 244
 - deleting after, 244
 - destination-node for, 242
 - forms for, 243
 - job name for, 243
 - mode for, 244
 - preventing header for, 245
 - priority for, 244
 - saving after, 245
 - sequence number for, 244
 - setting date for, 242
 - spooled-output, 246
 - starting page number for, 244
 - time limit for, 243
 - time-limit in batch job, 343
 - unit for, 244
- Plus signs between
 - filespecs, 197
- POP command, 247
- PRESERVE subcommand, 29
- /PRESERVE switch, 245, 254, 261, 342
- PRINT command, 249
- PRINT keyword, 37
- Printing
 - account charged for, 250
 - copies for, 253
 - deleting file after, 253
 - destination-node for, 250
 - forms for, 251
 - header for, 253
 - job name for, 251
 - mode for, 253
 - owner for, 252
 - page limit for, 251
 - preventing header for, 254
 - priority for, 252
 - sequence numbers for, 252
 - setting date, 250
 - spacing during, 254
 - spooled-output, 255
 - starting page number for, 253
 - text type for, 253
 - title for, 254
 - unit for, 252
- Priority for
 - batch, 342
- /PRIORITY switch, 217, 244, 252, 260, 342
- Privileges
 - see Capabilities

/PROCESSING switch, 217
 /PROCESSING-NODE switch, 342
 Program
 entry vector, 273
 PROGRAM argument, 312
 PROGRAM EPHEMERAL argument, 312
 PROGRAM KEEP argument, 312
 PROGRAM NO-EPHEMERAL argument, 313
 PROGRAM subcommand, 352
 Program-status
 displaying, 180
 PROGRAM-STATUS argument, 179
 Programs
 compiling, 46, 147, 192
 continuing, 57
 debugging, 84, 89
 displaying version of, 184
 ephemeral, 312
 executing, 147
 loading, 147, 192
 merging, 209
 monitoring, 58
 running, 269, 291
 running from command files, 359
 saving, 81, 293
 starting, 147, 334
 starting at alternate entries, 273
 PROHIBIT-MIGRATION subcommand, 116
 Project-programmer number
 corresponding directory name, 379
 Protection
 setting directory, 305
 setting file, 307
 PROTECTION subcommand, 29, 116
 /PROTECTION switch, 224
 Pseudo-terminals
 advising, 5
 PSI status
 displaying, 180
 PSI-STATUS argument, 180
 PTYs logging in to, 204
 PUNCH command, 257
 Punching
 account charged for, 258
 card limit for, 259
 copies for, 260
 deleting after, 260
 destination-node for, 259
 forms for, 259
 header for, 260
 job name for, 259
 mode for, 261
 paper tape limit for, 259
 preventing header for, 261, 262
 priority for, 260
 saving after, 261, 262
 sequence numbers for, 260
 setting date for, 258
 spooled-output, 263
 Punching (Cont.)
 unit for, 260
 PURGE subcommand, 155
 PUSH command, 265
 PUSH subcommand, 30

 -Q-
 Queue-class commands, Intro-3

 -R-
 R command, 269
 /R switch, 73, 132
 RAISE argument, 370
 /READ-ONLY switch, 225
 /READER switch, 342
 /READONLY switch, 73, 132
 REBUILD subcommand, 155
 RECEIVE argument, 370
 RECEIVE command, 271
 Recognition, Intro-5
 RECORDS argument, 19, 332
 REENTER argument, 109
 REENTER command, 273
 REFUSE command, 274
 /RELOCATABLE switch, 93, 151, 196
 REMARK command, 277
 /REMARK switch, 125, 225
 Remote node
 connecting terminal to, 326
 /REMOVE switch, 125
 RENAME command, 279
 REPEAT-LOGIN-MESSAGES subcommand, 30
 /REPORT switch, 217, 254
 Report title
 changing, 217
 RESET command, 282
 RESIST-MIGRATION subcommand, 116
 Restartable status
 changing, 217
 /RESTARTABLE switch, 217, 342
 RETAIN subcommand, 12
 Retrieval-requests
 information about, 180
 RETRIEVAL-REQUESTS argument, 180
 RETRIEVAL-WAIT argument, 313
 RETRIEVE command, 284
 RETRIEVE keyword, 37
 REVERSE subcommand, 116
 REWIND command, 289
 /RONLY switch, 73, 132
 RUN command, 291
 /RUN switch, 73, 132

 -S-
 /SAIL switch, 49, 93, 151, 196
 SAVE command, 293
 /SAVE switch, 73, 133
 Scratch
 tapes, 225

- /SCRATCH switch, 225
- Screen
 - clearing, 21
- Scrolling
 - with remote host, 328
- /SEARCH switch, 93, 151, 196
- SEND command, 295
 - in batch job, 296
- SEPARATE subcommand, 117
- /SEPARATORS switch, 73, 133
- Sequence number for
 - batch, 342
- /SEQUENCE switch, 38, 74, 133, 212, 244, 252, 260, 342
- SESSION-REMARK argument, 313
- SET command, 298
- SET HOST command, 326
- /SIMULA switch, 49, 93, 151, 196
- SINCE subcommand, 117
- SIZE subcommand, 117
- SKIP command, 332
- SMALLER subcommand, 117
- /SNOBOL switch, 49, 93, 151, 196
- Source files, 46, 147
- /SPACING switch, 218, 254
- Special arpanet queues for
 - subdirectories use of, 25
- SPEED argument, 371
- Spooled output
 - information about, 180
- SPOOLED-OUTPUT argument, 314
- /SPOOLED-OUTPUT switch, 39, 246, 255, 263
- SPOOLED-OUTPUT-ACTION argument, 180
- START argument, 109
- START command, 334
- /START switch, 74, 133, 226
- Starting programs, 334
- STATE subcommand, 352
- STATUS-WATCH argument, 314
- /STAY Switch, 50
- /STAY switch, 57, 94, 151, 196, 334
- /STEP switch, 74, 133
- Structure
 - mount count, 227
- STRUCTURE argument, 181
- /STRUCTURE-ID switch, 125, 226
- Structures
 - dismounting, 124
 - information about, 181
 - mounting, 222
 - removing, 125
 - renaming files between, 280
 - transferring files within, 279
 - unavailable for mounting, 230
- Subcommands, Intro-3
- See also individual subcommands
- Subdirectories
 - creating, 23
 - default file protection for, 25
 - deleting, 23
- Subdirectories (Cont.)
 - files-only, 26
 - modifying, 23
 - working disk storage for, 31
- Subdirectory
 - group rights, 30
 - groups, 26
- Subdirectory parameters
 - listing, 27
- SUBDIRECTORY-USER-GROUP
 - subcommand, 30
- SUBMIT command, 338
- Subsystem statistics
 - displaying, 181
- SUBSYSTEM-STATISTICS argument, 181
- SUPERIOR argument, 182
- Superior process, 247
- SUPERSEDE subcommand, 65
- SWITCH.INI file, 75, 134
- Switches, Intro-2
 - default, Intro-3
 - positioning, Intro-3
- Symbol table, 94
 - rebuilding, 155
- /SYMBOLS switch, 94, 196
- SYSTAT command, 350
- System mail
 - reading, 175
- System messages
 - receiving, 271
 - refusing, 274
- SYSTEM MESSAGES argument, 274
- System status, 350
 - displaying, 182
- SYSTEM subcommand, 352
- SYSTEM-DEFAULT argument, 374
- SYSTEM-MESSAGES argument, 271
- SYSTEM-STATUS argument, 182

-T-

- TABS argument, 371
- /TAG switch, 342
- TAKE command, 358
- TALK command, 361
- Tape
 - density, 223
 - drives, 223
 - labels, 223
 - protection, 224
 - setnames, 227
- TAPE argument, 316
- Tape drives
 - assigning, 15
- Tape sets
 - unloading, 126
- Tape-parameters
 - displaying, 183
- TAPE-PARAMETERS argument, 183
- Tapes
 - assigning tape drives, 15
 - backspacing, 19

Tapes (Cont.)
 creating new file set, 224
 dismounting, 124
 forwarding, 332
 load point, 289
 mounting, 222
 rewind with open files, 289
 rewinding, 289, 389
 setting density, 316
 setting format, 317
 setting parity, 317
 setting record-length, 317
 single volume tape sets, 230
 skipping records and files, 332
 unloading, 389
 volume identifier, 226
 write-enabled mode, 226
 writing end-of-file on, 141
 TDIRECTORY command, 365
 Terminal
 connecting to remote node, 326
 displaying characteristics of, 183
 freeing hung, 383
 linking to another, 361
 setting options, 298
 setting speed of, 376
 talking to another, 361
 to modify characteristics for, 371
 TERMINAL command, 366
 Terminal lines
 displaying available, 170
 TERMINAL-MODE argument, 183
 TERMINET argument, 374
 TI argument, 374
 TIME
 to display, 83
 Time
 entering in commands, Intro-7
 Time arguments
 formats of, Intro-7
 relative time, Intro-8
 Time limit
 removing CPU, 311
 setting batch, 342
 setting CPU, 317
 TIME subcommand, 352
 /TIME switch, 218, 342
 TIME-LIMIT argument, 317, 320
 TIMES subcommand, 117
 Timesharing jobs
 ending, 206
 starting, 201
 TOPS10-PROJECT-PROGRAMMER
 subcommand, 30
 /TPLOT switch, 218
 TRANSLATE command, 379
 TRAP argument, 318
 Trapping
 continuing after, 318
 disabling, 311, 318
 setting, 318
 .typ, Intro-1
 TYPE argument, 371
 TYPE command, 381
 TYPEOUT argument, 319
 -U-
 UDDT program, 84
 UNATTACH command, 383
 UNDELETE command, 385
 /UNIQUE switch, 218
 /UNIT switch, 218, 244, 252, 260
 UNKEEP command, 387
 Unkept fork, 387
 UNLOAD command, 389
 /UNSEQUENCE switch, 74, 133
 /UPPER switch, 74, 133
 /UPPERCASE switch, 218, 252
 /USE-SECTION switch, 84, 164, 209, 269, 291
 User messages
 receiving, 271
 refusing, 274, 295
 sending, 295
 User name, 201
 USER subcommand, 117, 352
 /USER switch, 39, 218, 252, 260
 USER-MESSAGES argument, 271, 274
 USER-OF-GROUP subcommand, 30
 UUO simulation
 disabling, 311
 UUO-SIMULATION argument, 319
 -V-
 VDIRECTORY command, 391
 VERSION argument, 184
 Visible files, 13, 308
 VK100 argument, 374
 Valid, 227
 /VOLIDS switch, 226
 Volume identifier, 227
 Volumes
 information about, 185
 VOLUMES argument, 185
 VT05 argument, 374
 VT100 argument, 375
 VT102 argument, 375
 VT125 argument, 375
 VT200-SERIES argument, 375
 VT50 argument, 375
 VT52 argument, 375
 -W-
 /WARNINGS switch, 94, 196
 WHAT subcommand, 352
 WHEEL subcommand, 31
 WHERE subcommand, 353
 WHO subcommand, 353
 WIDTH argument, 371
 /WINDOW switch, 74, 133
 WORKING subcommand, 31

/WRITE-ENABLED switch, 226

-X-

XDDT program, 84

READER'S COMMENTS

NOTE: This form is for document comments only. DIGITAL will use comments submitted on this form at the company's discretion. If you require a written reply and are eligible to receive one under Software Performance Report (SPR) service, submit your comments on an SPR form.

Did you find this manual understandable, usable, and well-organized? Please make suggestions for improvement.

Did you find errors in this manual? If so, specify the error and the page number.

Please indicate the type of reader that you most nearly represent.

- ☐ Assembly language programmer
- ☐ Higher-level language programmer
- ☐ Occasional programmer (experienced)
- ☐ User with little programming experience
- ☐ Student programmer
- ☐ Other (please specify) _____

Name _____ Date _____

Organization _____ Telephone _____

Street _____

City _____ State _____ Zip Code _____
or Country

-----Do Not Tear - Fold Here and Tape-----

digital



No Postage
Necessary
if Mailed in the
United States


BUSINESS REPLY MAIL

FIRST CLASS PERMIT NO. 33 MAYNARD MASS.

POSTAGE WILL BE PAID BY ADDRESSEE

SOFTWARE PUBLICATIONS

200 FOREST STREET MRO1-2/L12
MARLBOROUGH, MA 01752



-----Do Not Tear - Fold Here and Tape-----

Cut Along Dotted Line