

3-	1	WINCHR	-- Process next output character
4-	1	REGCHR	-- Process regular characters
5-	1	DOCTRL	-- Process control characters
6-	1	WCSCHK	-- Check for start of control sequence
7-	1	WCPESC	-- Escape processing
8-	1	EPCH1	-- Accrue a terminal control sequence
10-	1	ACRCS	-- Store a character into control seq buffer
11-	1	CSFIN	-- Process received control sequence
13-	1	CSPARM	-- Extract parameter value from control string
14-	1	TCBS	-- Process backspace character
15-	1	TCHT	-- Process horizontal tab character
16-	1	TCCR	-- Process carriage return
17-	1	TCUP	-- Move cursor up specified number of lines
18-	1	TCDOWN	-- Move cursor down specified number of lines
19-	1	TCLF	-- Process Line Feed character
20-	1	TCESCE	-- Move to 1st column of next line
21-	1	TCIXUP	-- Index up one line
22-	1	TCRIT	-- Move cursor right specified number of chars
23-	1	TCLEFT	-- Move cursor left specified number of chars
24-	1	TCCADR	-- Do direct cursor addressing
25-	1	TCCPSV	-- Save current cursor position
25-	23	TCCPRS	-- Restore cursor position
26-	1	TCINSL	-- Insert lines
27-	1	TCDELL	-- Delete specified number of lines
28-	1	TCGOAS	-- Designate G0 as ascii character set
28-	11	TCGODS	-- Designate G0 as DEC supplemental character set
28-	21	TCGOUK	-- Designate G0 as UK national character set
28-	31	TCGOGR	-- Designate G0 as graphics character set
29-	1	TCG1AS	-- Designate G1 as ascii character set
29-	11	TCG1DS	-- Designate G1 as DEC supplemental character set
29-	21	TCG1UK	-- Designate G1 as UK national character set
29-	31	TCG1GR	-- Designate G1 as graphics character set
30-	1	TCG2AS	-- Designate G2 as ascii character set
30-	11	TCG2DS	-- Designate G2 as DEC supplemental character set
30-	21	TCG2GR	-- Designate G2 as graphics character set
31-	1	TCG3AS	-- Designate G3 as ascii character set
31-	11	TCG3DS	-- Designate G3 as DEC supplemental character set
31-	21	TCG3GR	-- Designate G3 as graphics character set
32-	1	TCSD	-- Shift-out character - Lock shift G1 to GL
32-	11	TCSI	-- Shift-in character - Lock shift G0 to GL
32-	21	TCLS2	-- Lock shift G2 to GL
32-	31	TCLS3	-- Lock shift G3 to GL
32-	41	TCLS1R	-- Lock shift G1 into GR
32-	51	TCLS2R	-- Lock shift G2 into GR
32-	61	TCLS3R	-- Lock shift G3 into GR
32-	71	TCSS2	-- Single shift G2 to GL
32-	82	TCSS3	-- Single shift G3 to GL
33-	1	TCSAA	-- Set ANSI attribute
33-	15	TCRAA	-- Reset ANSI attribute
33-	29	TCSDA	-- Set DEC attribute
33-	43	TCRDA	-- Reset DEC attribute
34-	1	TCSTA	-- Set terminal attribute
35-	1	TCRTA	-- Reset terminal attribute
36-	1	CVTTAV	-- Convert terminal attribute value to flag
37-	1	CKTAC	-- Check for complex mode changes
38-	1	TCAKM	-- Select application keypad mode
38-	11	TCNKM	-- Select numeric keypad mode

Table of contents

39-	1	TCN3	-- Set line attributes
40-	1	TCSCA	-- Set character attributes
42-	1	TC100	-- Select VT100/VT200 mode
43-	1	TCRESF	-- Terminal reset
44-	1	TCPRF	-- Printer control operation
45-	1	TCLERS	-- Erase within a line
46-	1	TCBERS	-- Erase within a page
47-	1	TCSSR	-- Set scrolling region
48-	1	SETHOM	-- Set cursor to the home position
49-	1	SCRUP	-- Scroll screen up one line
50-	1	SCRDN	-- Scroll screen down one line
51-	1	SCRCHK	-- Check for scrolling limits
52-	1	WINSPN	-- Suspend job until it reattaches to terminal
53-	1	ERSLIN	-- Erase the current line
54-	1	ERSCTL	-- Erase from cursor to the end of the line
55-	1	ERSLTC	-- Erase from beginning of line to cursor
56-	1	ERSCTP	-- Erase from cursor to the end of the page
57-	1	ERSPTC	-- Erase from beginning of page to cursor
58-	1	ERSPAC	-- Clear entire page to spaces
59-	1	CLRLIN	-- Clear a line to spaces
60-	1	CPYLIN	-- Copy characters from one line to another
61-	1	SETLAB	-- Set attributes for current line
62-	1	GETLAB	-- Get attributes for current line
63-	1	SETLIN	-- Select a line as current line
64-	1	WINSF	-- Switch from a job with a display window
65-	1	WINST	-- Switch to job with a window
66-	1	WINDSP	-- Redisplay current window for job
67-	1	REFRSH	-- Refresh screen from window contents
68-	1	SNDLIN	-- Send line of characters to terminal
69-	1	GENCLR	-- Gen control sequence to clear screen
70-	1	GENCAF	-- Generate sequence to set character attributes
71-	1	GENCSC	-- Generate terminal sequence to select char set
72-	1	GENMAP	-- Generate sequence to set up char set mapping
73-	1	GENSSS	-- Generate sequence for split screen scrolling
74-	1	GENTEM	-- Turn VT52 emulation mode on or off
75-	1	GENWAF	-- Generate terminal sequence to set window attrib
76-	1	GENAAS	-- Generate control sequence for ANSI attributes
77-	1	GENDAS	-- Generate control sequence for DEC attributes
78-	1	GENLAF	-- Generate terminal sequence to set line attrib
79-	1	GENSPC	-- Generate sequence to move cursor over
80-	1	GENCSR	-- Generate cursor addressing sequence
81-	1	GENESC	-- Generate escape character
81-	8	GENCSI	-- Generate CSI character sequence
81-	30	GENCHR	-- Send a character to the terminal
82-	1	GENVAL	-- Convert value to digits and send
83-	1	EMTWIN	-- Dispatch window control EMT's
84-	1	WFNEW	-- EMT to create a new window
85-	1	WFMAP	-- EMT to select a window as the current window
86-	1	WFDEL	-- EMT to delete a window
87-	1	WFSPND	-- Suspend window processing
87-	15	WFRSUM	-- Resume window processing
88-	1	WFRPNT	-- Cause contents of a window to be printed
89-	1	WFREAD	-- Copy window information to program buffer
90-	1	WFSTT	-- EMT to set terminal type for windowing
91-	1	WINSTT	-- Set terminal type for a window
92-	1	WINREL	-- Release all display windows for a job
93-	1	WINDEL	-- Delete a window

Table of contents

94-	1	WINSRC	-- Locate control block for a window
95-	1	MAKWSB	-- Create named region for window screen buffer
96-	1	MAKRDB	-- Make a region definition block
97-	1	FREWSB	-- Free memory used by window screen buffer
98-	1	WININI	-- TSWIN initialization
99-	1	WINPRT	-- Window print-screen function

```

1          .TITLE  TSWIN -- TSX-Plus Display Windows
2          .ENABL  LC
3          .ENABL  AMA
4          .DSABL  GBL
5          .CSECT  TSWIN
6 000000    TSWIN: .RAD50  /WIN/          ;Overlay region id
7
8          ; TSWIN is the TSX-Plus system overlay that provides display window support.
9
10         ; Copyright (c) 1985.
11         ; S&H Computer Systems, Inc.
12         ; Nashville, Tennessee USA
13         ; All rights reserved.
14
15         ; Global definitions
16
17         .GLOBL  WINCHR, EMIWIN, WININI, WINREL, WINDSP
18         .GLOBL  WINST, WINSF, WINPRT
19
20         ; Global references
21
22         .GLOBL  LSW11, $V52EM, LNPRIM
23         .GLOBL  LSTSL, LPRC1, LPRC2, LBRKCQ, NMFREQ, GETRTQ
24         .GLOBL  IOQSIZ, CQ#R1, QCOMPL, VALADW, VALADB
25         .GLOBL  P2#CXT, PRIVC2, $BBIT, LSW2, AW#PRT
26         .GLOBL  RC#EXC, RC#FLG, LOTSIZ, LOTSPC, LOTNXT, LOTPNT
27         .GLOBL  $CTRLD, LSW3, $RFRSH, LSW4, AW$SPN
28         .GLOBL  $WDISP, LSW6, S$OTWT, LSTATE, RC#BLK, RC#CNT
29         .GLOBL  $VNOTT, LSW, PCSPND, FRKPRI, FORCEX
30         .GLOBL  DW#CSB, DW#CSR, DW#CSP, TCSBSZ, LWINDO
31         .GLOBL  ESC, CSICHR, SS3CHR, AW$52, DW$AW, BUFCHR, AW$552
32         .GLOBL  KPAR6, VPAR6, OVRHC, INTPRI, PSW, PR7
33         .GLOBL  DW#CCA, DW#COL, DW#CPL, DW#LIN, DW#SRB
34         .GLOBL  DW#SRT, DW#LPP, DW#TLN, DW#LPT, DW#MAP
35         .GLOBL  DW#RID, DW#JOB, DW#ID, RC#BAS, R. GID
36         .GLOBL  R. GSIZ, R. GSTS, R. NAME, RS. CGR, RS. PVT
37         .GLOBL  RS. GBL, EMTBLK, SETERR, EMTXIT, RS. EGR
38         .GLOBL  DW##SZ, CR, LF, AC#BLD, AC#BLK, AC#REV
39         .GLOBL  CORUSR, AC#ULN, AL#DHT, AL#DHB, AL#DWD
40         .GLOBL  BUFCHR, VMXWIN, VT52, VT2007, VT2008, LTRMTP
41         .GLOBL  AW$200, AW$132, AW$INS, AW$ACK, AW$REV, AW$ORS
42         .GLOBL  AW$AKM, AW#VCR, LSW7, $SLON, $SLKED, LCOL
43         .GLOBL  AW#PRM, $DETC, LSW, LSW6, $WDISP, AW#RPT
44         .GLOBL  AW$SS, DW#CLS, DW#GLM, DW#GRM, AC#SET
45         .GLOBL  DW#MSL, DW#NSL, AW#DDC
46         .GLOBL  DW#GOM, DW#G1M, DW#G2M, DW#G3M
47         .GLOBL  DW#SLN, DW#SCL, DW#SCA, WINTOP

```

```

1 ;-----
2 ; Macro definitions
3 ;
4 ; Macros to enable and disable interrupts
5 ;
6 ; .MACRO DISABL ;Disable interrupts
7 BIS #PR7,@#PSW
8 .ENDM DISABL
9
10 ; .MACRO ENABL ;Enable interrupts
11 BIC INTPRI,@#PSW
12 .ENDM ENABL
13 ;
14 ; Macro to call a system overlay
15 ;
16 ; .MACRO OCALL ENTADD
17 ; IF B,ENTADD
18 ; ERROR ;OCALL without entry address
19 ; ENDC
20 CALL OVRHC
21 ; WORD ENTADD
22 ; ENDM OCALL
23 ;
24 ; Macros to map to screen buffer and restore mapping
25 ;
26 ; .MACRO BUFMAP
27 DISABL
28 MOV @#KPAR6,MAPHLD
29 MOV DW$MAP(R2),@#KPAR6
30 ; ENDM BUFMAP
31
32 ; .MACRO UNMAP
33 MOV MAPHLD,@#KPAR6
34 ENABL
35 ; ENDM UNMAP
36 ;
37 ; Macro to send a character to the terminal
38 ;
39 ; .MACRO SEND CHAR
40 MOVB CHAR,R0
41 CALL GENCHR
42 ; ENDM SEND
43
44 ;-----
45 ; Data areas and parameters
46 ;
47 SEMI = 73 ; Semicolon
48 ;
49 DWBAS: .WORD WINTOP ;Pointer to 1st window control block
50 DWEND: .WORD 0 ;Pointer past last window control block
51 MAPHLD: .WORD 0 ;Temp cell used by BUFMAP/UNMAP macros
52 R5OWIN: .RAD50 /WIN/
53 R5OPRT: .RAD50 /PRT/
54 CSBUF: .BLKB 16. ;Cursor string work buffer
55 .EVEN

```

WINCHR -- Process next output character

```

1          .SBTTL  WINCHR -- Process next output character
2          ;-----
3          ; This routine is called to process each character sent to the terminal
4          ; by a running program.  It determines if the character is part of an
5          ; escape sequence or is a regular character.
6          ;
7          ; Inputs:
8          ;   R0 = Character being sent.
9          ;   R1 = Job index number.
10         ;
11         ; Outputs:
12         ;   C-flag set ==> Do not send this char to terminal now.
13         ;
14 000034 010046 WINCHR: MOV     R0,-(SP)
15 000036 010246         MOV     R2,-(SP)
16 000040 010546         MOV     R5,-(SP)
17 000042 010005         MOV     R0,R5          ;Carry character in R5
18         ;
19         ; Get pointer to current window control block for job
20         ;
21 000044 016102 0000000 MOV     LWINDO(R1),R2  ;Get pointer to window control block
22         ;
23         ; See if processing is suspended for this window
24         ;
25 000050 032762 0000000 0000000 BIT     #AW$SPN,DW$AW(R2);Is window processing suspended?
26 000056 001045         BNE     B$          ;Br if yes -- Just pass through the char
27         ;
28         ; Mask character to 7 bits unless 8 bit support has been enabled
29         ;
30 000060 032761 0000000 0000000 BIT     ##8BIT,LSW2(R1) ;Is 8 bit char support wanted?
31 000066 001002         BNE     1$          ;Br if yes
32 000070 042705 177600         BIC     #^C<177>,R5   ;Mask character to 7 bits
33         ;
34         ; Ignore nulls
35         ;
36 000074 105705 1$:      TSTB    R5          ;Is character null?
37 000076 001427         BEQ     7$          ;Br if null
38         ;
39         ; Determine if this character begins a terminal control sequence
40         ;
41 000100 004737 000510'     CALL    WCSCHK        ;Check for control sequence start
42 000104 103024         BCC     7$          ;Br if start of control sequence
43         ;
44         ; See if we are currently accepting a terminal control sequence
45         ;
46 000106 016200 0000000     MOV     DW$CSR(R2),R0  ;Are we processing a control sequence?
47 000112 001402         BEQ     3$          ;Br if not
48 000114 004710         CALL    (R0)          ;Call routine to process this character
49 000116 000417         BR     7$          ;Finished with this character
50         ;
51         ; If output is being directed to the terminal printer port, then
52         ; don't update window image with this character.
53         ;
54 000120 032762 0000000 0000000 3$:   BIT     #AW$PRT,DW$AW(R2);Is output going to printer?
55 000126 001013         BNE     7$          ;Br if yes -- Bypass window update
56         ;
57         ; Determine if this is a normal or control character

```

WINCHR -- Process next output character

```

58 ;
59 000130 010500          MOV     R5,R0          ;Get the character
60 000132 042700 177600   BIC     #^C<177>,R0     ;Mask to 7 bits
61 000136 020027 000037   CMP     R0,#37         ;Is this a control character?
62 000142 101003          BHI     4$             ;Br if not
63 000144 004737 000370'   CALL    DOCTRL        ;Process a control character
64 000150 000402          BR      7$             ;
65 ;
66 ; Process regular character
67 ;
68 000152 004737 000204'   4$:     CALL    REGCHR   ;Process a regular character
69 ;
70 ; See if we should display this character now
71 ;
72 000156 032762 0000000 0000000 7$:     BIT     #AW#DDC,DW$AW(R2);Should we suppress char display?
73 000164 001402          BEQ     8$             ;Br if not
74 ;
75 ; We don't want to display this character
76 ;
77 000166 000261          SEC                      ;Signal to not display the character
78 000170 000401          BR      9$             ;
79 ;
80 ; We want to display this character
81 ;
82 000172 000241          8$:     CLC                      ;Signal to display the character
83 ;
84 ; Finished
85 ;
86 000174 012605          9$:     MOV     (SP)+,R5
87 000176 012607          MOV     (SP)+,R2
88 000200 012600          MOV     (SP)+,R0
89 000202 000207          RETURN

```

REGCHR -- Process regular characters

```

1          .SBTTL  REGCHR -- Process regular characters
2          ;-----
3          ; Process regular characters which are stored into the appropriate
4          ; cell of the character matrix.
5          ;
6          ; Inputs:
7          ; R2 = Pointer to window control block
8          ; R5 = Character
9          ;
10         000204 010346 REGCHR: MOV     R3, -(SP)
11         000206 010546         MOV     R5, -(SP)
12         ;
13         ; Get pointer to 1st character on current line
14         ;
15         000210 016203 0000000 MOV     DW$LPT(R2), R3 ;Get pointer to 1st char on line
16         ;
17         ; Get pointer to current character on the line
18         ;
19         000214 016200 0000000 MOV     DW$COL(R2), R0 ;Get current column number
20         000220 005300         DEC     R0             ;1st column is # 1
21         000222 006300         ASL    R0             ;Two bytes used per column
22         000224 060003         ADD    R0, R3        ;Get pointer to char byte for current col
23         ;
24         ; Get number of character set for this character
25         ;
26         000226 116200 0000000 MOVVB  DW$GRM(R2), R0 ;Assume character is in GR
27         000232 032705 000200   BIT    #200, R5      ;Is character in GR (8 bit character)
28         000236 001013         BNE    1$           ;Br if yes
29         000240 116200 0000000 MOVVB  DW$GLM(R2), R0 ;Determine which set GL is mapped to
30         000244 032762 0000000 0000000 BIT    #AW$SS, DW$AW(R2);Are we single-shifting this character?
31         000252 001405         BEQ    1$           ;Br if not
32         000254 116200 0000000 MOVVB  DW$GLS(R2), R0 ;Get single-shift mapping for char
33         000260 042762 0000000 0000000 BIC    #AW$SS, DW$AW(R2);Reset single-shift flag
34         000266 060200         1$:  ADD    R2, R0      ;Add base address of window control block
35         000270 116000 0000000 MOVVB  DW$GOM(R0), R0 ;Get char set for this character
36         000274 042705 177600   BIC    #^C<177>, R5 ;Mask character to 7 bits
37         ;
38         ; Get character attribute flags (bold, blinking, etc.)
39         ;
40         000300 156200 0000000 BISB   DW$CCA(R2), R0 ;Add character attribute flags
41         ;
42         ; Store character and attribute into that cell
43         ;
44         000304         BUFBMAP ;;;Map to screen buffer
45         000326 110523 MOVVB  R5, (R3)+ ;;;Store character
46         000330 110023 MOVVB  R0, (R3)+ ;;;Store character attribute flags
47         000332         UNMAP ;Restore mapping
48         ;
49         ; Advance column number unless we are at the end of the line
50         ;
51         000346 026262 0000000 0000000 CMP    DW$COL(R2), DW$CPL(R2);Are we at the end of the line now?
52         000354 103002         BHIS  9$           ;Br if at end of the line now
53         000356 005262 0000000         INC    DW$COL(R2) ;Advance to next column
54         ;
55         ; Finished
56         ;
57         000362 012605 9$:  MOV    (SP)+, R5

```

58 000364 012603
59 000366 000207

MOV (SP)+,R3
RETURN

```

1          .SBTTL DOCTRL -- Process control characters
2          ;-----
3          ; This routine is called when the character being output is a
4          ; control character (000 - 037).
5          ;
6          ; Inputs:
7          ; R2 = Pointer to window control block
8          ; R5 = Character
9          ;
10         DOCTRL:
11         ;
12         ; Call processing routine for this character
13         ;
14         000370 010500          MOV     R5,R0          ;Get the character
15         000372 042700 177600  BIC     #^C<177>,R0    ;Mask to 7 bits
16         000376 006300          ASL     R0              ;Convert to word table index
17         000400 004770 000406'  CALL    @CCRTN(R0)     ;Call appropriate processing routine
18         ;
19         ; Finished
20         ;
21         000404 000207          RETURN
22         ;-----
23         ; Branch table for control character processing routines
24         ;
25         ;
26         000406 000506'  CCRTN: .WORD  CCEXIT          ; 000 - NUL
27         000410 000506'          .WORD  CCEXIT          ; 001 - SOH
28         000412 000506'          .WORD  CCEXIT          ; 002 - STX
29         000414 000506'          .WORD  CCEXIT          ; 003 - ETX
30         000416 000506'          .WORD  CCEXIT          ; 004 - EDT
31         000420 000506'          .WORD  CCEXIT          ; 005 - ENQ
32         000422 000506'          .WORD  CCEXIT          ; 006 - ACK
33         000424 000506'          .WORD  CCEXIT          ; 007 - BEL
34         000426 002230'          .WORD  TCBS           ; 010 - BS
35         000430 002246'          .WORD  TCHT           ; 011 - HT
36         000432 002454'          .WORD  TCLF           ; 012 - LF
37         000434 002454'          .WORD  TCLF           ; 013 - VT
38         000436 002454'          .WORD  TCLF           ; 014 - FF
39         000440 002306'          .WORD  TCCR           ; 015 - CR
40         000442 003516'          .WORD  TCSD           ; 016 - SD
41         000444 003526'          .WORD  TCSI           ; 017 - SI
42         000446 000506'          .WORD  CCEXIT          ; 020 - DLE
43         000450 000506'          .WORD  CCEXIT          ; 021 - DC1
44         000452 000506'          .WORD  CCEXIT          ; 022 - DC2
45         000454 000506'          .WORD  CCEXIT          ; 023 - DC3
46         000456 000506'          .WORD  CCEXIT          ; 024 - DC4
47         000460 000506'          .WORD  CCEXIT          ; 025 - NAK
48         000462 000506'          .WORD  CCEXIT          ; 026 - SYN
49         000464 000506'          .WORD  CCEXIT          ; 027 - ETB
50         000466 000506'          .WORD  CCEXIT          ; 030 - CAN
51         000470 000506'          .WORD  CCEXIT          ; 031 - EM
52         000472 000204'          .WORD  REGCHR         ; 032 - SUB (ctrl-Z)
53         000474 000506'          .WORD  CCEXIT          ; 033 - ESC
54         000476 000506'          .WORD  CCEXIT          ; 034 - FS
55         000500 000506'          .WORD  CCEXIT          ; 035 - GS
56         000502 000506'          .WORD  CCEXIT          ; 036 - RS
57         000504 000506'          .WORD  CCEXIT          ; 037 - US

```

```
58 ;  
59 ; Immediate return for most control characters  
60 ;  
61 000506 000207 CCEXIT: RETURN
```

```
1 .SBTTL WCSCHK -- Check for start of control sequence
2 -----
3 ; This routine is called to determine if the current character begins
4 ; a terminal control sequence.
5 ;
6 ; Inputs:
7 ; R2 = Window control block.
8 ; R5 = Current character
9 ;
10 ; Outputs:
11 ; C-flag cleared ==> Start of control sequence
12 ; C-flag set ==> Not start of control sequence
13 ;
14 000510 WCSCHK:
15 ;
16 ; See if this is the start of an escape sequence
17 ;
18 000510 120527 0000000 CMPB R5,#ESC ;Is this character escape?
19 000514 001003 BNE 1$ ;Br if not
20 000516 004737 000546' CALL WCPESC ;Begin escape sequence
21 000522 000405 BR B$
22 ;
23 ; See if this character is CSI, beginning of VT200 control sequence
24 ;
25 000524 120527 0000000 1$: CMPB R5,#CSICHR ;CSI character?
26 000530 001004 BNE 7$ ;Br if not
27 000532 004737 000600' CALL WPCSI ;Start VT200 control sequence
28 ;
29 ; We began a control sequence
30 ;
31 000536 000241 B$: CLC ;Signal control sequence began
32 000540 000401 BR 9$
33 ;
34 ; We did not begin a control sequence
35 ;
36 000542 000261 7$: SEC ;Signal that not control sequence
37 ;
38 ; Finished
39 ;
40 000544 000207 9$: RETURN
```

WCPESC -- Escape processing

```

1          .SBTTL  WCPESC -- Escape processing
2          ;-----
3          ; Process an Escape character
4          ;
5          ; Inputs:
6          ;   R2 = Window control block
7          ;   R5 = Escape character
8          ;
9 000546   WCPESC:
10         ;
11         ; Initialize control sequence buffer pointer
12         ;
13 000546   005062   0000000   CLR      DW#CSP(R2)      ; Say no chars accrued yet
14         ;
15         ; Set address of routine to be called to process 1st character after
16         ; escape.
17         ;
18 000552   012700   000624'   MOV      #EPCH1,R0      ; Routine for 1st character after escape
19 000556   032762   0000000 0000000   BIT      #<AW$52!AW$552>,DW#AW(R2); Is terminal in VT52 emulation mode?
20 000564   001402   BEQ      1$             ; Br if not
21 000566   012700   000710'   MOV      #EP52,R0      ; Set routine for VT52 mode
22 000572   010062   0000000   1$:     MOV      R0,DW#CSR(R2) ; Set address of processing routine
23 000576   000207   RETURN
24
25         ;-----
26         ; Received a CSI control character for a VT200 terminal.
27         ;
28         ; Inputs:
29         ;   R2 = Window control block address
30         ;
31 000600   012762   000624' 0000000   WCPCSI: MOV      #EPCH1,DW#CSR(R2) ; Set address of routine for next char
32 000606   005062   0000000   CLR      DW#CSP(R2)      ; Say no chars accrued yet
33 000612   112700   000133   MOVB    #'L,R0          ; Treat CSI char like ESC [
34 000616   004737   001136'   CALL    ACRC5           ; Store "L" as 1st char of sequence
35 000622   000207   RETURN

```

EPCH1 -- Accrue a terminal control sequence

```

1          .SBTTL  EPCH1  -- Accrue a terminal control sequence
2          ;-----
3          ; EPCH1 is called to accrue a VT100 or VT200 control sequence.
4          ;
5          ; There are two types of "control" sequences:
6          ;
7          ; Escape sequence format:  ESC I...I F
8          ;     I = Intermediate character in the range 040 to 057
9          ;     F = Final character in the range 060 to 176
10         ;
11         ; Control sequence format:  ESC P...P I...I F
12         ;     CSI = CSI character or ESC [
13         ;     P   = Parameter values in the range 060 to 077
14         ;     I   = Intermediate characters in the range 040 to 057
15         ;     F   = Final character in the range 100 to 176
16         ;
17         ; Inputs:
18         ;     R2 = Address of window control block.
19         ;     R5 = Received character
20         ;
21 000624  010546  EPCH1:  MOV     R5, -(SP)
22 000626  042705  177600      BIC     #^C<177>, R5      ;Mask character to 7 bits
23         ;
24         ; Add received character to end of control sequence already received
25         ;
26 000632  010500      MOV     R5, R0      ;Get received character
27 000634  004737  001136'    CALL    ACRC5      ;Store into control sequence buffer
28         ;
29         ; Determine if this character terminates the control sequence
30         ;
31 000640  120527  000060      CMPB   R5, #60      ;Is this the terminating character?
32 000644  103417      BLD    9$          ;Br if not
33 000646  120527  000176      CMPB   R5, #176     ;Is this the terminating character?
34 000652  101014      BHI    9$          ;Br if not
35 000654  120527  000133      CMPB   R5, #'[     ;Is this part of string header?
36 000660  001411      BEQ   9$          ;Br if string header
37 000662  120527  000100      CMPB   R5, #100    ;100 to 176 always terminates
38 000666  103004      BHIS  1$          ;
39 000670  126227  0000000 000133  CMPB   DW$CSB(R2), #'[ ;Is this an escape or control sequence?
40 000676  001402      BEQ   9$          ;Br if control sequence. Only 100-176 term
41         ;
42         ; This is the final character of the control sequence
43         ;
44 000700  004737  001174'    1$:    CALL    CSFIN      ;End of control sequence
45         ;
46         ; Finished
47         ;
48 000704  012605      9$:    MOV     (SP)+, R5
49 000706  000207      RETURN

```

EPCH1 -- Accrue a terminal control sequence

```

1
2 ; -----
3 ; Accrue VT52 control sequences.
4 ; All VT52 control sequences consist of ESC followed by a single character
5 ; except for the cursor addressing sequence ESC Y line col.
6 ; The VT52 sequences are converted to VT52 compatible sequences.
7 ;
8 ; Inputs:
9 ; R2 = Address of window control block
10 ; R5 = Received character
11 000710 010546 EP52: MOV R5, -(SP)
12 000712 042705 177600 BIC #^C<177>, R5 ; Mask character to 7 bits
13
14 ; If this character is a letter, insert "I" in front of it.
15 ;
16 000716 120527 000101 CMPB R5, #'A ; Letter
17 000722 103416 BLO 2$ ; Br if not
18 000724 120527 000132 CMPB R5, #'Z ; Letter
19 000730 101013 BHI 2$ ; Br if not
20 000732 012700 000133 MOV #'I, R0 ; Store "I"
21 000736 004737 001136' CALL ACRC5
22
23 ; Determine if this is the cursor addressing function
24 ;
25 000742 120527 000131 CMPB R5, #'Y ; Cursor addressing function?
26 000746 001004 BNE 2$ ; Br if not
27 000750 012762 000776' 0000000 MOV #EP52L, DW$CSR(R2); Set routine to process next char
28 000756 000405 BR 9$
29
30 ; This character terminates the control sequence.
31 ;
32 000760 010500 2$: MOV R5, R0 ; Get received character
33 000762 004737 001136' CALL ACRC5 ; Add to string we are accruing
34 000766 004737 001174' CALL CSFIN ; This terminates the control sequence
35
36 ; Finished
37 ;
38 000772 012605 9$: MOV (SP)+, R5
39 000774 000207 RETURN
40
41 ; -----
42 ; Accept the character which represents the line number in a VT52
43 ; cursor addressing sequence.
44 ;
45 ; Inputs:
46 ; R2 = Address of window control block
47 ; R5 = Received character (whose binary value is line number + 037)
48 ;
49 000776 042705 177600 EP52L: BIC #^C<177>, R5 ; Mask character to 7 bits
50 001002 120527 000070 CMPB R5, #70 ; Octal 70 ==> Remain on current line
51 001006 103404 BLO 1$ ; Br if new line specified
52 001010 016205 0000000 MOV DW$LIN(R2), R5 ; Get current line number
53 001014 062705 000037 ADD #37, R5 ; Convert to ascii character
54 001020 004737 001066' 1$: CALL CV52 ; Convert char to digit string
55 001024 112700 000073 MOVB #SEMI, R0 ; Get parameter separator character
56 001030 004737 001136' CALL ACRC5 ; Store after line number value
57 001034 012762 001044' 0000000 MOV #EP52C, DW$CSR(R2); Set routine to process column number char

```

EPCH1 -- Accrue a terminal control sequence

```

58 001042 000207          RETURN
59
60
61 ; -----
62 ; Accept the character which represents the column number in a VT52
63 ; cursor addressing sequence.
64 ;
65 ; Inputs:
66 ; R2 = Address of window control block
67 ; R5 = Received character (whose binary value is column number + 037)
68 001044 004737 001066' EP52C: CALL CV52          ;Convert char to digit string
69 001050 112700 000110    MOV  #'H,R0        ;Store terminating character
70 001054 004737 001136'    CALL ACRC        ;
71 001060 004737 001174'    CALL CSFIN       ;This terminates the control sequence
72 001064 000207          RETURN
73
74 ; -----
75 ; Convert a received character whose binary value represents a line
76 ; number or a column number in a VT52 cursor addressing sequence
77 ; into an ascii digit string and store into the accrued control
78 ; sequence.
79 ;
80 ; Inputs:
81 ; R2 = Address of window control block
82 ; R5 = Received character whose binary value - 37 is the stored result
83 ;
84 001066 010446          CV52:  MOV  R4,-(SP)
85 001070 010546          MOV  R5,-(SP)
86 ;
87 ; Subtract bias of 37
88 ;
89 001072 162705 000037    SUB   #37,R5        ;Remove bias from character value
90 ;
91 ; Convert to digit string
92 ;
93 001076 005004          CLR   R4            ;Clear high-order for divide
94 001100 071427 000012    DIV  #10.,R4       ;Split into two decimal digits
95 001104 062704 000060    ADD  #'0,R4        ;Form high-order ascii digit
96 001110 010400          MOV  R4,R0          ;Get the character
97 001112 004737 001136'    CALL ACRC        ;Store into control string
98 001116 062705 000060    ADD  #'0,R5        ;Form low-order ascii digit
99 001122 010500          MOV  R5,R0          ;Get the character
100 001124 004737 001136'   CALL ACRC        ;Store into control string
101 ;
102 ; Finished
103 ;
104 001130 012605          MOV  (SP)+,R5
105 001132 012604          MOV  (SP)+,R4
106 001134 000207          RETURN

```

ACRCS -- Store a character into control seq buffer

```

1          .SBTTL  ACRCS  -- Store a character into control seq buffer
2          ;-----
3          ; This routine is called to add another character to the end of the
4          ; accrued control sequence in the DW#CSB buffer area.
5          ;
6          ; Inputs:
7          ; R0 = Character to be added to end of string
8          ; R2 = Address of window descriptor block
9          ;
10         ACRCS:  MOV     R3, -(SP)
11         001136 010346      BIC     #^C<177>, R0      ;Mask character to 7 bits
12         001140 042700 177600
13         ; Make sure we don't overflow the control sequence buffer
14         ;
15         001144 016203 0000000      MOV     DW#CSP(R2), R3      ;Get # chars in buffer now
16         001150 020327 1777770      CMP     R3, #TCSBSZ-1      ;Is buffer full already?
17         001154 103005      BHIS    9$      ;Br if yes -- Ignore this character
18         ;
19         ; Store character into buffer
20         ;
21         001156 060203      ADD     R2, R3      ;Point to next char pos in buffer
22         001160 110063 0000000      MOVEB  R0, DW#CSB(R3)      ;Store char into buffer
23         001164 005262 0000000      INC     DW#CSP(R2)      ;Increment character count
24         ;
25         ; Finished
26         ;
27         001170 012603      9$:    MOV     (SP)+, R3
28         001172 000207      RETURN

```

CSFIN -- Process received control sequence

```

1          .SBTTL  CSFIN  -- Process received control sequence
2          ;-----
3          ; We have finished accruing a control sequence, process it.
4          ;
5          ; Inputs:
6          ; R2 = Address of window control block.
7          ;
8 001174 010346 CSFIN:  MOV    R3,-(SP)
9 001176 010446      MOV    R4,-(SP)
10 001200 010546      MOV    R5,-(SP)
11          ;
12          ; Store null at end of control sequence string
13          ;
14 001202 010203      MOV    R2,R3          ;Get address of window control block
15 001204 066203 0000000 ADD    DW$CSP(R2),R3 ;Point to next char pos in buffer
16 001210 105063 0000000 CLRB  DW$CSB(R3)     ;Store null at end of string
17          ;
18          ; Move control sequence to work buffer and remove any parameter characters
19          ;
20 001214 012705 000014'  MOV    #CSBUF,R5     ;Point to work buffer
21 001220 010203      MOV    R2,R3          ;Get address of buffer with full string
22 001222 062703 0000000 ADD    #DW$CSB,R3
23 001226 121327 000133  CMPB  (R3),#'E       ;Do we need to exclude parameter values?
24 001232 001014      BNE   3$             ;Br if not
25          ;
26          ; This is a control sequence. Ignore parameter value characters in the
27          ; range 060 to 076.
28          ;
29 001234 112300 1$:    MOVB  (R3)+,R0     ;Get next char from input string
30 001236 001410      BEQ   4$             ;Br if hit end of string
31 001240 120027 000060  CMPB  R0,#060        ;Is this a parameter character?
32 001244 103403      BLO   2$             ;Br if not
33 001246 120027 000076  CMPB  R0,#076        ;Parameter character?
34 001252 101770      BLOS  1$             ;Br if parameter character
35 001254 110025 2$:    MOVB  R0,(R5)+     ;Store char into work buffer
36 001256 000766      BR    1$             ;Keep moving
37 001260 105025 4$:    CLRB  (R5)+     ;Store null at end of string
38 001262 000402      BR    5$
39          ;
40          ; This is an escape sequence. We don't have to remove parameter values.
41          ;
42 001264 112325 3$:    MOVB  (R3)+,(R5)+   ;Move char to work buffer
43 001266 001376      BNE   3$             ;Loop till null moved
44          ;
45          ; The control sequence is now in the work buffer (CSBUF) with any parameter
46          ; value strings removed.
47          ; Begin loop to try to identify the control sequence.
48          ;
49 001270 012704 001432' 5$:    MOV    #CSTBLL,R4   ;Point to 1st set of control sequences
50 001274 126527 177776 000140 CMPB  -2(R5),#140    ;Is final char of sequence less than 140?
51 001302 103002      BHIS  10$            ;Br if not
52 001304 012704 001560'  MOV    #CSTBLU,R4   ;Point to control seq table for final < 140
53          ;
54          ; Compare accrued control sequence with sequence stored in table
55          ;
56 001310 012703 000014' 10$:   MOV    #CSBUF,R3    ;Point to accrued control sequence
57 001314 122324 12$:   CMPB  (R3)+,(R4)+   ;Compare the strings

```

CSFIN -- Process received control sequence

```

58 001316 001004          BNE      13$      ;Br if mismatch
59 001320 105764 177777   TSTB    -1(R4)    ;Was that the end of both strings?
60 001324 001373          BNE      12$      ;Br if not
61 001326 000412          BR       14$      ;We have a match
62                          ;
63                          ; Strings do not match --- Move on to next table entry
64                          ;
65 001330 005304          13$:    DEC      R4          ;Point to last char compared in table
66 001332 105724          15$:    TSTB    (R4)+      ;Search for null at end of asciz string
67 001334 001376          BNE      15$      ;Loop till null found
68 001336 062704 000003   ADD     #3,R4     ;Bound up and skip over following word
69 001342 042704 000001   BIC     #1,R4     ;Get to word boundary
70 001346 005714          TST     (R4)      ;Reached end of table?
71 001350 001357          BNE      10$      ;Loop if not
72 001352 000417          BR       20$      ;Control sequence is not in our table
73                          ;
74                          ; We found the control sequence in our table.
75                          ; Call processing routine.
76                          ; Set R5 to point to start of any possible parameter string in control seq.
77                          ;
78 001354 010205          14$:    MOV     R2,R5     ;Point to window control block
79 001356 062705 0000010  ADD     #DW$CSB+1,R5 ;Point to start of possible parameter string
80 001362 005204          INC     R4         ;Bound up to next word
81 001364 042704 000001   BIC     #1,R4     ;Get to word boundary
82 001370 011404          MOV     (R4),R4   ;Get address of routine to call
83 001372 032762 0000000 0000000  BIT     #AW$PRT,DW$AW(R2);Are we directing output to printer port?
84 001400 001403          BEQ     16$      ;Br if not
85 001402 020427 004666'  CMP     R4,#TCPRT ;Is this printer control operation?
86 001406 001001          BNE      20$      ;Br if not -- Ignore till printer turned off
87 001410 004714          16$:    CALL    (R4)    ;Call processing routine
88                          ;
89                          ; Finished with control sequence
90                          ;
91 001412 005062 0000000  20$:    CLR     DW$CSP(R2) ;No accrued chars in control sequence
92 001416 005062 0000000  CLR     DW$CSR(R2)  ;Not accruing a control sequence now
93 001422 012605          MOV     (SP)+,R5
94 001424 012604          MOV     (SP)+,R4
95 001426 012603          MOV     (SP)+,R3
96 001430 000207          RETURN

```

CSFIN -- Process received control sequence

```

1      ;-----
2      ; Generate table of terminal control sequences and associated processing
3      ; routines.
4      ;
5      .MACRO ESCSEQ STRING,RTN
6      .ASCIZ /STRING/
7      .EVEN
8      .WORD RTN
9      .ENDM ESCSEQ
10     ;
11     ; Table for control sequences whose final character is in the
12     ; range 140 to 177
13     ;
14     001432 CSTBLL:
15     001432 ESCSEQ <[f>,TCCADR ;Cursor addressing
16     001440 ESCSEQ <[p>,TC100 ;Select VT100/VT200 mode
17     001446 ESCSEQ <[h>,TCSAA ;Set ANSI terminal attribute
18     001454 ESCSEQ <[l>,TCRAA ;Reset ANSI terminal attribute
19     001462 ESCSEQ <[?h>,TCSDA ;Set DEC terminal attribute
20     001470 ESCSEQ <[?l>,TCRDA ;Reset DEC terminal attribute
21     001476 ESCSEQ <[i>,TCPRT ;Printer control code
22     001504 ESCSEQ <[m>,TCSCA ;Set character attribute
23     001512 ESCSEQ <[r>,TCSSR ;Set scrolling region
24     001520 ESCSEQ <[!p>,TCREST ;Soft reset
25     001526 ESCSEQ <[c>,TCREST ;Hard reset
26     001532 ESCSEQ <[~>,TCLSR ;Lock shift G1 as GR character set
27     001536 ESCSEQ <[n>,TCLSR ;Lock shift G2 as GL character set
28     001542 ESCSEQ <[o>,TCLSR ;Lock shift G3 as GL character set
29     001546 ESCSEQ <[>>,TCLSR ;Lock shift G2 as GR character set
30     001552 ESCSEQ <[!>,TCLSR ;Lock shift G3 as GR character set
31     001556 000000 .WORD 0 ;End of table
32     ;
33     ; Table for control sequences whose final character is in the
34     ; range 60 to 137
35     ;
36     001560 CSTBLU:
37     001560 ESCSEQ <[A>,TCUP ;Move cursor up
38     001566 ESCSEQ <[B>,TCDOWN ;Move cursor down
39     001574 ESCSEQ <[C>,TCRIT ;Move cursor right
40     001602 ESCSEQ <[D>,TCLEFT ;Move cursor left
41     001610 ESCSEQ <[F>,TCGODS ;Select graphic char set for VT52
42     001616 ESCSEQ <[G>,TCGOAS ;Select normal char set for VT52
43     001624 ESCSEQ <[H>,TCCADR ;Cursor addressing
44     001632 ESCSEQ <[I>,TCIXUP ;Reverse index (VT52)
45     001640 ESCSEQ <[J>,TCPERS ;Erase within a page
46     001646 ESCSEQ <[K>,TCLERS ;Erase within a line
47     001654 ESCSEQ <[L>,TCINSL ;Insert lines
48     001662 ESCSEQ <[M>,TCDELL ;Delete lines
49     001670 ESCSEQ <[D>,TCLF ;Index (Move cursor down one line)
50     001674 ESCSEQ <[E>,TCESCE ;Move to 1st column of next line
51     001700 ESCSEQ <[M>,TCIXUP ;Reverse index (move up 1 line)
52     001704 ESCSEQ <[N>,TCSS2 ;Single shift next char to G2
53     001710 ESCSEQ <[O>,TCSS3 ;Single shift next char to G3
54     001714 ESCSEQ <[A>,TCGOUK ;Designate G0 as UK
55     001722 ESCSEQ <[B>,TCGOAS ;Designate G0 as ascii
56     001730 ESCSEQ <[O>,TCGOGR ;Designate G0 as graphics
57     001736 ESCSEQ <[A>,TCG1AS ;Designate G1 as UK

```

58	001744			ESCSEQ	,TCG1AB	;Designate G1 as ascii
59	001752			ESCSEQ	<O>,TCG1OR	;Designate G1 as graphics
60	001760			ESCSEQ	<*B>,TCG2AB	;Designate G2 as ascii
61	001766			ESCSEQ	<*O>,TCG2OR	;Designate G2 as graphics
62	001774			ESCSEQ	<+B>,TCG3AB	;Designate G3 as ascii
63	002002			ESCSEQ	<+O>,TCG3OR	;Designate G3 as graphics
64	002010			ESCSEQ	<#3>,TCN3	;Line is top half of double-high line
65	002016			ESCSEQ	<#4>,TCN4	;Line is bottom half of double high
66	002024			ESCSEQ	<#5>,TCN5	;Line is single width
67	002032			ESCSEQ	<#6>,TCN6	;Line is double width
68	002040			ESCSEQ	<7>,TCCPSV	;Save cursor position
69	002044			ESCSEQ	<8>,TCCPRG	;Restore cursor position
70	002050			ESCSEQ	<=>,TCAKM	;Select application keypad mode
71	002054	050	074	.ASCIZ	/(</>74>	; "<"
72				.EVEN		
73	002060	003354'		.WORD	TCG0DS	;Designate G0 as DEC supplemental graphics
74	002062	051	074	.ASCIZ	/)/<74>	; ">"
75				.EVEN		
76	002066	003412'		.WORD	TCG1DS	;Designate G1 as DEC supplemental graphics
77	002070	052	074	.ASCIZ	/*/<74>	; "*<"
78				.EVEN		
79	002074	003450'		.WORD	TCG2DS	;Designate G2 as DEC supplemental graphics
80	002076	053	074	.ASCIZ	/+</>74>	; "+<"
81				.EVEN		
82	002102	003476'		.WORD	TCG3DS	;Designate G3 as DEC supplemental graphics
83	002104	074	000	.ASCIZ	<74>	;Select ANSI mode with "<" character
84	002106	004466'		.WORD	TC100	;Select ANSI mode
85	002110	076	000	.ASCIZ	<76>	;Generate entry with ">" character
86	002112	004232'		.WORD	TCNKM	;Select numeric keypad mode
87	002114	000000		.WORD	0	;End of table

CSPARM -- Extract parameter value from control string

```

1          .SBTTL  CSPARM -- Extract parameter value from control string
2          ;-----
3          ; CSPARM obtains the next parameter value from the control string.
4          ; If there is no parameter value, 0 is returned as the value.
5          ; Non-parameter characters are skipped over.
6          ;
7          ; Inputs:
8          ; R5 = Pointer into control string where parameter may start.
9          ;
10         ; Outputs:
11         ; C-flag set ==> No more parameter values.
12         ; R0 = Accrued parameter value.
13         ; R5 = Points past end of parameter value.
14         ;
15 002116 010146 CSPARM: MOV     R1, -(SP)
16 002120 005001          CLR     R1          ;Accrue the value in R1
17         ;
18         ; Scan up to the start of a parameter value
19         ;
20 002122 112500 1$:      MOVB   (R5)+, R0      ;Get next char from control seq
21 002124 001430          BEQ     5$          ;Br if hit end of the string
22 002126 120027 000073  CMPB   R0, #SEMI      ;Semicolon is value separator
23 002132 001432          BEQ     7$          ;Br if no value specified for this param
24 002134 120027 000071  CMPB   R0, #'9      ;Is this a parameter character?
25 002140 101370          BHI     1$          ;Br if not
26 002142 120027 000060  CMPB   R0, #'0      ;
27 002146 103765          BLO     1$          ;Br if not digit
28         ;
29         ; We found the start of a parameter value.  Accrue it.
30         ;
31 002150 000412          BR      4$          ;Enter loop in middle
32 002152 112500 3$:      MOVB   (R5)+, R0      ;Get next char of parameter
33 002154 001420          BEQ     2$          ;Br if hit null at end of string
34 002156 120027 000071  CMPB   R0, #'9      ;Is this char part of parameter?
35 002162 101016          BHI     7$          ;Br if not
36 002164 120027 000060  CMPB   R0, #'0      ;
37 002170 103413          BLO     7$          ;Br if not
38 002172 070127 000012  MUL    #10, R1      ;Multiply previous value by 10.
39 002176 162700 000060 4$:      SUB    #'0, R0      ;Convert ascii digit to binary value
40 002202 060001          ADD    R0, R1      ;Add into previous value
41 002204 000762          BR      3$          ;Keep accruing
42         ;
43         ; There are no more parameter values
44         ;
45 002206 005305 5$:      DEC     R5          ;Point to string terminator
46 002210 005000          CLR     R0          ;Return 0 as "value"
47 002212 000261          SEC     ;Signal that there are no more parameters
48 002214 000403          BR      9$
49         ;
50         ; Finished getting the parameter value
51         ;
52 002216 005305 2$:      DEC     R5          ;Point to parameter terminator
53 002220 010100 7$:      MOV    R1, R0      ;Get accrued value
54 002222 000241          CLC     ;Signal success on return
55         ;
56         ; Finished
57         ;

```

58	002224	012601	7%:	MOV	(SP)+, R1
59	002226	000207		RETURN	

TCBS -- Process backspace character

```

1          .SBTTL  TCBS  -- Process backspace character
2          ;-----
3          ; Process a backspace character.
4          ;
5          ; Inputs:
6          ; R2 = Pointer to window control block
7          ;
8 002230   TCBS:
9          ;
10         ; Set column number back one unless we are already at column one
11         ;
12 002230   026227 0000000 000001      CMP     DW$COL(R2),#1      ;Are we already at column 1?
13 002236   001402      BEQ     9$          ;Br if yes
14 002240   005362 0000000      DEC     DW$COL(R2)      ;Move column number back one
15         ;
16         ; Finished
17         ;
18 002244   000207      9$:  RETURN

```

TCHT --- Process horizontal tab character

```

1          .SBTTL  TCHT  --- Process horizontal tab character
2          ;-----
3          ; Process horizontal tab character.
4          ;
5          ; Inputs:
6          ; R2 = Pointer to window control block
7          ;
8 002246   TCHT:
9          ;
10         ; Get current column number and advance to next multiple of B
11         ;
12 002246   016200   0000000   MOV     DW$COL(R2),R0   ;Get current column number
13 002252   005300   DEC     R0           ;Make 1st column be # 0
14 002254   062700   000010   ADD     #8.,R0        ;Advance to next tab stop
15 002260   042700   000007   BIC     #7,R0        ;Bound to next multiple of B
16 002264   005200   INC     R0           ;Make 1st column be # 1
17         ;
18         ; Make sure we don't go beyond end of line
19         ;
20 002266   020062   0000000   CMP     R0,DW$CPL(R2) ;Compare with # columns per line
21 002272   101402   BLOS   1$           ;Br if within line
22 002274   016200   0000000   MOV     DW$CPL(R2),R0 ;Force to end of line
23 002300   010062   0000000 1$: MOV     R0,DW$COL(R2) ;Set new column number
24         ;
25         ; Finished
26         ;
27 002304   000207   RETURN

```

TCCR -- Process carriage return

```
1 .SBTTL TCCR -- Process carriage return
2 ;-----
3 ; Process carriage return, move to 1st char of current line.
4 ;
5 ; Inputs:
6 ; R2 = Pointer to window control block.
7 ;
8 002306 012762 000001 0000006 TCCR: MOV #1,DW$COL(R2) ; Say current column = 1
9 ;
10 ; Finished
11 ;
12 002314 000207 RETURN
```

TCUP --- Move cursor up specified number of lines

```

1          .SBTTL  TCUP  -- Move cursor up specified number of lines
2          ;-----
3          ; Move the cursor up the page the specified number of lines.
4          ; Do not scroll if we reach the bottom of the page.
5          ;
6          ; Inputs:
7          ; R2 = Pointer to window control block
8          ; R5 = Pointer to parameter value in control sequence
9          ;
10         002316 TCUP:
11         ;
12         ; Get count of number of lines to move up
13         ;
14         002316 004737 002116'          CALL  CSPARM          ;Accrue parameter value
15         002322 005700                  TST    R0              ;Was specified value 0?
16         002324 001001                  BNE   1$              ;Br if not
17         002326 005200                  INC   R0              ;Treat 0 like 1
18         ;
19         ; Move up specified number of lines
20         ;
21         002330 005400          1$:     NEG    R0              ;Get negative number of lines to move
22         002332 066200 0000000        ADD    DW$LIN(R2),R0    ;Compute new line
23         002336 003002                  BGT   2$              ;Br if didn't go past top of page
24         002340 012700 000001          MOV    #1,R0           ;Constrain to top of page
25         002344 026262 0000000 0000000 2$:  CMP    DW$LIN(R2),DW$SRT(R2);Were we already above top of scroll rgn?
26         002352 103400                  BLO   3$              ;Br if yes -- Don't constrain
27         002354 020062 0000000        CMP    R0,DW$SRT(R2)   ;Would this put us above top of scroll regn?
28         002360 103002                  BHIS  3$              ;Br if not
29         002362 016200 0000000        MOV    DW$SRT(R2),R0  ;Constrain to top of scroll region
30         002366 004737 006702'          3$:   CALL  SETLIN     ;Set new line for cursor
31         ;
32         ; Finished
33         ;
34         002372 000207          RETURN

```

TCDOWN -- Move cursor down specified number of lines

```

1          .SBTTL  TCDOWN -- Move cursor down specified number of lines
2          ;-----
3          ; Move the cursor down the page the specified number of lines.
4          ; Do not scroll if we reach the bottom of the page.
5          ;
6          ; Inputs:
7          ; R2 = Pointer to window control block
8          ; R5 = Pointer to parameter value in control sequence
9          ;
10         002374 TCDOWN:
11         ;
12         ; Get count of number of lines to move down
13         ;
14         002374 004737 002116'          CALL  CSPARM          ;Accrue parameter value
15         002400 005700          TST    RO          ;Was specified value 0?
16         002402 001001          BNE    1$          ;Br if not
17         002404 005200          INC    RO          ;Treat 0 like 1
18         ;
19         ; Move down specified number of lines
20         ;
21         002406 066200 0000000 1$:  ADD    DW$LIN(R2),RO  ;Compute new line
22         002412 020062 0000000      CMP    RO,DW$LPP(R2)  ;Would this go past end of page?
23         002416 101402          BLOS  3$          ;Br if not
24         002420 016200 0000000      MOV    DW$LPP(R2),RO  ;Constrain to bottom of page
25         ;
26         ; If we are currently with the scroll region, don't move out
27         ;
28         002424 026262 0000000 0000000 3$:  CMP    DW$LIN(R2),DW$SRB(R2);Were we already past end of scroll?
29         002432 101005          BHI    2$          ;Br if past end -- Don't constrain
30         002434 020062 0000000      CMP    RO,DW$SRB(R2)  ;Did we go past end of scroll region?
31         002440 101402          BLOS  2$          ;Br if not
32         002442 016200 0000000      MOV    DW$SRB(R2),RO  ;Stop at bottom of scroll region
33         002446 004737 006702'      2$:  CALL  SETLIN          ;Set new line for cursor
34         ;
35         ; Finished
36         ;
37         002452 000207          RETURN

```

TCLF --- Process Line Feed character

```

1          .SBTTL  TCLF  --- Process Line Feed character
2          ;-----
3          ; Process a line feed character.  Move down to the next line.
4          ;
5          ; Inputs:
6          ; R2 = Pointer to window control block
7          ;
8 002454   TCLF:
9          ;
10         ; If we are not at the bottom line of a scrolling region, simply
11         ; advance the line number.
12         ;
13 002454   016200   0000000   MOV     DW$LIN(R2),R0   ;Get the current line number
14 002460   020062   0000000   CMP     R0,DW$SRB(R2)  ;Are we at bottom of scrolling region?
15 002464   001411                   BEQ     1$             ;Br if yes
16 002466   005200                   INC     R0             ;Increment the line number
17 002470   020062   0000000   CMP     R0,DW$LPP(R2) ;Are we past the end of the page?
18 002474   101402                   BLOS   2$             ;Br if not
19 002476   016200   0000000   MOV     DW$LPP(R2),R0 ;Constrain to bottom of page
20 002502   004737   006702'   2$:    CALL   SETLIN   ;Set this as current line
21 002506   000402                   BR     9$
22         ;
23         ; We are at the bottom line of a scroll region.
24         ; We must scroll up one line.
25         ;
26 002510   004737   005146'   1$:    CALL   SCRLUP   ;Scroll up one line
27         ;
28         ; Finished
29         ;
30 002514   000207                   9$:    RETURN

```

TCE SCE -- Move to 1st column of next line

```
1          .SBTTL  TCE SCE -- Move to 1st column of next line
2          ;-----
3          ; Move to first column of next line.  Equivalent to carriage-return,
4          ; line-feed.
5          ;
6          ; Inputs:
7          ; R2 = Pointer to window control block.
8          ;
9 002516 004737 002306' TCE SCE: CALL  TCCR          ; Simulate carriage return
10 002522 004737 002454'      CALL  TCLF          ; Simulate line feed
11 002526 000207      RETURN
```

TCIXUP -- Index up one line

```

1          .SBTTL  TCIXUP -- Index up one line
2          ;-----
3          ; Move the cursor up one line.  Scroll the screen if we are on the top line.
4          ;
5          ; Inputs:
6          ;   R2 = Pointer to window control block
7          ;   R5 = Pointer to parameter value start in control sequence
8          ;
9          002530 TCIXUP:
10         ;
11         ; If we are not at the top line of a scrolling region,
12         ; simply decrement the line number.
13         ;
14         002530 016200 0000000  MOV     DW$LIN(R2),R0  ;Get current line number
15         002534 020062 0000000  CMP     R0,DW$SRT(R2)  ;Are we at top of scrolling region?
16         002540 001406          BEQ     1$              ;Br if yes
17         002542 005300          DEC     R0              ;Decrement line number
18         002544 003001          BGT     2$              ;Br if didn't go past line 1
19         002546 005200          INC     R0              ;Constrain to line 1
20         002550 004737 006702'  2$:    CALL   SETLIN      ;Set this as current line
21         002554 000407          BR      9$
22         ;
23         ; We are at the top line of a scroll region.
24         ; We must scroll down one line.
25         ;
26         002556 004737 005266'  1$:    CALL   SCRLDN      ;Scroll down one line
27         ;
28         ; Finished
29         ;
30         002562 000207          9$:    RETURN

```

TCRIT -- Move cursor right specified number of chars

```

1          .SBTTL  TCRIT  -- Move cursor right specified number of chars
2          ;-----
3          ; Move cursor right a specified number of characters.
4          ;
5          ; Inputs:
6          ;   R2 = Pointer to window control block
7          ;   R5 = Pointer to parameter value in control sequence
8          ;
9 002564   TCRIT:
10         ;
11         ; Get parameter value of number of chars to move
12         ;
13 002564  004737  002116'      CALL    CSPARM          ;Get parameter value
14         ;
15         ; Translate parameter value of 0 to 1
16         ;
17 002570  005700      TST     R0          ;Parameter value zero?
18 002572  001001      BNE     1$         ;Br if not
19 002574  005200      INC     R0          ;Translate to 1
20         ;
21         ; Move the cursor the specified number of columns but don't go past
22         ; right margin.
23         ;
24 002576  066200  000000G     1$:   ADD     DW$COL(R2),R0      ;Get updated cursor column
25 002602  020062  000000G     CMP     RO,DW$CPL(R2)    ;Did we go past right column?
26 002606  101402      BLOS    2$         ;Br if not
27 002610  016200  000000G     MOV     DW$CPL(R2),R0    ;Constrain to right column
28 002614  010062  000000G     2$:   MOV     RO,DW$COL(R2)    ;Set new column number
29         ;
30         ; Finished
31         ;
32 002620  000207      RETURN

```

TCLEFT -- Move cursor left specified number of chars

```

1          .SBTTL  TCLEFT -- Move cursor left specified number of chars
2          ;-----
3          ; Move cursor left a specified number of characters.
4          ;
5          ; Inputs:
6          ;   R2 = Pointer to window control block
7          ;   R5 = Pointer to parameter value in control sequence
8          ;
9 002622   TCLEFT:
10         ;
11         ; Get parameter value of number of chars to move
12         ;
13 002622  004737  002116'      CALL    CSPARM      ;Get parameter value
14         ;
15         ; Translate parameter value of 0 to 1
16         ;
17 002626  005700      TST     RO          ;Parameter value zero?
18 002630  001001      BNE     1$         ;Br if not
19 002632  005200      INC     RO          ;Translate to 1
20         ;
21         ; Move the cursor the specified number of columns but don't go past
22         ; left margin.
23         ;
24 002634  005400      1$:   NEG     RO          ;Get negative movement count
25 002636  066200  000000G      ADD     DW#COL(R2),RO  ;Get updated cursor column
26 002642  003002      BGT     2$         ;Br if didn't go past column 1
27 002644  012700  000001      MOV     #1,RO       ;Constrain to column 1
28 002650  010062  000000G      2$:   MOV     RO,DW#COL(R2) ;Set new column number
29         ;
30         ; Finished
31         ;
32 002654  000207      RETURN

```

```

1          .SBTTL  TCCADR -- Do direct cursor addressing
2          ;-----
3          ; Move cursor to a specified line and column.
4          ;
5          ; Inputs:
6          ;   R2 = Pointer to window control block.
7          ;   R5 = Pointer to parameter string within control sequence
8          ;
9 002656   TCCADR:
10         ;
11         ; Get line number parameter
12         ;
13 002656   004737   002116'       CALL    CSPARM       ;Accrue line number parameter
14 002662   005700           TST      RO           ;Translate 0 to 1
15 002664   001001           BNE      1$
16 002666   005200           INC      RO           ;Force to 1
17 002670   032762   0000000 0000000 1$:  BIT      #AW$ORS,DW$AW(R2);Is origin relative to scrolling region?
18 002676   001410           BEQ      5$           ;Br if not
19 002700   066200   0000000       ADD      DW$SRT(R2),RO   ;Bias line number by top of scrolling region
20 002704   005300           DEC      RO           ;Top line number is 1
21 002706   020062   0000000       CMP      RO,DW$SRB(R2)  ;Don't allow to go past end of scroll region
22 002712   101402           BLOS   5$           ;Br if ok
23 002714   016200   0000000       MOV      DW$SRB(R2),RO  ;Constrain to bottom of scroll region
24 002720   020062   0000000       5$:    CMP      RO,DW$LPP(R2) ;Don't go past bottom of page
25 002724   101402           BLOS   2$           ;Br if ok
26 002726   016200   0000000       MOV      DW$LPP(R2),RO  ;Constrain to bottom of page
27 002732   004737   006702'       2$:    CALL    SETLIN       ;Set new line as current line
28         ;
29         ; Get column number parameter
30         ;
31 002736   004737   002116'       CALL    CSPARM       ;Accrue column number parameter
32 002742   005700           TST      RO           ;Don't allow column 0
33 002744   001001           BNE      3$           ;Br if non zero
34 002746   005200           INC      RO           ;Translate 0 to 1
35 002750   020062   0000000       3$:    CMP      RO,DW$CPL(R2) ;Don't allow to go past right margin
36 002754   101402           BLOS   4$           ;Br if ok
37 002756   016200   0000000       MOV      DW$CPL(R2),RO  ;Constrain to right margin
38 002762   010062   0000000       4$:    MOV      RO,DW$COL(R2) ;Set new column number
39         ;
40         ; Finished
41         ;
42 002766   000207           RETURN

```

TCCPSV -- Save current cursor position

```

1          .SBTTL  TCCPSV -- Save current cursor position
2          ;-----
3          ; Save the current cursor position and character attributes.
4          ;
5          ; Inputs:
6          ; R2 = Pointer to window control block.
7          ;
8 002770   TCCPSV:
9          ;
10         ; Save cursor position
11         ;
12 002770   116262  000000G 000000G          MOVB    DW$LIN(R2),DW$SLN(R2);Save current line number
13 002776   116262  000000G 000000G          MOVB    DW$COL(R2),DW$SCL(R2);Save current column number
14         ;
15         ; Save character attributes
16         ;
17 003004   116262  000000G 000000G          MOVB    DW$CCA(R2),DW$SCA(R2);Save character attribute flags
18         ;
19         ; Finished
20         ;
21 003012   000207          RETURN
22         ;
23         .SBTTL  TCCPRS -- Restore cursor position
24         ;-----
25         ; Restore cursor position and character attributes from saved data.
26         ;
27         ; Inputs:
28         ; R2 = Pointer to window control block.
29         ;
30 003014   TCCPRS:
31         ;
32         ; Restore the column number
33         ;
34 003014   116262  000000G 000000G          MOVB    DW$SCL(R2),DW$COL(R2);Restore column number
35         ;
36         ; Restore the line number
37         ;
38 003022   116200  000000G          MOVB    DW$SLN(R2),R0    ;Get saved line number
39 003026   004737  006702'          CALL    SETLIN          ;Set as current line number
40         ;
41         ; Restore character attributes
42         ;
43 003032   116262  000000G 000000G          MOVB    DW$SCA(R2),DW$CCA(R2);Restore character attribute flags
44         ;
45         ; Finished
46         ;
47 003040   000207          RETURN

```

TCINSL -- Insert lines

```

1
2
3
4
5
6
7
8
9
10
11 003042 010146
12 003044 010346
13 003046 010446
14 003050 010546
15
16
17
18 003052 016203 0000000
19 003056 020362 0000000
20 003062 103444
21 003064 020362 0000000
22 003070 101041
23
24
25
26 003072 004737 002116'
27 003076 005700
28 003100 003002
29 003102 012700 0000001
30 003106 016201 0000000
31 003112 160301
32 003114 005201
33 003116 020100
34 003120 101413
35
36
37
38 003122 010103
39 003124 160003
40 003126 010001
41 003130 016205 0000000
42 003134 010504
43 003136 160104
44 003140 004737 006346'
45 003144 005305
46 003146 077306
47
48
49
50 003150 016203 0000000
51 003154 010300
52 003156 004737 006232'
53 003162 005203
54 003164 077105
55
56
57

```

```

.SBTTL TCINSL -- Insert lines
-----
; Insert a specified number of lines in front of the line in which
; the cursor is currently resting. The cursor is left positioned
; at column 1 of the first inserted line.
;
; Inputs:
; R2 = Pointer to window control block
; R5 = Pointer to command string argument
;
TCINSL: MOV R1, -(SP)
        MOV R3, -(SP)
        MOV R4, -(SP)
        MOV R5, -(SP)
;
; Ignore this command if we are not within the scroll region
;
        MOV DW$LIN(R2), R3 ;Get current line number
        CMP R3, DW$SRT(R2) ;Are we above top to scroll region?
        BLO 9$ ;Br if yes
        CMP R3, DW$SRB(R2) ;Are we below bottom of scroll region?
        BHI 9$ ;Br if yes
;
; Determine how many lines will be inserted
;
        CALL C$PARM ;Get command parameter
        TST R0 ;Was 0 specified?
        BGT 1$ ;Br if not
        MOV #1, R0 ;Set it to 1
1$: MOV DW$SRB(R2), R1 ;Get bottom line # of scroll region
    SUB R3, R1 ;Get # lines from current to end of region
    INC R1 ;This is max # inserted lines
    CMP R1, R0 ;Can we scroll as many as requested?
    BLOS 2$ ;Br if all lines are scrolled off
;
; Scroll down lines to make room for inserted lines
;
        MOV R1, R3 ;Get number of lines to scroll
        SUB R0, R3
        MOV R0, R1 ;Get # lines being inserted
        MOV DW$SRB(R2), R5 ;Get # of line at bottom of scroll reg
3$: MOV R5, R4
    SUB R1, R4 ;Get # of line to copy to bottom
    CALL CPY$LIN ;Copy a line down
    DEC R5 ;Get next destination line number
    SOB R3, 3$ ;Loop if more lines to scroll down
;
; Blank fill inserted lines
;
2$: MOV DW$LIN(R2), R3 ;Get top line to blank
4$: MOV R3, R0 ;Get # of line to clear
    CALL CLR$LIN ;Clear that line
    INC R3 ;Advance line number
    SOB R1, 4$ ;Loop if more lines to clear
;
; Move cursor to column 1
;

```

```
58 003166 012762 000001 0000000      MOV      #1,DW$COL(R2) ;Say cursor is at column 1
59                                     ;
60                                     ; Finished
61                                     ;
62 003174 012605      9#:      MOV      (SP)+,R5
63 003176 012604      MOV      (SP)+,R4
64 003200 012603      MOV      (SP)+,R3
65 003202 012601      MOV      (SP)+,R1
66 003204 000207      RETURN
```

TCDELL -- Delete specified number of lines

```

1          .SBTTL  TCDELL -- Delete specified number of lines
2          ;-----
3          ; Delete the specified number of lines starting with the one in which
4          ; the cursor is positioned.
5          ;
6          ; Inputs:
7          ; R2 = Pointer to window control block
8          ; R5 = Pointer to command string argument
9          ;
10         003206 010146 TCDELL: MOV     R1,-(SP)
11         003210 010346         MOV     R3,-(SP)
12         003212 010446         MOV     R4,-(SP)
13         003214 010546         MOV     R5,-(SP)
14         ;
15         ; Ignore this command if we are not within the scroll region
16         ;
17         003216 016203 0000000  MOV     DW$LIN(R2),R3 ;Get current line number
18         003222 020362 0000000  CMP     R3,DW$SRT(R2) ;Are we above top to scroll region?
19         003226 103442          BLO    9$             ;Br if yes
20         003230 020362 0000000  CMP     R3,DW$SRB(R2) ;Are we below bottom of scroll region?
21         003234 101037          BHI    9$             ;Br if yes
22         ;
23         ; Determine how many lines will be deleted
24         ;
25         003236 004737 002116'   CALL    CSPARM        ;Get command parameter
26         003242 005700          TST    R0             ;Was 0 specified?
27         003244 003002          BGT    1$             ;Br if not
28         003246 012700 0000001   MOV     #1,R0         ;Set it to 1
29         003252 016201 0000000 1$:   MOV     DW$SRB(R2),R1 ;Get bottom line # of scroll region
30         003256 160301          SUB    R3,R1         ;Get # lines from current to end of region
31         003260 005201          INC    R1            ;This is max # deleted lines
32         003262 020100          CMP    R1,R0         ;Can we delete as many as requested?
33         003264 101412          BLOS   2$             ;Br if all lines are deleted
34         ;
35         ; Scroll up the remaining lines.
36         ;
37         003266 010305          MOV    R3,R5         ;Get current line number
38         003270 010103          MOV    R1,R3         ;Get number of lines to scroll
39         003272 160003          SUB    R0,R3
40         003274 010001          MOV    R0,R1         ;Get # lines being inserted
41         003276 010504          3$:   MOV    R5,R4
42         003300 060104          ADD    R1,R4         ;Get line to copy from
43         003302 004737 006346'   CALL    CPYLIN        ;Copy a line up
44         003306 005205          INC    R5             ;Advance line number
45         003310 077306          SOB    R3,3$         ;Br if more lines to copy
46         ;
47         ; Blank fill lines at end of scrolling region
48         ;
49         003312 016203 0000000 2$:   MOV    DW$SRB(R2),R3 ;Get # of line at bottom of region
50         003316 010300          4$:   MOV    R3,R0         ;Get # of line to blank fill
51         003320 004737 006232'   CALL    CLRLIN        ;Blank the line
52         003324 077104          SOB    R1,4$         ;Loop if more lines to blank
53         ;
54         ; Say cursor is at column 1
55         ;
56         003326 012762 000001 0000000 MOV    #1,DW$COL(R2) ;Say cursor is at column 1
57         ;

```

```
58 ; Finished  
59 ;  
60 003334 012605 9#: MOV (SP)+,R5  
61 003336 012604 MOV (SP)+,R4  
62 003340 012603 MOV (SP)+,R3  
63 003342 012601 MOV (SP)+,R1  
64 003344 000207 RETURN
```

TCGOAS -- Designate GO as ascii character set

```

1          .SBTTL  TCGOAS -- Designate GO as ascii character set
2          ;-----
3          ; Designate the GO character set as ascii characters.
4          ;
5          ; Inputs:
6          ; R2 = Pointer to window control block
7          ;
8 003346 105062 0000000 TCGOAS: CLRB   DW$GOM(R2)   ;Set character set number
9 003352 000207          RETURN

```

```

10         .SBTTL  TCGODS -- Designate GO as DEC supplemental character set
11        ;-----
12        ; Designate the GO character set as DEC supplemental character set.
13        ;
14        ; Inputs:
15        ; R2 = Pointer to window control block.
16        ;
17        ;
18 003354 112762 000001 0000006 TCGODS: MOVB  #1,DW$GOM(R2) ;Set character set number
19 003362 000207          RETURN

```

```

20        .SBTTL  TCGOUK -- Designate GO as UK national character set
21        ;-----
22        ; Designate the GO character set as UK national character set.
23        ;
24        ; Inputs:
25        ; R2 = Pointer to window control block.
26        ;
27        ;
28 003364 112762 000002 0000006 TCGOUK: MOVB  #2,DW$GOM(R2) ;Set character set number
29 003372 000207          RETURN

```

```

30        .SBTTL  TCGOGR -- Designate GO as graphics character set
31        ;-----
32        ; Designate the GO character set as graphics characters.
33        ;
34        ; Inputs:
35        ; R2 = Pointer to window control block.
36        ;
37        ;
38 003374 112762 000003 0000006 TCGOGR: MOVB  #3,DW$GOM(R2) ;Set character set number
39 003402 000207          RETURN

```

TCG1AS -- Designate G1 as ascii character set

```

1          .SBTTL  TCG1AS -- Designate G1 as ascii character set
2          ;-----
3          ; Designate the G1 character set as ascii characters.
4          ;
5          ; Inputs:
6          ;   R2 = Pointer to window control block
7          ;
8 003404  105062  0000000  TCG1AS: CLRB    DW$G1M(R2)    ;Set character set number
9 003410  000207          RETURN

```

```

11         .SBTTL  TCG1DS -- Designate G1 as DEC supplemental character set
12         ;-----
13         ; Designate the G1 character set as DEC supplemental character set.
14         ;
15         ; Inputs:
16         ;   R2 = Pointer to window control block.
17         ;
18 003412  112762  000001  0000000  TCG1DS: MOVB   #1,DW$G1M(R2)  ;Set character set number
19 003420  000207          RETURN

```

```

21         .SBTTL  TCG1UK -- Designate G1 as UK national character set
22         ;-----
23         ; Designate the G1 character set as UK national character set.
24         ;
25         ; Inputs:
26         ;   R2 = Pointer to window control block.
27         ;
28 003422  112762  000002  0000000  TCG1UK: MOVB   #2,DW$G1M(R2)  ;Set character set number
29 003430  000207          RETURN

```

```

31         .SBTTL  TCG1GR -- Designate G1 as graphics character set
32         ;-----
33         ; Designate the G1 character set as graphics characters.
34         ;
35         ; Inputs:
36         ;   R2 = Pointer to window control block.
37         ;
38 003432  112762  000003  0000000  TCG1GR: MOVB   #3,DW$G1M(R2)  ;Set character set number
39 003440  000207          RETURN

```

TCG2AS -- Designate G2 as ascii character set

```

1          .SBTTL  TCG2AS -- Designate G2 as ascii character set
2          ;-----
3          ; Designate the G2 character set as ascii characters.
4          ;
5          ; Inputs:
6          ; R2 = Pointer to window control block
7          ;
8 003442 105062 000000G TCG2AS: CLRB   DW$G2M(R2)   ;Set character set number
9 003446 000207          RETURN

```

```

10         .SBTTL  TCG2DS -- Designate G2 as DEC supplemental character set
11        ;-----
12        ; Designate the G2 character set as DEC supplemental character set.
13        ;
14        ; Inputs:
15        ; R2 = Pointer to window control block.
16        ;
17        ;
18 003450 112762 000001 000000G TCG2DS: MOVB  #1,DW$G2M(R2) ;Set character set number
19 003456 000207          RETURN

```

```

20        .SBTTL  TCG2GR -- Designate G2 as graphics character set
21        ;-----
22        ; Designate the G2 character set as graphics characters.
23        ;
24        ; Inputs:
25        ; R2 = Pointer to window control block.
26        ;
27        ;
28 003460 112762 000003 000000G TCG2GR: MOVB  #3,DW$G2M(R2) ;Set character set number
29 003466 000207          RETURN

```

TCG3AS -- Designate G3 as ascii character set

```

1          .SBTTL  TCG3AS -- Designate G3 as ascii character set
2          ;-----
3          ; Designate the G3 character set as ascii characters.
4          ;
5          ; Inputs:
6          ; R2 = Pointer to window control block
7          ;
8 003470 105062 0000000 TCG3AS: CLRB    DW$G3M(R2)    ;Set character set number
9 003474 000207          RETURN

```

```

10         .SBTTL  TCG3DS -- Designate G3 as DEC supplemental character set
11         ;-----
12         ; Designate the G3 character set as DEC supplemental character set.
13         ;
14         ; Inputs:
15         ; R2 = Pointer to window control block.
16         ;
17         ;
18 003476 112762 000001 0000000 TCG3DS: MOVB   #1,DW$G3M(R2)  ;Set character set number
19 003504 000207          RETURN

```

```

20         .SBTTL  TCG3GR -- Designate G3 as graphics character set
21         ;-----
22         ; Designate the G3 character set as graphics characters.
23         ;
24         ; Inputs:
25         ; R2 = Pointer to window control block.
26         ;
27         ;
28 003506 112762 000003 0000000 TCG3GR: MOVB   #3,DW$G3M(R2)  ;Set character set number
29 003514 000207          RETURN

```

TCSO -- Shift-out character - Lock shift G1 to GL

```

1          .SBTTL  TCSO  -- Shift-out character - Lock shift G1 to GL
2          ;-----
3          ; The shift-out character is used to lock character set G1 to GL.
4          ;
5          ; Inputs:
6          ; R2 = Pointer to window control block
7          ;
8 003516  112762  000001  000000G TCSO:  MOVB   #1,DW$GLM(R2) ;Map GL to G1
9 003524  000207
10
11         .SBTTL  TCSI  -- Shift-in character - Lock shift G0 to GL
12        ;-----
13        ; The shift-in character is used to lock character set G0 to GL.
14        ;
15        ; Inputs:
16        ; R2 = Pointer to window control block.
17        ;
18 003526  105062  000000G TCSI:  CLRB   DW$GLM(R2) ;Map GL to G0
19 003532  000207
20
21        .SBTTL  TCLS2  -- Lock shift G2 to GL
22        ;-----
23        ; Set G2 as current GL character set.
24        ;
25        ; Inputs:
26        ; R2 = Pointer to window control block.
27        ;
28 003534  112762  000002  000000G TCLS2: MOVB   #2,DW$GLM(R2) ;Map GL to G2
29 003542  000207
30
31        .SBTTL  TCLS3  -- Lock shift G3 to GL
32        ;-----
33        ; Set G3 as current GL character set.
34        ;
35        ; Inputs:
36        ; R2 = Pointer to window control block.
37        ;
38 003544  112762  000003  000000G TCLS3: MOVB   #3,DW$GLM(R2) ;Map GL to G3
39 003552  000207
40
41        .SBTTL  TCLS1R -- Lock shift G1 into GR
42        ;-----
43        ; Set G1 as current GR character set.
44        ;
45        ; Inputs:
46        ; R2 = Pointer to window control block.
47        ;
48 003554  112762  000001  000000G TCLS1R: MOVB   #1,DW$GRM(R2) ;Map GR to G1
49 003562  000207
50
51        .SBTTL  TCLS2R -- Lock shift G2 into GR
52        ;-----
53        ; Set G2 as the GR character set.
54        ;
55        ; Inputs:
56        ; R2 = Pointer to window control block.
57        ;

```

58 003564 112762 000002 000000G TCLS2R: MOVB #2,DW\$GRM(R2) ;Map GR to G2
59 003572 000207 RETURN

60

61

.SBTTL TCLS3R -- Lock shift G3 into GR

62

;-----
; Set G3 as the GR character set.

63

64

65

; Inputs:

66

; R2 = Pointer to window control block.

67

68 003574 112762 000003 000000G TCLS3R: MOVB #3,DW\$GRM(R2) ;Map GR to G3

69 003602 000207

RETURN

70

71

.SBTTL TCSS2 -- Single shift G2 to GL

72

;-----
; Set G2 as GL for next character only.

73

74

75

; Inputs:

76

; R2 = Pointer to window control block.

77

78 003604 112762 000002 000000G TCSS2: MOVB #2,DW\$GLS(R2) ;Map GL to G2 for next character only

79 003612 052762 000000G 000000G

BIS #AW\$SS,DW\$AW(R2);Remember single shift is pending

80 003620 000207

RETURN

81

82

.SBTTL TCSS3 -- Single shift G3 to GL

83

;-----
; Set G3 as GL for next character only.

84

85

86

; Inputs:

87

; R2 = Pointer to window control block.

88

89 003622 112762 000003 000000G TCSS3: MOVB #3,DW\$GLS(R2) ;Map GL to G3 for next character only

90 003630 052762 000000G 000000G

BIS #AW\$SS,DW\$AW(R2);Remember single shift is pending

91 003636 000207

RETURN

TCSAA -- Set ANSI attribute

```

1          .SBTTL  TCSAA  -- Set ANSI attribute
2          ;-----
3          ; Set an ANSI terminal attribute.
4          ;
5          ; Inputs:
6          ;   R2 = Pointer to window control block
7          ;   R5 = Pointer to parameter values
8          ;
9 003640   010346   TCSAA:  MOV     R3,-(SP)
10 003642   012703   004112'   MOV     #ASATAT,R3      ;Point to ANSI conversion table
11 003646   004737   003730'   CALL    TCSTA          ;Go set the attribute
12 003652   012603   MOV     (SP)+,R3
13 003654   000207   RETURN
14
15          .SBTTL  TCRAA  -- Reset ANSI attribute
16          ;-----
17          ; Reset an ANSI terminal attribute.
18          ;
19          ; Inputs:
20          ;   R2 = Pointer to window control block
21          ;   R5 = Pointer to parameter values
22          ;
23 003656   010346   TCRAA:  MOV     R3,-(SP)
24 003660   012703   004112'   MOV     #ASATAT,R3      ;Point to ANSI conversion table
25 003664   004737   003766'   CALL    TCRTA          ;Reset the attribute
26 003670   012603   MOV     (SP)+,R3
27 003672   000207   RETURN
28
29          .SBTTL  TCSDA  -- Set DEC attribute
30          ;-----
31          ; Set a DEC terminal attribute
32          ;
33          ; Inputs:
34          ;   R2 = Pointer to window control block
35          ;   R5 = Pointer to parameter values
36          ;
37 003674   010346   TCSDA:  MOV     R3,-(SP)
38 003676   012703   004120'   MOV     #DECTAT,R3      ;Point to DEC conversion table
39 003702   004737   003730'   CALL    TCSTA          ;Set the attribute
40 003706   012603   MOV     (SP)+,R3
41 003710   000207   RETURN
42
43          .SBTTL  TCRDA  -- Reset DEC attribute
44          ;-----
45          ; Reset a DEC terminal attribute
46          ;
47          ; Inputs:
48          ;   R2 = Pointer to window control block
49          ;   R5 = Pointer to parameter values
50          ;
51 003712   010346   TCRDA:  MOV     R3,-(SP)
52 003714   012703   004120'   MOV     #DECTAT,R3      ;Point to DEC conversion table
53 003720   004737   003766'   CALL    TCRTA          ;Reset the attribute
54 003724   012603   MOV     (SP)+,R3
55 003726   000207   RETURN

```

TCSTA -- Set terminal attribute

```

1          .SBTTL  TCSTA  -- Set terminal attribute
2          ;-----
3          ; Set a terminal attribute
4          ;
5          ; Inputs:
6          ; R2 = Pointer to window control block
7          ; R3 = Pointer to table to convert attribute value to flag bit
8          ; R5 = Pointer to parameter values
9          ;
10         003730  010446  TCSTA:  MOV      R4, -(SP)
11         ;
12         ; Begin loop to accrue attribute parameters until end of string hit
13         ;
14         003732  004737  002116' 1$:    CALL    CSPARM      ;Accrue next parameter value
15         003736  103411          BCS     9$             ;Br if no more parameter values
16         ;
17         ; Convert parameter value into flag mask
18         ;
19         003740  010004          MOV     RO,R4          ;Save parameter value
20         003742  004737  004060'  CALL    CVTTAV        ;Convert parameter value into flag mask
21         003746  103771          BCS     1$             ;Br if parameter not recognized
22         ;
23         ; Set appropriate flag bit
24         ;
25         003750  050062  0000000  BIS     RO,DW$AW(R2)  ;Set appropriate attribute flag
26         ;
27         ; See if this change requires doing more than setting a flag bit
28         ;
29         003754  004737  004152'  CALL    CKTAC         ;Check for additional changes
30         ;
31         ; See if there are more attributes to set
32         ;
33         003760  000764          BR     1$
34         ;
35         ; Finished
36         ;
37         003762  012604  9$:    MOV     (SP)+,R4
38         003764  000207          RETURN

```

TCRTA -- Reset terminal attribute

```

1          .SBTTL  TCRTA  -- Reset terminal attribute
2          ;-----
3          ; Reset a terminal attribute
4          ;
5          ; Inputs:
6          ; R2 = Pointer to window control block
7          ; R3 = Pointer to table to convert attribute value to flag bit
8          ; R5 = Pointer to parameter values
9          ;
10         003766  010446  TCRTA:  MOV      R4,-(SP)
11         ;
12         ; Begin loop to accrue attribute parameters until end of string hit
13         ;
14         003770  004737  002116'  1$:    CALL    CSPARM      ;Accrue next parameter value
15         003774  103427          BCS     9$           ;Br if no more parameters
16         ;
17         ; Check for special parameter value 2 which means select VT52 mode
18         ;
19         003776  020027  000002          CMP     R0,#2        ;Select VT52 mode?
20         004002  001013          BNE     2$           ;Br if not
21         004004  052762  0000000 0000000  BIS     #AW$S52,DW$AW(R2);Enable VT52 simulation mode for window
22         004012  116204  0000000          MOVB   DW$JOB(R2),R4  ;Get out job index number
23         004016  116404  0000000          MOVB   LNPRIM(R4),R4 ;Get our primary job #
24         004022  052764  0000000 0000000  BIS     #$V52EM,LSW11(R4);Say we are emulating a VT52
25         004030  000757          BR     1$
26         ;
27         ; Convert parameter value into flag mask
28         ;
29         004032  010004  2$:    MOV     R0,R4      ;Save parameter value
30         004034  004737  004060'  CALL    CVTTAV      ;Convert parameter value into flag mask
31         004040  103753          BCS     1$           ;Br if parameter value not recognized
32         ;
33         ; Reset appropriate flag bit
34         ;
35         004042  040062  0000000          BIC     R0,DW$AW(R2) ;Reset appropriate attribute flag
36         ;
37         ; See if this change requires doing more than clearing a bit
38         ;
39         004046  004737  004152'          CALL    CKTAC      ;Check for special mode changes
40         ;
41         ; See if there are more attributes to reset
42         ;
43         004052  000746          BR     1$
44         ;
45         ; Finished
46         ;
47         004054  012603  9$:    MOV     (SP)+,R3
48         004056  000207          RETURN

```

CVTTAV -- Convert terminal attribute value to flag

```

1          .SBTTL  CVTTAV -- Convert terminal attribute value to flag
2          ;-----
3          ; Convert a terminal attribute parameter value into a flag mask.
4          ;
5          ; Inputs:
6          ;   RO = Attribute value
7          ;   R3 = Pointer to table to convert attribute value to flag bit
8          ;
9          ; Outputs:
10         ;   C-flag set ==> Attribute value not recognized
11         ;   RO = Flag mask if attribute value recognized
12         ;
13 004060  010346  CVTTAV: MOV     R3, -(SP)
14         ;
15         ; See if we can find attribute value in table
16         ;
17 004062  020023  1$:      CMP     RO, (R3)+      ; Is next entry for our value?
18 004064  001406          BEQ     2$              ; Br if yes
19 004066  005723          TST     (R3)+      ; Skip over flag mask
20 004070  005713          TST     (R3)        ; Is there another entry in table?
21 004072  001373          BNE     1$              ; Br if yes
22         ;
23         ; Attribute value is not in table
24         ;
25 004074  005000          CLR     RO              ; Return no flag mask
26 004076  000261          SEC              ; Signal failure on return
27 004100  000402          BR     9$
28         ;
29         ; We found the attribute in the table
30         ;
31 004102  011300  2$:      MOV     (R3), RO      ; Get the flag mask
32 004104  000241          CLC              ; Signal success on return
33         ;
34         ; Finished
35         ;
36 004106  012603  9$:      MOV     (SP)+, R3
37 004110  000207          RETURN
38         ;-----
39         ;
40         ; Table to relate ANSI attribute values with flag masks
41         ;
42 004112  000004  0000006  ASATAT: .WORD  4, AW$INS      ; Insert mode
43 004116  000000          .WORD  0
44         ;
45         ; Table to relate DEC attribute values with flag masks
46         ;
47 004120  000001  0000006  DECTAT: .WORD  1, AW$ACK      ; Application mode for cursor keys
48 004124  000003  0000006          .WORD  3, AW$132      ; 132 column mode
49 004130  000005  0000006          .WORD  5, AW$REV      ; Reverse video
50 004134  000006  0000006          .WORD  6, AW$ORS      ; Origin relative to scroll region
51 004140  000010  0000006          .WORD  8, AW$RPT      ; Automatic keypad repeat
52 004144  000031  0000006          .WORD 25, AW$VCR      ; Make cursor visible
53 004150  000000          .WORD  0              ; End of table

```

CKTAC -- Check for complex mode changes

```

1          .SBTTL  CKTAC  -- Check for complex mode changes
2          ;-----
3          ; This routine is called each time a terminal attribute changes to see
4          ; if we must do things other than setting or clearing an attribute flag.
5          ;
6          ; Inputs:
7          ; R2 = Pointer to window control block
8          ; R4 = Parameter value specified with attribute change command.
9          ;
10 004152  CKTAC:
11          ;
12          ; If we just changed the origin mode, home the cursor
13          ;
14 004152  020427  000006          CMP     R4,#6          ;Change origin mode?
15 004156  001003          BNE     1$          ;Br if not
16 004160  004737  005110'       CALL   SETHOM        ;Say cursor has moved to home
17 004164  000415          BR     9$
18          ;
19          ; If we just changed line width (80/132 mode), clear the screen,
20          ; set scrolling region to full screen, and home the cursor.
21          ;
22 004166  020427  000003  1$:   CMP     R4,#3          ;Change line width?
23 004172  001012          BNE     9$          ;Br if not
24 004174  012762  000001  000000G  MOV     #1,DW$SRT(R2) ;Set top scroll line to 1
25 004202  016262  000000G  000000G  MOV     DW$LPP(R2),DW$SRB(R2) ;Set bottom scroll line to end of page
26 004210  004737  005110'       CALL   SETHOM        ;Set cursor to home position
27 004214  004737  006210'       CALL   ERSPA0        ;Erase the entire page
28          ;
29          ; Finished
30          ;
31 004220  000207  9$:   RETURN

```

TCAKM -- Select application keypad mode

```
1 .SBTTL TCAKM -- Select application keypad mode
2 ;-----
3 ; Select application keypad mode
4 ;
5 ; Inputs:
6 ; R2 = Pointer to window control block
7 ;
8 004222 052762 000000G 000000G TCAKM: BIS #AW$AKM,DW$AW(R2);Say we are in application keypad mode
9 004230 000207 RETURN
```

```
10
11 .SBTTL TCNKM -- Select numeric keypad mode
12 ;-----
13 ; Select numeric keypad mode
14 ;
15 ; Inputs:
16 ; R2 = Pointer to window control block
17 ;
18 004232 042762 000000G 000000G TCNKM: BIC #AW$AKM,DW$AW(R2);Reset application keypad mode
19 004240 000207 RETURN
```

TCN3 -- Set line attributes

```

1          .SBTTL  TCN3  -- Set line attributes
2          ;-----
3          ; Set attributes for the current line.
4          ;
5          ; Inputs:
6          ;   R2 = Pointer to window control block
7          ;
8          ; Line is top half of double-high line
9          ;
10         004242 004737 006612' TCN3:  CALL  GETLAB      ;Get current line attribute flags
11         004246 042700 0000000  BIC   #AL#DHB,RO  ;Clear double-high-bottom flag
12         004252 052700 0000000  BIS   #AL#DHT,RO  ;Set double-high-top flag
13         004256 004737 006522'  CALL  SETLAB      ;Store new attribute flags for line
14         004262 000207          RETURN
15         ;
16         ; Line is bottom half of double-high line
17         ;
18         004264 004737 006612' TCN4:  CALL  GETLAB      ;Get current line attribute flags
19         004270 042700 0000000  BIC   #AL#DHT,RO  ;Clear double-high-top flag
20         004274 052700 0000000  BIS   #AL#DHB,RO  ;Set double-high-bottom flag
21         004300 004737 006522'  CALL  SETLAB      ;Store new attribute flags for line
22         004304 000207          RETURN
23         ;
24         ; Line is single width
25         ;
26         004306 004737 006612' TCN5:  CALL  GETLAB      ;Get current line attribute flags
27         004312 042700 0000000  BIC   #AL#DWD,RO  ;Clear double-wide attribute
28         004316 004737 006522'  CALL  SETLAB      ;Store new attribute flags for line
29         004322 000207          RETURN
30         ;
31         ; Line is double width
32         ;
33         004324 004737 006612' TCN6:  CALL  GETLAB      ;Get current line attribute flags
34         004330 052700 0000000  BIS   #AL#DWD,RO  ;Set double-wide flag
35         004334 004737 006522'  CALL  SETLAB      ;Store new attribute flags for line
36         004340 000207          RETURN

```

TCSCA -- Set character attributes

```

1          .SBTTL  TCSCA  -- Set character attributes
2          ;-----
3          ; Specify attributes for characters that follow
4          ;
5          ; Inputs:
6          ; R2 = Pointer to window control block
7          ; R5 = Pointer to start of parameter values
8          ;
9 004342  010346  TCSCA:  MOV      R3, -(SP)
10         ;
11         ; If no parameters were specified, reset all character attributes
12         ;
13 004344  121527  000155          CMPB   (R5), #'m      ;Any attributes specified?
14 004350  001004          BNE    1$           ;Br if yes
15 004352  142762  000000C 000000G  BICB  #<AC$BLD!AC$BLK!AC$REV!AC$ULN>, DW$CCA(R2); Clear all attributes
16 004360  000422          BR     9$           ;Finished
17         ;
18         ; Begin loop to accrue and process each parameter
19         ;
20 004362  004737  002116'  1$:    CALL   CSPARM      ;Accrue next parameter value
21 004366  103417          BCS    9$           ;Br if no more parameter values
22         ;
23         ; Look up parameter value to determine which attribute flags
24         ; are to be set and reset.
25         ;
26 004370  012703  004432'          MOV    #CATABL, R3    ;Point to attribute table
27 004374  120023  2$:    CMPB   R0, (R3)+   ;Search for parameter value in table
28 004376  001406          BEQ    3$           ;Br if found it
29 004400  062703  000002          ADD   #2, R3        ;Skip over flag bytes
30 004404  020327  004465'          CMP   R3, #CATEND   ;Reached end of table?
31 004410  103771          BLD   2$           ;Keep looking if not
32 004412  000763          BR    1$           ;Cannot find this parameter value
33         ;
34         ; Found parameter value in table.
35         ; Set and reset some flags
36         ;
37 004414  152362  000000G  3$:    BISB   (R3)+, DW$CCA(R2); Set some attributes
38 004420  142362  000000G          BICB   (R3)+, DW$CCA(R2); Reset some attributes
39 004424  000756          BR    1$           ;Process any other attributes
40         ;
41         ; Finished
42         ;
43 004426  012603  9$:    MOV    (SP)+, R3
44 004430  000207          RETURN

```

TCSCA -- Set character attributes

```

1
2 ; -----
3 ; Table to convert attribute parameter values into flags to be
4 ; set and reset.
5 ; Each entry has three values: (1) numeric parameter value that
6 ; occurs in control sequence; (2) flags to be set; (3) flags to
7 ; be reset.
8 004432      000      000      000C CATABL: .BYTE 0.,0,AC$BLD!AC$BLK!AC$REV!AC$ULN
9 004435      001      000G      000      .BYTE 1.,AC$BLD,0
10 004440     004      000G      000      .BYTE 4.,AC$ULN,0
11 004443     005      000G      000      .BYTE 5.,AC$BLK,0
12 004446     007      000G      000      .BYTE 7.,AC$REV,0
13 004451     026      000      000G      .BYTE 22.,0,AC$BLD
14 004454     030      000      000G      .BYTE 24.,0,AC$ULN
15 004457     031      000      000G      .BYTE 25.,0,AC$BLK
16 004462     033      000      000G      .BYTE 27.,0,AC$REV
17 004465
18 CATEND: .EVEN

```

TC100 -- Select VT100/VT200 mode

```

1          .SBTTL  TC100  -- Select VT100/VT200 mode
2          ;-----
3          ; Set terminal to VT100 or VT200 mode of operation
4          ;
5          ; Inputs:
6          ;   R2 = Pointer to window control block
7          ;   R5 = Pointer to parameter values
8          ;
9 004466   TC100:
10         ;
11         ; Say terminal is not in VT52 mode and not in VT200 mode
12         ; (i.e., set to VT100 mode)
13         ;
14 004466   042762  000000C 000000G      BIC      #<AW$52!AW$552!AW$200>,DW$AW(R2) ;Terminal is in VT100 mode
15         ;
16         ; Reset VT52 emulation-mode flag in entry for primary line so that
17         ; other windows connected to this terminal will know.
18         ;
19 004474   116200  000000G      MOVVB   DW$JOB(R2),R0   ;Get our line index number
20 004500   116000  000000G      MOVVB   LNPRIM(R0),R0  ;Get number of primary line
21 004504   042760  000000G 000000G      BIC      #$V52EM,LSW11(R0) ;Say terminal not emulating a VT52
22         ;
23         ; If job's terminal type is VT200, set that mode
24         ;
25 004512   116200  000000G      MOVVB   DW$JOB(R2),R0   ;Get job index number
26 004516   032760  000000C 000000G      BIT      #<VT2007!VT2008>,LTRMTP(R0);Is terminal a VT200?
27 004524   001005          BNE      1$              ;Br if yes
28         ;
29         ; Get 1st parameter value and see if we should go to VT200 mode
30         ;
31 004526   004737  002116'      CALL    CSPARM          ;Accrue 1st parameter value
32 004532   020027  000076          CMP     R0,#62.         ;VT200 mode?
33 004536   001003          BNE     9$              ;Br if not
34         ;
35         ; Set terminal type to VT200
36         ;
37 004540   052762  000000G 000000G 1$:   BIS     #AW$200,DW$AW(R2);Set VT200 mode
38         ;
39         ; Finished
40         ;
41 004546   000207 9$:   RETURN

```

TCREST -- Terminal reset

```

1          .SBTTL  TCREST -- Terminal reset
2          ;-----
3          ; Perform a terminal reset operation
4          ;
5          ; Inputs:
6          ;   R2 = Pointer to window control block
7          ;
8 004550 010146  TCREST: MOV     R1, -(SP)
9          ;
10         ; Turn off VT52 emulation mode
11         ;
12 004552 042762 0000000 0000000      BIC     #AW$S52, DW$AW(R2); Turn off attribute for window
13 004560 116201 0000000      MOV     DW$JOB(R2), R1 ; Get our job index number
14 004564 116100 0000000      MOV     LNPRIM(R1), R0 ; Get primary line number
15 004570 042760 0000000 0000000      BIC     #V52EM, LSW11(R0) ; Say terminal is not in VT52 mode
16         ;
17         ; Reset scrolling region
18         ;
19 004576 012762 0000001 0000000      MOV     #1, DW$SRT(R2) ; Set top scroll line to 1
20 004604 016262 0000000 0000000      MOV     DW$LPP(R2), DW$SRB(R2) ; Set bottom scroll line to end of page
21         ;
22         ; Reset misc window status flags
23         ;
24 004612 042762 0000000C 0000000G    BIC     #<AW$132!AW$INS!AW$ACK!AW$ORS!AW$AKM!AW$SS!AW$PRT>, DW$AW(R2)
25         ;
26         ; Say cursor is at home
27         ;
28 004620 004737 005110'      CALL    SETHOM          ; Set cursor to home position
29         ;
30         ; Erase the entire page
31         ;
32 004624 004737 006210'      CALL    ERSPAG         ; Erase the entire page
33         ;
34         ; Reset character set mapping for a VT200
35         ;
36 004630 032761 0000000C 0000000G    BIT     #<VT2007!VT200B>, LTRMTP(R1) ; Is this a VT200?
37 004636 001411      BEQ     9$              ; Br if not
38 004640 112762 0000001 0000000G    MOV     #1, DW$G2M(R2) ; Map G2 to DEC supplemental chars
39 004646 112762 0000001 0000000G    MOV     #1, DW$G3M(R2) ; Map G3 to DEC supplemental chars
40 004654 112762 0000002 0000000G    MOV     #2, DW$GRM(R2) ; Map GR to G2
41         ;
42         ; Finished
43         ;
44 004662 012601 9$:      MOV     (SP)+, R1
45 004664 000207      RETURN

```

```
1 .SBTTL TCPRT -- Printer control operation
2 -----
3 ; Direct output to printer or back to terminal.
4 ;
5 ; Inputs:
6 ; R2 = Pointer to window control block
7 ; R5 = Pointer to start of parameter value
8 ;
9 004666 TCPRT:
10 ;
11 ; Get first parameter value and see if we should direct output to printer
12 ; or to terminal.
13 ;
14 004666 004737 002116' CALL CSPARM ;Get first parameter value
15 004672 020027 000005 CMP R0,#5 ;Direct output to printer?
16 004676 001004 BNE 1$ ;Br if not
17 004700 052762 0000000 0000000 BIS #AW#PRT,DW$AW(R2);Direct output to printer
18 004706 000406 BR 9$
19 004710 020027 000004 1$: CMP R0,#4 ;Direct output to terminal?
20 004714 001003 BNE 9$ ;Br if not
21 004716 042762 0000000 0000000 BIC #AW#PRT,DW$AW(R2);Direct output to terminal
22 ;
23 ; Finished
24 ;
25 004724 000207 9$: RETURN
```

TCLERS -- Erase within a line

```

1          .SBTTL  TCLERS -- Erase within a line
2          ;-----
3          ; Erase within a line.
4          ;
5          ; Inputs:
6          ; R2 = Pointer to window control block
7          ; R5 = Pointer to start of parameter value
8          ;
9 004726   TCLERS:
10         ;
11         ; Accrue parameter value to determine what type of erase this is
12         ;
13 004726  004737  002116'      CALL  CSPARM      ;Accrue parameter value
14 004732  005700              TST    R0          ;Parameter = 0?
15 004734  001003              BNE    1$         ;Br if not
16 004736  004737  005632'      CALL  ERSCTL      ;Erase from cursor to end of line
17 004742  000413              BR     9$
18 004744  020027  000001      1$:  CMP    R0,#1      ;Parameter = 1?
19 004750  001003              BNE    2$         ;Br if not
20 004752  004737  005744'      CALL  ERSLTC      ;Erase from beginning of line to cursor
21 004756  000405              BR     9$
22 004760  020027  000002      2$:  CMP    R0,#2      ;Parameter = 2?
23 004764  001002              BNE    9$         ;Br if not
24 004766  004737  005546'      CALL  ERSLIN      ;Erase entire line
25         ;
26         ; Finished
27         ;
28 004772  000207      9$:  RETURN

```

TCPERS -- Erase within a page

```

1          .SBTTL  TCPERS -- Erase within a page
2          ;-----
3          ; Erase characters within the current page.
4          ;
5          ; Inputs:
6          ; R2 = Pointer to window control block
7          ; R5 = Pointer to start of parameter value
8          ;
9 004774   TCPERS:
10         ;
11         ; Accrue parameter value and determine how much to erase
12         ;
13 004774   004737   002116'       CALL    CSPARM       ;Accrue parameter
14 005000   005700       TST      R0           ;Parameter = 0?
15 005002   001003       BNE      1$         ;Br if not
16 005004   004737   006030'       CALL    ERSCTP       ;Erase from cursor to end of page
17 005010   000413       BR       9$
18 005012   020027   000001   1$:   CMP      R0,#1       ;Parameter = 1?
19 005016   001003       BNE      2$         ;Br if not
20 005020   004737   006112'       CALL    ERSPTC       ;Erase from beginning of page to cursor
21 005024   000405       BR       9$
22 005026   020027   000002   2$:   CMP      R0,#2       ;Parameter = 2?
23 005032   001002       BNE      9$         ;Br if not
24 005034   004737   006210'       CALL    ERSPAG       ;Erase entire page
25         ;
26         ; Finished
27         ;
28 005040   000207       9$:   RETURN

```

TCSSR -- Set scrolling region

```

1          .SBTTL  TCSSR  -- Set scrolling region
2          ;-----
3          ; Set the scrolling region.
4          ;
5          ; Inputs:
6          ; R2 = Pointer to window control block
7          ; R5 = Pointer to parameter values
8          ;
9 005042   TCSSR:
10         ;
11         ; Accrue scrolling region top value
12         ;
13 005042   004737   002116'   CALL    CSPARM      ; Accrue scrolling region top line
14 005046   005700           TST     RO              ; Was top line number specified?
15 005050   001002           BNE     1$              ; Br if yes
16 005052   012700   000001   MOV     #1,RO      ; Set 1 as top line
17 005056   010062   0000000 1$:    MOV     RO,DW$SRT(R2) ; Set top line of scrolling region
18         ;
19         ; Accrue scrolling region bottom value
20         ;
21 005062   004737   002116'   CALL    CSPARM      ; Accrue scrolling region bottom line
22 005066   005700           TST     RO              ; Was bottom line specified?
23 005070   001002           BNE     2$              ; Br if yes
24 005072   016200   0000000  MOV     DW$LPP(R2),RO ; Set last line as bottom of region
25 005076   010062   0000000 2$:    MOV     RO,DW$SRB(R2) ; Set bottom line of scrolling region
26         ;
27         ; Set the cursor to the home position
28         ;
29 005102   004737   005110'   CALL    SETHOM      ; Set cursor to home position
30         ;
31         ; Finished
32         ;
33 005106   000207           RETURN

```

SETHOM -- Set cursor to the home position

```

1          .SBTTL  SETHOM -- Set cursor to the home position
2          ;-----
3          ; This routine is called to set the current cursor position to
4          ; home.  The home line depends on whether absolute or relative
5          ; origin has been selected.
6          ;
7          ; Inputs:
8          ;   R2 = Pointer to window control block.
9          ;
10         SETHOM:
11         ;
12         ; Set the cursor line number.
13         ; See if absolute or relative origin has been selected.
14         ;
15         005110 032762 000000G 000000G      BIT    #AW#ORS,DW#AW(R2); Is origin relative to scroll region?
16         005116 001403                    BEQ    1$          ; Br if not
17         005120 016200 000000G            MOV    DW#SRT(R2),RO  ; Say cursor is at top of scroll reg
18         005124 000402                    BR     2$
19         005126 012700 000001             1$:  MOV    #1,RO          ; Say cursor is at line 1
20         005132 004737 006702'           2$:  CALL   SETLIN        ; Set the line number
21         ;
22         ; Set column to 1
23         ;
24         005136 012762 000001 000000G      MOV    #1,DW#COL(R2)  ; Say cursor is at column 1
25         ;
26         ; Finished
27         ;
28         005144 000207                    RETURN

```

SCRLUP -- Scroll screen up one line

```

1          .SBTTL  SCRLUP -- Scroll screen up one line
2          ;-----
3          ; Scroll the screen up one line.
4          ;
5          ; Inputs:
6          ; R2 = Pointer to window control block.
7          ;
8 005146 010346 SCRLUP: MOV     R3,-(SP)
9 005150 010446      MOV     R4,-(SP)
10 005152 010546      MOV     R5,-(SP)
11          ;
12          ; See if we are allowed to scroll any more lines
13          ;
14 005154 012700 000001      MOV     #1,R0          ;We are scrolling up one line
15 005160 004737 005414'    CALL    SCRCHK          ;See if scrolling allowed
16          ;
17          ; If the scrolling region is the entire screen, we can do the scrolling
18          ; by simply changing the number of the top line.
19          ;
20 005164 026227 000000G 000001      CMP     DW$SRT(R2),#1    ;Top line of scrolling region = 1?
21 005172 001013          BNE     2$              ;Br if not
22 005174 026262 000000G 000000G    CMP     DW$SRB(R2),DW$LPP(R2);Scrolling region go to bottom of page?
23 005202 001007          BNE     2$              ;Br if not
24          ;
25          ; Scrolling region covers the entire page
26          ;
27 005204 005362 000000G          DEC     DW$TLN(R2)      ;Change top line number
28 005210 003016          BGT     1$              ;Br if did not just scroll line 1
29 005212 016262 000000G 000000G    MOV     DW$LPP(R2),DW$TLN(R2);Cycle to last line on page
30 005220 000412          BR      1$
31          ;
32          ; The scrolling region does not cover the entire page.
33          ; Move characters from line to line to do the scrolling.
34          ;
35 005222 016203 000000G    2$:    MOV     DW$SRT(R2),R3  ;Get top line # of scrolling region
36 005226 010305    3$:    MOV     R3,R5          ;Set number of line to copy to
37 005230 005203          INC     R3
38 005232 010304          MOV     R3,R4          ;Set number of line to copy from
39 005234 004737 006346'    CALL    CPYLIN          ;Copy characters from one line to another
40 005240 020362 000000G          CMP     R3,DW$SRB(R2)   ;Have we copied all that is needed?
41 005244 103770          BLD     3$              ;Loop if not
42          ;
43          ; Clear the line at the bottom of the scrolling region
44          ;
45 005246 016200 000000G    1$:    MOV     DW$SRB(R2),R0  ;Get # of line at bottom of scrolling regn
46 005252 004737 006232'    CALL    CLRLIN          ;Clear that line
47          ;
48          ; Finished
49          ;
50 005256 012605          MOV     (SP)+,R5
51 005260 012604          MOV     (SP)+,R4
52 005262 012603          MOV     (SP)+,R3
53 005264 000207          RETURN

```

SCRLDN -- Scroll screen down one line

```

1          .SBTTL  SCRLDN -- Scroll screen down one line
2          ;-----
3          ; Scroll the screen down one line.
4          ;
5          ; Inputs:
6          ; R2 = Pointer to window control block.
7          ;
8 005266 010346 SCRLDN: MOV     R3,-(SP)
9 005270 010446      MOV     R4,-(SP)
10 005272 010546      MOV     R5,-(SP)
11         ;
12         ; See if we are allowed to scroll any more lines
13         ;
14 005274 012700 177777      MOV     #-1,R0      ;Say we are scrolling down one line
15 005300 004737 005414'    CALL    SCRCHK      ;See if we are allowed to scroll more
16         ;
17         ; If the scrolling region is the entire screen, we can do the scrolling
18         ; by simply changing the number of the top line.
19         ;
20 005304 026227 0000000 000001      CMP     DW$SRT(R2),#1 ;Top line of scrolling region = 1?
21 005312 001016      BNE     2$          ;Br if not
22 005314 026262 0000000 0000000    CMP     DW$SRB(R2),DW$LPP(R2);Scrolling region go to bottom of page?
23 005322 001012      BNE     2$          ;Br if not
24         ;
25         ; Scrolling region covers the entire page
26         ;
27 005324 005262 0000000      INC     DW$TLN(R2)    ;Change top line number
28 005330 026262 0000000 0000000    CMP     DW$TLN(R2),DW$LPP(R2);Did we just scroll last line?
29 005336 101416      BLOS   1$          ;Br if not
30 005340 012762 000001 0000000    MOV     #1,DW$TLN(R2) ;Cycle back to line 1
31 005346 000412      BR     1$
32         ;
33         ; The scrolling region does not cover the entire page.
34         ; Move characters from line to line to do the scrolling.
35         ;
36 005350 016203 0000000    2$:    MOV     DW$SRB(R2),R3 ;Get bottom line # of scrolling region
37 005354 010305    3$:    MOV     R3,R5      ;Set number of line to copy to
38 005356 005303      DEC     R3
39 005360 010304      MOV     R3,R4      ;Set number of line to copy from
40 005362 004737 006346'    CALL    CPYLIN     ;Copy characters from one line to another
41 005366 020362 0000000    CMP     R3,DW$SRT(R2) ;Have we copied all that is needed?
42 005372 101370      BHI    3$          ;Loop if not
43         ;
44         ; Clear the line at the top of the scrolling region
45         ;
46 005374 016200 0000000    1$:    MOV     DW$SRT(R2),R0 ;Get # of line at top of scrolling regn
47 005400 004737 006232'    CALL    CLRLIN     ;Clear that line
48         ;
49         ; Finished
50         ;
51 005404 012605      MOV     (SP)+,R5
52 005406 012604      MOV     (SP)+,R4
53 005410 012603      MOV     (SP)+,R3
54 005412 000207      RETURN

```

```

1          .SBTTL  SCRCHK -- Check for scrolling limits
2          ;-----
3          ; Determine if we are allowed to scroll the screen any further while the
4          ; job is detached from the terminal.  If we have reached the limit of
5          ; our scrolling, the job is suspended until the terminal is reconnected.
6          ;
7          ; Inputs:
8          ; R0 = +1 if scrolling up, -1 if scrolling down.
9          ; R2 = Pointer to window control block.
10         ;
11 005414 010146 SCRCHK: MOV     R1,-(SP)
12         ;
13         ; See if job is currently attached to terminal
14         ;
15 005416 032762 0000000 0000000 BIT     #AW$DDC,DW$AW(R2);Are we suppressing char display?
16 005424 001426 BEQ     9$           ;Br if not
17 005426 116201 0000000 MOV     DW$JOB(R2),R1 ;Get number of job
18 005432 032761 0000000 0000000 BIT     #$VNOTT,LSW(R1);Is job currently connected to terminal?
19 005440 001420 BEQ     9$           ;Br if yes
20         ;
21         ; Job is not currently attached to the terminal.
22         ; See if we are allowed to scroll an unlimited number of lines.
23         ;
24 005442 116201 0000000 MOV     DW$MSL(R2),R1 ;Are we allowed to scroll unlimited # lines?
25 005446 002415 BLT     9$           ;Br if yes
26 005450 001412 BEQ     2$           ;Br if no scrolling is allowed
27         ;
28         ; See if this scroll would exceed limit.
29         ;
30 005452 116201 0000000 MOV     DW$NSL(R2),R1 ;Get # lines scrolled so far
31 005456 060001 ADD     R0,R1         ;Add number scrolled this time
32 005460 110162 0000000 MOV     R1,DW$NSL(R2);Save new total
33 005464 002001 BGE     1$           ;Br if total is positive
34 005466 005401 NEG     R1            ;Get positive line count
35 005470 120162 0000000 1$: CMP     R1,DW$MSL(R2);Would this exceed max allowed scroll?
36 005474 101402 BLOS   9$           ;Br if not
37         ;
38         ; Suspend job until job reattaches to the terminal
39         ;
40 005476 004737 005506' 2$: CALL   WINSFN      ;Suspend job
41         ;
42         ; Finished
43         ;
44 005502 012601 9$: MOV     (SP)+,R1
45 005504 000207 RETURN

```

WINSPN -- Suspend job until it reattaches to terminal

```

1          .SBTTL  WINSPN -- Suspend job until it reattaches to terminal
2          ;-----
3          ; Suspend the execution of a job until it reattaches to a terminal.
4          ;
5          ; Inputs:
6          ; R2 = Pointer to window control block
7          ;
8 005506 010146 WINSPN: MOV     R1,-(SP)
9          ;
10         ; Never suspend if we are running at fork level (doing character echoing)
11         ;
12 005510 105737 0000000  TSTB   FRKPRI      ;Are we running at fork level?
13 005514 001012          BNE    9$          ;Br if yes
14         ;
15         ; See if job has reattached to the terminal
16         ;
17 005516 116201 0000000 1$:   MOVB   DW#JOB(R2),R1 ;Get job index number
18 005522 032761 0000000 0000000 BIT    ##VNOTT,LSW(R1) ;Is job attached to terminal?
19 005530 001404          BEQ    9$          ;Br if yes
20         ;
21         ; Suspend the job
22         ;
23 005532          DCALL  PCSPND      ;Suspend execution of the job
24 005540 000766          BR     1$          ;Wait till job reconnects to terminal
25         ;
26         ; Finished
27         ;
28 005542 012601 9$:   MOV    (SP)+,R1
29 005544 000207          RETURN

```

ERSLIN -- Erase the current line

```

1          .SBTTL  ERSLIN -- Erase the current line
2          ;-----
3          ; Erase the current line.  Do not change the line attributes and leave
4          ; the cursor where it is.
5          ;
6          ; Inputs:
7          ; R2 = Pointer to window control block
8          ;
9 005546 010346  ERSLIN: MOV      R3, -(SP)
10         ;
11         ; Store blanks with all attributes cleared into all line columns
12         ;
13 005550 016203 0000000  MOV      DW#LPT(R2), R3  ;Get pointer to 1st char in line
14 005554 016200 0000000  MOV      DW#CPL(R2), R0  ;Get number of columns per line
15 005560         1$:  BUFMAP          ;;;Map to display buffer
16 005602 112723 000040  MOV      #40, (R3)+     ;;;Store blank as the character
17 005606 105023         CLR      (R3)+          ;;;Clear all attribute flags
18 005610         UNMAP          ;Restore mapping
19 005624 077023         SOB      R0, 1$      ;Clear entire line
20         ;
21         ; Finished
22         ;
23 005626 012603         MOV      (SP)+, R3
24 005630 000207         RETURN

```

ERSCTL -- Erase from cursor to the end of the line

```

1          .SBTTL  ERSCTL -- Erase from cursor to the end of the line
2          ;-----
3          ; Erase all characters from the cursor position to the end of the line.
4          ; The cursor does not move. Character attributes are reset for all
5          ; erased characters.
6          ;
7          ; Inputs:
8          ; R2 = Pointer to window control block
9          ;
10         005632 010346 ERSCTL: MOV     R3, -(SP)
11         005634 010446         MOV     R4, -(SP)
12         ;
13         ; Get pointer to current cursor position and to end of line
14         ;
15         005636 016203 00000000         MOV     DW$COL(R2), R3 ;Get current column number
16         005642 005303         DEC     R3 ;Convert to column offset
17         005644 006303         ASL     R3 ;Two bytes are used by each column
18         005646 066203 00000000         ADD     DW$LPT(R2), R3 ;Point to byte for current column
19         005652 016204 00000000         MOV     DW$CPL(R2), R4 ;Get number of columns per line
20         005656 005304         DEC     R4 ;Convert to offset
21         005660 006304         ASL     R4 ;Two bytes per column
22         005662 066204 00000000         ADD     DW$LPT(R2), R4 ;Get pointer to byte for last column
23         ;
24         ; Clear the line to blanks
25         ;
26         005666         1$: BUFMAP ;;;Map to display buffer
27         005710 112723 000040         MOV     #40, (R3)+ ;;;Store blank as character
28         005714 105023         CLRB   (R3)+ ;;;Clear attribute flags
29         005716         UNMAP ;Restore mapping
30         005732 020304         CMP    R3, R4 ;Finished line?
31         005734 101754         BLOS  1$ ;Loop if not
32         ;
33         ; Finished
34         ;
35         005736 012604         MOV     (SP)+, R4
36         005740 012603         MOV     (SP)+, R3
37         005742 000207         RETURN

```

ERSLTC -- Erase from beginning of line to cursor

```

1          .SBTTL  ERSLTC -- Erase from beginning of line to cursor
2          ;-----
3          ; Erase from the beginning of the line up to and including the character
4          ; pointed to by the cursor.  The cursor does not move.
5          ;
6          ; Inputs:
7          ; R2 = Pointer to window control block.
8          ;
9 005744  010346  ERSLTC: MOV      R3, -(SP)
10         ;
11         ; Set up pointer to start of line and to cursor position
12         ;
13 005746  016203  0000000  MOV      DW$LPT(R2), R3  ;Get pointer to 1st byte for the line
14 005752  016200  0000000  MOV      DW$COL(R2), R0  ;Get current cursor column
15         ;
16         ; Blank the characters
17         ;
18 005756          1$:  BUFMAP          ;;Map to display buffer
19 006000  112723  000040  MOVB     #40, (R3)+      ;;Store blank as the character
20 006004  105023          CLRB     (R3)+          ;;Clear attribute flags
21 006006          UNMAP          ;Restore mapping
22 006022  077023          SOB      R0, 1$      ;Loop if more characters to clear
23         ;
24         ; Finished
25         ;
26 006024  012603  MOV      (SP)+, R3
27 006026  000207  RETURN

```

ERSCTP -- Erase from cursor to the end of the page

```

1          .SBTTL  ERSCTP -- Erase from cursor to the end of the page
2          ;-----
3          ; Erase from the current cursor position to the end of the page.
4          ; The cursor does not move.  Line attributes for completely erased
5          ; lines are reset.
6          ;
7          ; Inputs:
8          ; R2 = Pointer to window control block
9          ;
10         006030 010544 ERSCTP: MOV     R5,-(SP)
11         006032 016244 0000000  MOV     DW$LIN(R2),-(SP); Save the current line number
12         ;
13         ; Initialize the line number to the current line
14         ;
15         006036 016205 0000000  MOV     DW$LIN(R2),R5 ; Get current line number
16         ;
17         ; Determine if we are clearing all of the current line
18         ;
19         006042 026227 0000000 000001  CMP     DW$COL(R2),#1 ; Is cursor at column 1 of current line?
20         006050 001403  BEQ     1$ ; Br if yes -- Clear all of current line
21         ;
22         ; Clear from cursor to end of current line
23         ;
24         006052 004737 005632'  CALL   ERSCTL ; Erase to end of current line
25         006056 005205  INC     R5 ; Advance line number
26         ;
27         ; Now clear all lines below current line
28         ;
29         006060 020562 0000000 1$:  CMP     R5,DW$LPP(R2) ; Have we erased all lines?
30         006064 101005  BHI     9$ ; Br if yes
31         006066 010500  MOV     R5,R0 ; Get number of line to be cleared
32         006070 004737 006232'  CALL   CLRLIN ; Clear the line
33         006074 005205  INC     R5 ; Increment line number
34         006076 000770  BR     1$ ; See if there are more to clear
35         ;
36         ; Finished
37         ;
38         006100 012600 9$:  MOV     (SP)+,R0 ; Recover original line number
39         006102 004737 006702'  CALL   SETLIN ; Restore line number
40         006106 012605  MOV     (SP)+,R5
41         006110 000207  RETURN

```

ERSPTC -- Erase from beginning of page to cursor

```

1          .SBTTL  ERSPTC -- Erase from beginning of page to cursor
2          ;-----
3          ; Erase all of the characters from the beginning of the page up to and
4          ; including the character under the cursor.  Line attributes are cleared
5          ; for lines that are completely erased.
6          ;
7          ; Inputs:
8          ; R2 = Pointer to window control block
9          ;
10         006112  010446  ERSPTC:  MOV     R4,-(SP)
11         006114  010546          MOV     R5,-(SP)
12         ;
13         ; Initialize line numbers
14         ;
15         006116  016205  0000000  MOV     DW$LIN(R2),R5 ;Get number of current line
16         006122  012704  0000001  MOV     #1,R4        ;Get number of first line
17         ;
18         ; Erase all lines up to, but not including, current line
19         ;
20         006126  020405  1$:      CMP     R4,R5      ;Have we reached current line?
21         006130  103005          BHIS    2$          ;Br if yes
22         006132  010400          MOV     R4,R0      ;Get number of line to erase
23         006134  004737  006232'  CALL   CLRLIN     ;Erase the line
24         006140  005204          INC     R4        ;Advance the line number
25         006142  000771          BR     1$        ;See if more lines to erase
26         ;
27         ; Erase the line the cursor is on
28         ;
29         006144  010400  2$:      MOV     R4,R0      ;Get number of current line
30         006146  026262  0000000  0000000  CMP     DW$COL(R2),DW$CPL(R2);Is cursor at the end of the line?
31         006154  001003          BNE    3$        ;Br if not
32         006156  004737  006232'  CALL   CLRLIN     ;Clear it
33         006162  000404          BR     9$        ;
34         006164  004737  006702'  3$:      CALL   SETLIN    ;Select current line
35         006170  004737  005744'  CALL   ERSLTC    ;Erase up to cursor
36         ;
37         ; Finished
38         ;
39         006174  010500  9$:      MOV     R5,R0      ;Get back current line number
40         006176  004737  006702'  CALL   SETLIN    ;Select as current line
41         006202  012605          MOV     (SP)+,R5
42         006204  012604          MOV     (SP)+,R4
43         006206  000207          RETURN
44
45

```

```
1          .SBTTL  ERSPAG -- Clear entire page to spaces
2          ;-----
3          ; Clear the entire page to spaces
4          ;
5          ; Inputs:
6          ; R2 = Pointer to window control block
7          ;
8 006210 010546 ERSPAG: MOV     R5, -(SP)
9          ;
10         ; Begin loop to clear all lines
11         ;
12 006212 016205 0000006          MOV     DW$LPP(R2), R5 ; Get last line number
13 006216 010500          1$:  MOV     R5, R0          ; Get number of line to clear
14 006220 004737 006232'          CALL  CLRLIN          ; Clear line to spaces
15 006224 077504          SOB     R5, 1$          ; Loop if more lines to clear
16         ;
17         ; Finished
18         ;
19 006226 012605          MOV     (SP)+, R5
20 006230 000207          RETURN
```

CLRLIN -- Clear a line to spaces

```

1          .SBTTL  CLRLIN -- Clear a line to spaces
2          ;-----
3          ; Clear a line to spaces and set the line attributes to single high,
4          ; single wide.
5          ;
6          ; Inputs:
7          ; R0 = Number of line to be cleared
8          ; R2 = Pointer to window control block
9          ;
10         CLRLIN:  MOV     R3, -(SP)
11                MOV     R4, -(SP)
12         006232  010346  00000000  MOV     DW$LIN(R2), -(SP); Save current line number
13                ;
14                ; Select the line to be cleared
15                ;
16         006242  004737  006702'   CALL    SETLIN          ; Select line to be cleared
17                ;
18                ; Blank the line
19                ;
20         006246  016203  00000000  MOV     DW$LPT(R2), R3   ; Get pointer to start of line
21         006252  016204  00000000  MOV     DW$CPL(R2), R4   ; Get # columns in the line
22         006256  ;          ;          ; Map to screen buffer
23         006300  112723  0000040   MOVB   #40, (R3)+        ; Store blank character
24         006304  105023  ;          ; Clear character attributes
25         006306  ;          ;          ; Restore mapping
26         006322  077423  ;          ; Loop if need to store more blanks
27         SOB     R4, 1$
28                ;
29                ; Reset line attributes
30                ;
31         006324  005000  ;          ; Set attribute to 0
32         006326  004737  006522'   CALL    SETLAB          ; Reset all line attributes
33                ;
34                ; Finished
35                ;
36         006332  012600  ;          ; Get back original line #
37         006334  004737  006702'   CALL    SETLIN          ; Reselect original line
38         006340  012604  ;          ;
39         006342  012603  ;          ;
40         006344  000207  ;          ;
41                RETURN

```

CPYLIN -- Copy characters from one line to another

```

1          .SBTTL  CPYLIN -- Copy characters from one line to another
2          ;-----
3          ; Copy the characters and attributes from one line to another.
4          ; The line attribute is also copied.
5          ;
6          ; Inputs:
7          ; R2 = Pointer to window control block
8          ; R4 = Number of line to copy from
9          ; R5 = Number of line to copy to
10         ;
11 006346  010346  CPYLIN: MOV     R3,-(SP)
12 006350  010446          MOV     R4,-(SP)
13 006352  010546          MOV     R5,-(SP)
14 006354  016246  0000000  MOV     DW$LIN(R2),-(SP); Save current line number
15         ;
16         ; Copy the line attribute byte
17         ;
18 006360  010400          MOV     R4,R0          ;Get source line #
19 006362  004737  006702'  CALL    SETLIN        ;Set up info about that line
20 006366  004737  006612'  CALL    GETLAB        ;Get line attribute information (to R0)
21 006372  010003          MOV     R0,R3          ;Save line attribute
22 006374  010500          MOV     R5,R0          ;Get dest line #
23 006376  004737  006702'  CALL    SETLIN        ;Set up info about that line
24 006402  010300          MOV     R3,R0          ;Get line attribute byte
25 006404  004737  006522'  CALL    SETLAB        ;Set line attribute byte
26         ;
27         ; Get pointers to characters in from and to lines
28         ;
29 006410  010400          MOV     R4,R0          ;Get # of line we are copying from
30 006412  004737  006702'  CALL    SETLIN        ;Set up information about the line
31 006416  016204  0000000  MOV     DW$LPT(R2),R4  ;Get pointer to 1st char in from line
32 006422  010500          MOV     R5,R0          ;Get # of line we are copying to
33 006424  004737  006702'  CALL    SETLIN        ;Set up information about the line
34 006430  016205  0000000  MOV     DW$LPT(R2),R5  ;Get pointer to 1st char in to line
35         ;
36         ; Begin loop to copy the characters
37         ;
38 006434  016200  0000000  MOV     DW$CPL(R2),R0  ;Get # columns to copy
39 006440          1$:  BUFMAP          ;;;Map to screen buffer
40 006462  112425  MOV     (R4)+,(R5)+    ;;;Copy character
41 006464  112425  MOV     (R4)+,(R5)+    ;;;Copy attribute
42 006466          UNMAP          ;Restore mapping
43 006502  077022  SOB     R0,1$          ;Loop to copy all chars in the line
44         ;
45         ; Finished
46         ;
47 006504  012600          MOV     (SP)+,R0       ;Get back original line #
48 006506  004737  006702'  CALL    SETLIN        ;Reselect that line
49 006512  012605          MOV     (SP)+,R5
50 006514  012604          MOV     (SP)+,R4
51 006516  012603          MOV     (SP)+,R3
52 006520  000207          RETURN

```

SETLAB -- Set attributes for current line

```

1          .SBTTL  SETLAB -- Set attributes for current line
2          ;-----
3          ; SETLAB is called to set the line attribute byte for the current line.
4          ;
5          ; Inputs:
6          ;   R0 = Line attribute byte value
7          ;   R2 = Pointer to window control block
8          ;
9 006522  010346  SETLAB: MOV      R3, -(SP)
10         ;
11         ; Compute virtual address of byte with attribute for current line
12         ;
13 006524  016203  0000000  MOV      DW$LIN(R2), R3  ;Get current line number
14 006530  166203  0000000  SUB      DW$TLN(R2), R3  ;Get offset from line at top of buffer
15 006534  002002  BGE      1$              ;Br if line greater than 1st line
16 006536  066203  0000000  ADD      DW$LPP(R2), R3  ;Get offset to line we want
17 006542  062703  0000000  1$: ADD   #VPAR6, R3     ;Add virtual base address
18         ;
19         ; Store the new attribute byte
20         ;
21 006546  BUFMAP                    ;;;Map to screen buffer
22 006570  110013  MOV      RO, (R3)        ;;;Store new attribute for line
23 006572  UNMAP                      ;Restore mapping
24         ;
25         ; Finished
26         ;
27 006606  012603  MOV      (SP)+, R3
28 006610  000207  RETURN

```

GETLAB -- Get attributes for current line

```

1          .SBTTL  GETLAB -- Get attributes for current line
2          ;-----
3          ; GETLAB is called to get the line attribute byte for the current line.
4          ;
5          ; Inputs:
6          ;   R2 = Pointer to window control block
7          ;
8          ; Outputs:
9          ;   R0 = Line attribute byte for current line.
10         ;
11 006612  010346  GETLAB: MOV      R3, -(SP)
12         ;
13         ; Compute virtual address of byte with attribute for current line
14         ;
15 006614  016203  0000000  MOV      DW$LIN(R2), R3  ;Get current line number
16 006620  166203  0000000  SUB      DW$TLN(R2), R3  ;Get offset from line at top of buffer
17 006624  002002                BGE      1$              ;Br if line greater than 1st line
18 006626  066203  0000000  ADD      DW$LPP(R2), R3  ;Get offset to line we want
19 006632  062703  0000000  1$: ADD      #VPAR6, R3   ;Add virtual base address
20         ;
21         ; Get the attribute byte
22         ;
23 006636                BUFMAP                ;;;Map to screen buffer
24 006660  111300  MOV      (R3), R0        ;;;Get the line attribute byte
25 006662                UNMAP                  ;Restore mapping
26         ;
27         ; Finished
28         ;
29 006676  012603  MOV      (SP)+, R3
30 006700  000207  RETURN

```

SETLIN -- Select a line as current line

```

1          .SBTTL  SETLIN -- Select a line as current line
2          ;-----
3          ; Select a specified line as the current line and set up pointer information
4          ; for it.
5          ;
6          ; Inputs:
7          ; R0 = Line number being selected (1-24)
8          ; R2 = Pointer to window control block
9          ;
10         ; Outputs:
11         ; DW$LIN(R2) = Set to current line number
12         ; DW$LPT(R2) = Virtual address of 1st character on current line
13         ;
14 006702 010146 SETLIN: MOV      R1,-(SP)
15         ;
16         ; Set the current line number in WCB
17         ;
18 006704 010062 0000000 MOV      R0,DW$LIN(R2) ;Set current line number
19         ;
20         ; Compute virtual address of 1st character in this line
21         ;
22 006710 166200 0000000 SUB      DW$TLN(R2),R0 ;Get # lines from top to line wanted
23 006714 002002 BGE     1$ ;Br if top line is LE one wanted
24 006716 066200 0000000 ADD      DW$LPP(R2),R0 ;Add total number of lines per page
25 006722 010001 1$: MOV     R0,R1 ;Get # lines offset to line we want
26 006724 070162 0000000 MUL      DW$CPL(R2),R1 ;Multiply by number of columns per line
27 006730 006301 ASL     R1 ;Times two because of attribute bytes
28 006732 066201 0000000 ADD      DW$LPP(R2),R1 ;Skip over bytes with line attributes
29 006736 062701 0000000 ADD      #VPAR6,R1 ;Add base virtual address
30 006742 010162 0000000 MOV      R1,DW$LPT(R2) ;This is virtual addr of start of line
31         ;
32         ; Finished
33         ;
34 006746 012601 MOV      (SP)+,R1
35 006750 000207 RETURN

```

WINSF -- Switch from a job with a display window

```

1          .SRTTL  WINSF  -- Switch from a job with a display window
2          ;-----
3          ; WINSF is called from TSTTY when we are switching from a job which
4          ; has an active display window.
5          ;
6          ; Inputs:
7          ; R2 = Pointer to display window control block for job being switched from
8          ;
9 006752   WINSF:
10         ;
11         ; Set flag which prevents characters from being passed through to the
12         ; screen.
13         ;
14 006752  052762  0000000 0000000      BIS      #AW$DDC,DW$AW(R2);Don't pass through any more chars
15         ;
16         ; Reset number of lines scrolled since we disconnected from window
17         ;
18 006760  105062  0000000      CLRB     DW$NSL(R2)      ;No lines scrolled yet
19         ;
20         ; Finished
21         ;
22 006764  000207      RETURN

```

WINST -- Switch to job with a window

```

1          .SBTTL  WINST  -- Switch to job with a window
2          ;-----
3          ;  WINST is called from TSTTY when we are switching to a job that has
4          ;  a display window active.
5          ;
6          ;  Inputs:
7          ;  R2 = Pointer to current window control block for job being switched to
8          ;
9 006766  010146  WINST:  MOV     R1, -(SP)
10         ;
11         ;  Get job index number
12         ;
13 006770  116201  0000000  MOVB   DW$JOB(R2), R1  ;Get job index number
14         ;
15         ;  Set flag which will cause the window to be redisplayed when the
16         ;  job resumes execution.
17         ;
18 006774  052761  0000000 0000000  BIS    #$WDISP, LSW6(R1); Set flag saying to redisplay window
19         ;
20         ;  If job is in terminal-output-wait state, restart its execution
21         ;
22 007002  026127  0000000 0000000  CMP    LSTATE(R1), #S$OTWT; TT-output-wait state?
23 007010  001002  BNE    9$          ;Br if not
24 007012  004737  0000000  CALL   FORCEX      ;Restart execution of job
25         ;
26         ;  Finished
27         ;
28 007016  012601  9$:    MOV     (SP)+, R1
29 007020  000207  RETURN

```

WINDSP -- Redisplay current window for job

```

1          .SBTTL  WINDSP -- Redisplay current window for job
2          ;-----
3          ; WINDSP is called from the scheduler when it is about ready to
4          ; reenter a job whose window needs to be redisplayed.
5          ;
6          ; Inputs:
7          ; R1 = Current job index number
8          ;
9 007022  010246  WINDSP: MOV      R2,-(SP)
10         ;
11         ; Reset flag that says window redisplay needed
12         ; and set flag that says a window refresh is being done.
13         ;
14 007024  042761  0000000 0000000      BIC      ##WDISP,LSW6(R1);Window redisplay no longer needed
15 007032  052761  0000000 0000000      BIS      ##RFRSH,LSW4(R1);Window refresh currently being done
16         ;
17         ; Redisplay current window for job
18         ;
19 007040  016102  0000000      MOV      LWINDO(R1),R2      ;Get addr of current window control block
20 007044  001402      BEQ      9$              ;Br if job is not doing windowing
21 007046  004737  007064'      CALL     REFRSH          ;Redisplay window
22         ;
23         ; Finished
24         ;
25 007052  042761  0000000 0000000 9$:  BIC      ##RFRSH,LSW4(R1);Say window refresh is finished
26 007060  012602      MOV      (SP)+,R2
27 007062  000207      RETURN

```

REFRSH -- Refresh screen from window contents

```

1          .SBTTL  REFRSH -- Refresh screen from window contents
2          ;-----
3          ; This routine is called to clear the screen and refresh its contents
4          ; from the screen buffer.
5          ;
6          ; Inputs:
7          ; R2 = Pointer to window control block
8          ;
9 007064 010146 REFRSH: MOV     R1,-(SP)
10 007066 010546      MOV     R5,-(SP)
11          ;
12          ; Stop characters from being passed from program to screen while we are
13          ; doing the refresh
14          ;
15 007070 052762 0000000 0000000      BIS     #AW$DDC,DW$AW(R2); Suppress character pass-through
16          ;
17          ; Clear contents of line's output buffer and reset control-D flag
18          ;
19 007076 116201 0000000      MOV     DW$JOB(R2),R1 ;Get job index number
20 007102      DISABL      ;;; Disable interrupts
21 007110 016161 0000000 0000000      MOV     LOTSIZ(R1),LOTSPC(R1);; Clear contents of line's output buffer
22 007116 016161 0000000 0000000      MOV     LOTNXT(R1),LOTPNT(R1);;
23 007124      ENABL      ; Enable interrupts
24 007132 042761 0000000 0000000      BIC     #$CTRLD,LSW3(R1); Reset control-D flag
25          ;
26          ; See if we need to turn VT52 emulation mode on or off
27          ;
28 007140 004737 011110'      CALL     GENTEM      ; Check VT52 emulation mode status
29          ;
30          ; Clear the screen
31          ;
32 007144 004737 007612'      CALL     GENCLR      ; Clear the screen
33          ;
34          ; Set overall window attributes
35          ;
36 007150 004737 011240'      CALL     GENWAF      ; Set overall window attributes
37          ;
38          ; Initialize character attribute flags
39          ;
40 007154 005005      CLR     R5      ; No character attribute flags
41          ;
42          ; Begin loop to send each line to the screen
43          ;
44 007156 016246 0000000      MOV     DW$LIN(R2),-(SP); Save current line number
45 007162 012701 0000001      MOV     #1,R1      ; Get 1st line number
46 007166 010100      1$:  MOV     R1,R0      ; Get line number
47 007170 004737 006702'      CALL     SETLIN      ; Select as current line
48 007174 004737 007302'      CALL     SNDLIN      ; Send line to screen
49 007200 005201      INC     R1      ; Increment line number
50 007202 020162 0000000      CMP     R1,DW$LPP(R2) ; Have we done all lines?
51 007206 101767      BLOS    1$      ; Loop if not
52          ;
53          ; Reset line number
54          ;
55 007210 012600      MOV     (SP)+,R0      ; Get back line where we should be
56 007212 004737 006702'      CALL     SETLIN      ; Set this as the current line
57          ;

```

```
58 ; Set up scrolling region status
59 ;
60 007216 004737 010746' CALL GENSSS ;Set up split screen scrolling
61 ;
62 ; Place cursor where it should be
63 ;
64 007222 004737 012104' CALL GENCSR ;Gen cursor positioning commands
65 007226 016200 0000000 MOV DW$COL(R2),R0 ;Get current column number
66 007232 005300 DEC R0 ;Make 1st column be 0
67 007234 116201 0000000 MOVB DW$JOB(R2),R1 ;Get our job number
68 007240 110061 0000000 MOVB R0,LCOL(R1) ;Tell TSTTY where cursor is
69 ;
70 ; Make sure character attribute is set correctly
71 ;
72 007244 120562 0000000 CMPB R5,DW$CCA(R2) ;Is character attribute set correctly?
73 007250 001404 BEQ 2$ ;Br if yes
74 007252 116200 0000000 MOVB DW$CCA(R2),R0 ;Get needed character attribute
75 007256 004737 010122' CALL GENCAF ;Set character attribute
76 ;
77 ; Set up correct character set mapping
78 ;
79 007262 004737 010534' 2$: CALL GENMAP ;Set up correct character set mapping
80 ;
81 ; Now allow characters to be passed to the screen
82 ;
83 007266 042762 0000000 0000000 BIC #AW$DDC,DW$AW(R2);Enable character pass-through
84 ;
85 ; Finished
86 ;
87 007274 012605 9$: MOV (SP)+,R5
88 007276 012601 MOV (SP)+,R1
89 007300 000207 RETURN
```

SNDLIN -- Send line of characters to terminal

```

1          .SBTTL  SNDLIN -- Send line of characters to terminal
2          ;-----
3          ; Send a line of characters from the screen buffer to the terminal.
4          ; The currently selected line is the one sent.
5          ;
6          ; Inputs:
7          ; R2 = Pointer to window control block.
8          ; R5 = Current character attribute flags
9          ;
10         ; Outputs:
11        ; R5 = Character attribute flags for last character on line
12        ;
13 007302 010146  SNDLIN: MOV     R1,-(SP)
14 007304 010346          MOV     R3,-(SP)
15 007306 010446          MOV     R4,-(SP)
16 007310 016246 0000000  MOV     DW$COL(R2),-(SP); Save current column number
17        ;
18        ; Set line attribute flag and determine number of columns to display
19        ;
20 007314 004737 006612'   CALL    GETLAB      ;Get line attribute flags for cur line to R0
21 007320 012701 000120   MOV     #80.,R1     ;Assume 80 columns to display
22 007324 032762 0000000 0000000  BIT     #AW$132,DW$AW(R2);Are we in 132 column mode?
23 007332 001402          BEQ     1$          ;Br if not in 132 col mode
24 007334 012701 000204   MOV     #132.,R1    ;Say we need to display 132 columns
25 007340 132700 0000000  1$:    BITB    #<AL$DHT!AL$DHB!AL$DWD>,R0 ;Double wide line?
26 007344 001401          BEQ     3$          ;Br if not double wide
27 007346 006201          ASR     R1          ;Only need to display half as many chars
28 007350 004737 011622'  3$:    CALL    GENLAF      ;Generate line attribute flag info
29        ;
30        ; Store number of columns to display on top of stack
31        ;
32 007354 020162 0000000   CMP     R1,DW$CPL(R2) ;Are we storing as many cols as needed?
33 007360 101402          BLOS   5$          ;Br if yes
34 007362 016201 0000000   MOV     DW$CPL(R2),R1 ;Get # columns we are storing
35 007366 010146          5$:    MOV     R1,-(SP)    ;Store # columns to display on top of stack
36        ;
37        ; Begin loop to output the characters on the line
38        ;
39 007370 012701 0000001   MOV     #1,R1       ;Init column number
40 007374 010162 0000000   MOV     R1,DW$COL(R2) ;Init col where next character goes
41 007400 016203 0000000   MOV     DW$LPT(R2),R3 ;Get pointer to 1st char on this line
42        ;
43        ; Scan over spaces that have no attributes set
44        ;
45 007404          4$:    BUFMAP      ;;;Map to screen buffer
46 007426 112304          MOVVB   (R3)+,R4     ;;;Get character
47 007430 112300          MOVVB   (R3)+,R0     ;;;Get attribute flags for character
48 007432          UNMAP      ;Restore mapping
49 007446 120427 000040   CMPB   R4,#40       ;Is character a space?
50 007452 001005          BNE    2$          ;Br if not
51 007454 120005          CMPB   R0,R5        ;Are attributes changing?
52 007456 001003          BNE    2$          ;Br if yes
53 007460 032700 0000000  BIT     #<AC$BLD!AC$BLK!AC$REV!AC$ULN>,R0 ;Bold, blink, reverse, under
54 007464 001420          BEQ    8$          ;Br if not
55        ;
56        ; We found a character that we need to send.
57        ; (R4 = character, R0 = attribute flags)

```

SNDLIN -- Send line of characters to terminal

```

58          ; Position to correct column for the character.
59          ;
60 007466 020162 0000000 2$:    CMP    R1,DW$COL(R2) ;Are we at correct column now?
61 007472 001404          BEQ    6$          ;Br if yes
62 007474 010046          MOV    R0,-(SP)    ;Save character attribute flags
63 007476 004737 011736' CALL   GENSPC    ;Generate spaces to move to correct col
64 007502 012600          MOV    (SP)+,R0    ;Restore character attribute flags
65          ;
66          ; See if we need to change attributes for this character
67          ;
68 007504 120005 6$:    CMPB   R0,R5          ;Do we need to change attributes?
69 007506 001402          BEQ    7$          ;Br if not
70 007510 004737 010122' CALL   GENCAF    ;Set character attribute flags
71          ;
72          ; Send the character to the terminal
73          ;
74 007514 010400 7$:    MOV    R4,R0          ;Get character to send
75 007516 004737 012314' CALL   GENCHR    ;Send the character to the terminal
76 007522 005262 0000000 INC    DW$COL(R2) ;Increment current column number
77          ;
78          ; Advance to next character
79          ;
80 007526 005201 8$:    INC    R1          ;Increment column number
81 007530 020116          CMP    R1,(SP)    ;Done all columns?
82 007532 101724          BLOS   4$          ;Loop if not
83          ;
84          ; Output carriage-return line-feed at the end of the line
85          ;
86 007534 026262 0000000 0000000 CMP    DW$LIN(R2),DW$LPP(R2);Is this the last line on the page?
87 007542 001414          BEQ    20$         ;Br if yes -- Don't send CR-LF
88 007544 026227 0000000 000001  CMP    DW$COL(R2),#1 ;Are we still at col 1 (entire line blank)?
89 007552 001404          BEQ    10$         ;Br if yes
90 007554          SEND   #CR          ;Send carriage return
91 007564          10$:  SEND   #LF          ;Send line feed
92          ;
93          ; Finished
94          ;
95 007574 005726 20$:    TST    (SP)+          ;Pop number of columns per line
96 007576 012662 0000000 MOV    (SP)+,DW$COL(R2);Restore cursor column number
97 007602 012604          MOV    (SP)+,R4
98 007604 012603          MOV    (SP)+,R3
99 007606 012601          MOV    (SP)+,R1
100 007610 000207          RETURN

```

GENCLR -- Gen control sequence to clear screen

```

1          .SBTTL  GENCLR -- Gen control sequence to clear screen
2          ;-----
3          ; Generate the appropriate terminal control sequence to clear the screen.
4          ;
5          ; Inputs:
6          ;   R2 = Pointer to window control block
7          ;
8 007612   GENCLR:
9          ;
10         ; See if we need to generate a VT100 or VT52 sequence
11         ;
12 007612   032762   000000C 000000G          BIT      #<AW$52!AW$552>,DW$AW(R2);VT52?
13 007620   001115          BNE      1$          ;Br if yes
14         ;
15         ; Generate VT100 sequence
16         ; Reset scrolling region
17         ;
18 007622   004737   012272'          CALL     GENCSI          ;Generate CSI header
19 007626          SEND     #'r          ;Reset scrolling region
20         ;
21         ; Set absolute origin
22         ;
23 007636   004737   012272'          CALL     GENCSI          ;Generate CSI header
24 007642          SEND     #'?          ;Send ?
25 007652          SEND     #'6          ;Send 6
26 007662          SEND     #'1          ;Send 1
27         ;
28         ; Home cursor and clear to end of screen
29         ;
30 007672   004737   012272'          CALL     GENCSI          ;Generate CSI header
31 007676          SEND     #'H          ;Send H -- Home cursor
32 007706   004737   012272'          CALL     GENCSI          ;Generate CSI header
33 007712          SEND     #'J          ;Send J -- Clear to end of screen
34         ;
35         ; Reset character attributes
36         ;
37 007722   004737   012272'          CALL     GENCSI          ;Send CSI O m to reset char attributes
38 007726          SEND     #'O
39 007736          SEND     #'m
40         ;
41         ; Map GL to G0 and designate G0 as ascii
42         ;
43 007746          SEND     #17          ;Send shift-in -- Lock shift G0 to GL
44 007756   004737   012260'          CALL     GENESC          ;Send escape
45 007762          SEND     #'(          ;Select G0
46 007772          SEND     #'B          ;Map G0 to ascii
47         ;
48         ; Map GR to G2 and designate G2 as ascii
49         ;
50 010002   032762   000000G 000000G          BIT      #AW$200,DW$AW(R2);Is this a VT200 terminal?
51 010010   001443          BEQ      9$          ;Br if not -- Don't have to mess with GR
52 010012   004737   012260'          CALL     GENESC          ;Send ESC
53 010016          SEND     #'}          ;Lock shift GR to G2
54 010026   004737   012260'          CALL     GENESC          ;Send escape
55 010032          SEND     #'*          ;Select G2
56 010042          SEND     #'B          ;Designate ascii
57 010052   000422          BR      9$

```

GENCLR -- Gen control sequence to clear screen

```
58 ;  
59 ; Generate VT52 sequence  
60 ;  
61 010054 004737 012260' 1$: CALL GENESC ;Generate ESC character  
62 010060 SEND #'H ;Send H -- Home cursor  
63 010070 004737 012260' CALL GENESC ;Generate ESC character  
64 010074 SEND #'J ;Send J -- Clear to end of screen  
65 010104 004737 012260' CALL GENESC ;Generate ESC character  
66 010110 SEND #'G ;Select ascii character set  
67 ;  
68 ; Finished  
69 ;  
70 010120 000207 9$: RETURN
```

GENCAF -- Generate sequence to set character attributes

```

1          .SBTTL  GENCAF -- Generate sequence to set character attributes
2          ;-----
3          ; Generate the terminal sequence to set character attributes.
4          ;
5          ; Inputs:
6          ; R0 = Character attribute wanted
7          ; R2 = Pointer to window control block
8          ; R5 = Current character attribute
9          ;
10         ; Outputs:
11         ; R5 = New character attributes
12         ;
13 010122  010146  GENCAF: MOV     R1, -(SP)
14 010124  010346      MOV     R3, -(SP)
15 010126  010446      MOV     R4, -(SP)
16 010130  010001      MOV     R0, R1          ; Carry new attributes in R1
17         ;
18         ; See if we need to change character sets
19         ;
20 010132  004737  010354'  CALL    GENCSO          ; See if we need to do character set change
21         ;
22         ; Don't have to worry about attributes if this is a VT52
23         ;
24 010136  032762  000000C 000000G  BIT     #<AW$52!AW$552>, DW$AW(R2); Is this a VT52?
25 010144  001076      BNE     9$              ; Br if yes
26         ;
27         ; See if character attributes have changed
28         ;
29 010146  010103      MOV     R1, R3          ; Get new attributes
30 010150  010504      MOV     R5, R4          ; Get current attributes
31 010152  042703  000000C  BIC     #^C<AC$BLD!AC$BLK!AC$REV!AC$ULN>, R3
32 010156  042704  000000C  BIC     #^C<AC$BLD!AC$BLK!AC$REV!AC$ULN>, R4
33 010162  020304      CMP     R3, R4          ; Have attributes changed?
34 010164  001466      BEQ     9$              ; Br if not
35         ;
36         ; Initialize control sequence and turn off all attributes
37         ;
38 010166  004737  012272'  CALL    GENCSI          ; Send CSI
39 010172      SEND    #'0          ; Send 0
40         ;
41         ; See if bold is wanted
42         ;
43 010202  032701  000000G  BIT     #AC$BLD, R1      ; Is bold wanted?
44 010206  001410      BEQ     1$              ; Br if not
45 010210      SEND    #SEMI          ; Send ';'
46 010220      SEND    #'1              ; Send '1'
47         ;
48         ; See if underscore is wanted
49         ;
50 010230  032701  000000G  1$: BIT     #AC$ULN, R1   ; Underline wanted?
51 010234  001410      BEQ     2$              ; Br if not
52 010236      SEND    #SEMI          ; Send ";"
53 010246      SEND    #'4              ; Send "4"
54         ;
55         ; See if blinking is wanted
56         ;
57 010256  032701  000000G  2$: BIT     #AC$BLK, R1   ; Blinking wanted?

```

```
58 010262 001410          BEQ      3$          ;Br if not
59 010264                SEND     #SEMI        ;Send ";5"
60 010274                SEND     #'5
61                      ;
62                      ; See if reverse video is wanted
63                      ;
64 010304 032701 0000000 3$:    BIT      #AC$REV,R1      ;Reverse video wanted?
65 010310 001410          BEQ      7$          ;Br if not
66 010312                SEND     #SEMI        ;Send ";7"
67 010322                SEND     #'7
68                      ;
69                      ; Terminate the string by sending "m"
70                      ;
71 010332                7$:    SEND     #'m          ;Send "m"
72                      ;
73                      ; Finished
74                      ;
75 010342 010105          9$:    MOV      R1,R5          ;Change current attributes to new attributes
76 010344 012604          MOV      (SP)+,R4
77 010346 012603          MOV      (SP)+,R3
78 010350 012601          MOV      (SP)+,R1
79 010352 000207          RETURN
```

GENCSC -- Generate terminal sequence to select char set

```

1          .SBTTL  GENCSC -- Generate terminal sequence to select char set
2          ;-----
3          ; Generate terminal control sequence to select the correct character
4          ; set for the next character.
5          ;
6          ; Inputs:
7          ; R0 = Character attribute wanted
8          ; R2 = Pointer to window control block
9          ; R5 = Current character attribute
10         ;
11 010354 010046 GENCSC: MOV     R0, -(SP)
12 010356 010146      MOV     R1, -(SP)
13 010360 010346      MOV     R3, -(SP)
14 010362 010446      MOV     R4, -(SP)
15 010364 010001      MOV     R0, R1          ; Carry new attributes in R1
16         ;
17         ; Determine if character set has changed
18         ;
19 010366 010103      MOV     R1, R3          ; Get new attributes
20 010370 042703 000000C BIC     #^C<AC$SET>, R3 ; Select character set number only
21 010374 010504      MOV     R5, R4          ; Get current attributes
22 010376 042704 000000C BIC     #^C<AC$SET>, R4 ; Select character set number only
23 010402 020304      CMP     R3, R4          ; Has character set changed?
24 010404 001443      BEQ     9$           ; Br if char set has not changed
25         ;
26         ; Character set has changed
27         ;
28 010406 032762 000000C 000000C BIT     #<AW$52!AW$552>, DW$AW(R2); Is this a VT52 terminal?
29 010414 001031      BNE     1$           ; Br if VT52
30         ;
31         ; VT100/VT200 terminal.
32         ; Generate sequence to map G0 and G2 to correct character set
33         ;
34 010416 004737 012260'  CALL    GENESC          ; Send ESC character
35 010422      SEND    #'(          ; Select G0
36 010432      SEND    SET200(R3)    ; Send char to map G0 to correct char set
37 010442 032762 000000C 000000C BIT     #AW$200, DW$AW(R2); Is this a VT200 terminal?
38 010450 001421      BEQ     9$           ; Br if not -- Don't need to change G2
39 010452 004737 012260'  CALL    GENESC          ; Send ESC character
40 010456      SEND    #'*          ; Select G2
41 010466      SEND    SET200(R3)    ; Send char to map G2 to correct char set
42 010476 000406      BR     9$           ;
43         ;
44         ; VT52 terminal.
45         ; Select ascii or graphics character set.
46         ;
47 010500 004737 012260'  1$: CALL    GENESC          ; Send ESC character
48 010504      SEND    SET52(R3)    ; Select ascii or graphics characters
49         ;
50         ; Finished
51         ;
52 010514 012604 9$: MOV     (SP)+, R4
53 010516 012603      MOV     (SP)+, R3
54 010520 012601      MOV     (SP)+, R1
55 010522 012600      MOV     (SP)+, R0
56 010524 000207      RETURN
57         ;

```

GENCSC -- Generate terminal sequence to select char set

```
58          ; Characters to be sent to change GO character set designation
59          ;
60 010526    107    074    101 SET200: .ASCII /B<AO/
    010531    060
61          ;
62          ; Characters to select ascii or graphics mode on a VT52
63          ;
64 010532    107    106    SET52:  .ASCII /GF/
65          .EVEN
```

GENMAP -- Generate sequence to set up char set mapping

```

1          .SBTTL  GENMAP -- Generate sequence to set up char set mapping
2          ;-----
3          ; Generate control sequence to set up the correct character set
4          ; mapping for GL, GR, GO, G1, G2, and G3.
5          ;
6          ; Inputs:
7          ; R2 = Pointer to window control block
8          ;
9 010534 010346 GENMAP: MOV     R3, -(SP)
10 010536 032762 000000C 000000G BIT     #<AW$52!AW$552>, DW$AW(R2); Is this a VT52 terminal?
11 010544 001060          BNE     5$          ; Br if VT52
12          ;
13          ; This is a VT100/VT200 terminal.
14          ; Set up mapping for GL.
15          ;
16 010546 116203 000000G          MOVVB  DW$GLM(R2), R3 ; Get mapping for GL
17 010552 120327 0000001          CMPB  R3, #1          ; Mapping to GO or G1?
18 010556 101402          BLOS  1$          ; Br if yes
19 010560 004737 012260'          CALL  GENESC          ; Send ESC
20 010564          1$: SEND   LSLCHR(R3) ; Send correct lock shift character
21          ;
22          ; Set up mapping for GR
23          ;
24 010574 032762 000000G 000000G BIT     #AW$200, DW$AW(R2); Is this a VT200?
25 010602 001410          BEQ   2$          ; Br if not -- Don't need to mess with GR
26 010604 116203 000000G          MOVVB  DW$GRM(R2), R3 ; Get mapping for GR
27 010610 004737 012260'          CALL  GENESC          ; Send ESC
28 010614          SEND   LSRCHR(R3) ; Send correct lock shift character
29          ;
30          ; Set up mapping for GO, G1, G2, and G3
31          ;
32 010624 012703 0000001          2$: MOV   #1, R3          ; Assume we only need to map GO and G1
33 010630 032762 000000G 000000G BIT     #AW$200, DW$AW(R2); Is this a VT200?
34 010636 001402          BEQ   3$          ; Br if not
35 010640 012703 0000003          MOV   #3, R3          ; Map G2 and G3 too
36 010644 004737 012260'          3$: CALL  GENESC          ; Send ESC
37 010650          SEND   GNMCHR(R3) ; Select G#
38 010660 010300          MOV   R3, R0          ; Get G number
39 010662 060200          ADD   R2, R0          ; Point into window control block
40 010664 116000 000000G          MOVVB  DW$GOM(R0), R0 ; Get mapping wanted for G#
41 010670          SEND   SET200(R0) ; Set mapping for the G#
42 010700 005303          DEC   R3          ; Have more G# to do?
43 010702 002360          BGE   3$          ; Loop if yes
44 010704 000410          BR    9$
45          ;
46          ; Set up mapping for a VT52 terminal
47          ;
48 010706 004737 012260'          5$: CALL  GENESC          ; Generate ESC character
49 010712 116203 000000G          MOVVB  DW$GOM(R2), R3 ; Get ascii/graphics mapping code
50 010716          SEND   SET52(R3) ; Select correct mapping
51          ;
52          ; Finished
53          ;
54 010726 012603          9$: MOV   (SP)+, R3
55 010730 000207          RETURN
56          ;
57          ; Characters used to lock shift a mapping into GL

```

```
58 ;  
59 010732 017 016 156 LSLCHR: .ASCII <17><16>/no/  
010735 157  
60 ;  
61 ; Characters used to lock shift a mapping into QR  
62 ;  
63 010736 077 176 175 LSRCHR: .ASCII /?~}!/  
010741 174  
64 ;  
65 ; Characters used to select Q0, Q1, Q2, or Q3 for mapping  
66 ;  
67 010742 050 051 052 QNMCHR: .ASCII /()*+/  
010745 053  
68 .EVEN
```

GENSSS -- Generate sequence for split screen scrolling

```

1          .SBTTL  GENSSS -- Generate sequence for split screen scrolling
2          ;-----
3          ; Generate the terminal control sequence needed to set the terminal to
4          ; split screen scrolling mode if that is needed.
5          ;
6          ; Inputs:
7          ; R2 = Pointer to window control block
8          ;
9 010746   GENSSS:
10         ;
11         ; We never set split screen scrolling for VT52 terminals
12         ;
13 010746   032762   0000000 0000000      BIT      #<AW$52!AW$S52>,DW$AW(R2);Is this a VT52?
14 010754   001054           9$          ;Br if yes
15         ;
16         ; See if we need to set split screen scrolling
17         ;
18 010756   026227   0000000 0000001      CMP      DW$SRT(R2),#1 ;Is top line of scrolling region 1?
19 010764   001004           BNE      2$          ;Br if not
20 010766   026262   0000000 0000000      CMP      DW$SRB(R2),DW$LPP(R2);Is bottom scroll line bottom of page?
21 010774   001444           BEQ      9$          ;Br if yes
22         ;
23         ; Declare scrolling region
24         ;
25 010776   004737   012272' 2$:      CALL     GENCSI      ;Generate CSI character
26 011002   016200   0000000      MOV      DW$SRT(R2),R0 ;Get top line # of scrolling region
27 011006   004737   012334'      CALL     GENVAL      ;Cvt to ascii digits and send them
28 011012           SEND     #SEMI      ;Send semicolon
29 011022   016200   0000000      MOV      DW$SRB(R2),R0 ;Get bottom line of scrolling region
30 011026   004737   012334'      CALL     GENVAL      ;Cvt to ascii digits and send them
31 011032           SEND     #'r       ;Terminate control sequence
32         ;
33         ; See if we need to set relative origin mode
34         ;
35 011042   032762   0000000 0000000      BIT      #AW$ORS,DW$AW(R2);Is origin to be relative to scroll region?
36 011050   001416           BEQ      9$          ;Br if not
37 011052   004737   012272'      CALL     GENCSI      ;Generate CSI character
38 011056           SEND     #'?       ;Send ?
39 011066           SEND     #'6       ;Send 6
40 011076           SEND     #'h       ;Send h
41         ;
42         ; Finished
43         ;
44 011106   000207 9$:      RETURN

```

```

1          .SBTTL  GENTEM -- Turn VT52 emulation mode on or off
2
3          ; -----
4          ; Generate the terminal control sequence to turn VT52 emulation mode
5          ; on or off as needed by this window.
6
7          ; Inputs:
8          ;   R2 = Pointer to window control block
9
10         ; See if we need to go into VT52 emulation mode
11
12 011110 116200 0000000 GENTEM: MOVB  DW#JOB(R2),R0 ;Get our job index number
13 011114 116000 0000000      MOVB  LNPRIM(R0),R0 ;Get our primary line index number
14 011120 032762 0000000 0000000      BIT   #AW#S52,DW#AW(R2) ;Does window want VT52 emulation mode?
15 011126 001426          BEQ   2$ ;Br if not
16 011130 032760 0000000 0000000      BIT   ##V52EM,LSW11(R0);Is VT52 emulation mode on now?
17 011136 001037          BNE   9$ ;Br if yes
18 011140 052760 0000000 0000000      BIS   ##V52EM,LSW11(R0);Say we are turning on VT52 emulation
19 011146 004737 012272'      CALL  GENCSI ;Send CSI character
20 011152          SEND  #'? ;Send "?21" to reset ANSI mode
21 011162          SEND  #'2
22 011172          SEND  #'1
23 011202 000415          BR    9$
24
25         ; See if we need to turn off VT52 emulation mode
26
27 011204 032760 0000000 0000000 2$: BIT   ##V52EM,LSW11(R0);Is VT52 emulation mode on now?
28 011212 001411          BEQ   9$ ;Br if not
29 011214 042760 0000000 0000000      BIC   ##V52EM,LSW11(R0);Say we are turning off VT52 emulation
30 011222 004737 012260'      CALL  GENESC ;Send ESC
31 011226          SEND  #'< ;Tell VT52 to enter ANSI mode
32
33         ; Finished
34
35 011236 000207          9$:  RETURN
  
```

GENWAF -- Generate terminal sequence to set window attrib

```

1          .SBTTL  GENWAF -- Generate terminal sequence to set window attrib
2          ;-----
3          ; Generate the terminal control sequence needed to set attributes for
4          ; the entire window.
5          ;
6          ; Inputs:
7          ; R2 = Pointer to window control block
8          ;
9 011240 010346 GENWAF: MOV     R3,-(SP)
10 011242 010446      MOV     R4,-(SP)
11          ;
12          ; Get control flags for the window attributes
13          ;
14 011244 016203 0000000 MOV     DW$AW(R2),R3 ;Get window attribute flags
15          ;
16          ; Generate control sequence to reset some flags
17          ;
18 011250 005103      COM     R3 ;Set flags that should be reset
19 011252 012704 000154 MOV     #'l,R4 ;Terminate string with lower-case L
20 011256 004737 011350' CALL    GENAAS ;Generate for ANSI attributes
21 011262 004737 011412' CALL    GENDAS ;Generate for DEC attributes
22          ;
23          ; Generate control sequence to set some flags
24          ;
25 011266 005103      COM     R3 ;Set flags that should be set
26 011270 012704 000150 MOV     #'h,R4 ;Terminate string with lower-case H
27 011274 004737 011350' CALL    GENAAS ;Generate for ANSI attributes
28 011300 004737 011412' CALL    GENDAS ;Generate for DEC attributes
29          ;
30          ; See if we should set or reset application keypad mode
31          ;
32 011304 004737 012260' CALL    GENESC ;Send escape
33 011310 032762 0000000 0000000 BIT     #AW$AKM,DW$AW(R2);Is application keypad mode wanted?
34 011316 001405      BEQ     1$ ;Br if not
35 011320      SEND    #'= ;Send equal sign
36 011330 000404      BR     9$
37 011332      1$: SEND    #'> ;Send greater-than sign
38          ;
39          ; Finished
40          ;
41 011342 012604      9$: MOV     (SP)+,R4
42 011344 012603      MOV     (SP)+,R3
43 011346 000207      RETURN

```

GENAAS -- Generate control sequence for ANSI attributes

```

1          .SBTTL  GENAAS -- Generate control sequence for ANSI attributes
2          ;-----
3          ; Generate the control sequence to set or reset ANSI attribute flags.
4          ;
5          ; Inputs:
6          ;   R2 = Pointer to window control block
7          ;   R3 = Word with flags
8          ;   R4 = Character to terminate string with
9          ;
10         011350 GENAAS:
11         ;
12         ; Don't send anything if this is a VT52
13         ;
14         011350 032762 0000000 0000000      BIT    #<AW$52!AW$552>,DW$AW(R2); Is this a VT52?
15         011356 001014                      BNE    9$          ;Br if yes
16         ;
17         ; See if insert mode is wanted
18         ;
19         011360 032703 0000000              BIT    #AW$INS,R3      ; Insert mode wanted?
20         011364 001411                      BEQ    9$          ; Br if not
21         011366 004737 012272'             CALL   GENCSI       ; Send CSI character
22         011372                                SEND   #'4          ; Send 4
23         011402                                SEND   R4          ; Terminate string
24         ;
25         ; Finished
26         ;
27         011410 000207 9$: RETURN

```

GENDAS -- Generate control sequence for DEC attributes

```

1          .SBTTTL  GENDAS -- Generate control sequence for DEC attributes
2          ;-----
3          ; Generate a terminal control sequence to set or reset DEC attributes.
4          ;
5          ; Inputs:
6          ; R2 = Pointer to window control block
7          ; R3 = AW$xxx attribute flags
8          ; R4 = Character to terminate string with
9          ;
10         GENDAS:  MOV    R1,-(SP)
11                 MOV    R3,-(SP)
12                 MOV    R5,-(SP)
13         ;
14         ; We don't have to set any DEC private attributes for VT52 terminals.
15         ;
16         011420  032762  0000000 0000000      BIT    #<AW$52!AW$552>,DW$AW(R2); Is this a VT52?
17         011426  001056                BNE    9$          ;Br if VT52
18         ;
19         ; VT100/VT200
20         ; If this is a VT100, clear VT200-only attribute flags.
21         ;
22         011430  032762  0000000 0000000      BIT    #AW$200,DW$AW(R2); Is this a VT200?
23         011436  001002                BNE    5$          ;Br if VT200
24         011440  042703  0000000      BIC    #AW$VCR,R3      ;Clear VT200-only flags
25         ;
26         ; Init flag that says string hasn't been initiated yet
27         ;
28         011444  005005      5$:    CLR    R5          ;Nothing sent yet
29         ;
30         ; Begin loop to decide what values need to be sent
31         ;
32         011446  012701  011574'      MOV    #DECAT,R1      ;Point to attribute table
33         ;
34         ; See if next attribute needs to be selected
35         ;
36         011452  036103  0000002      1$:    BIT    2(R1),R3      ;Is this attribute needed?
37         011456  001431                BEQ    4$          ;Br if not
38         ;
39         ; We need to select this attribute, see if we need to send
40         ; CSI to start the string or semicolon to separate parameter values
41         ;
42         011460  005705                TST    R5          ;Have we initiated the string?
43         011462  001010                BNE    2$          ;Br if yes
44         011464  004737  012272'      CALL   GENCSI       ;Send CSI character
45         011470                SEND   #'?'         ;Send question mark
46         011500  005205                INC    R5          ;Remember string started
47         011502  000404                BR     3$          ;
48         011504      2$:    SEND   #SEMI       ;Send semicolon
49         ;
50         ; Now send the parameter value to selete the attribute
51         ;
52         011514  011100      3$:    MOV    (R1),R0      ;Get parameter value for attribute
53         011516  004737  012334'      CALL   GENVAL       ;Convert value to digit string and send
54         ;
55         ; If this is a VT100, terminate the string for each attribute.
56         ;
57         011522  032762  0000000 0000000      BIT    #AW$200,DW$AW(R2); VT200?

```

GENDAS -- Generate control sequence for DEC attributes

```

58 011530 001004          BNE      4$          ;Br if yes
59 011532                SEND      R4          ;Send terminating character
60 011540 005005          CLR       R5          ;Say string is not in progress
61                          ;
62                          ; See if more attributes need to be selected
63                          ;
64 011542 062701 000004 4$:  ADD      #4,R1          ;Point to next attribute entry
65 011546 005711          TST      (R1)         ;Reached end of table?
66 011550 001340          BNE      1$          ;Loop if not
67                          ;
68                          ; If we started the string, terminate it
69                          ;
70 011552 005705          TST      R5          ;Did we start the string?
71 011554 001403          BEQ      9$          ;Br if not
72 011556                SEND      R4          ;Send terminating character
73                          ;
74                          ; Finished
75                          ;
76 011564 012605          9$:  MOV      (SP)+,R5
77 011566 012603          MOV      (SP)+,R3
78 011570 012601          MOV      (SP)+,R1
79 011572 000207          RETURN
80                          ;
81                          ;-----
82                          ; Table of attribute values and DEC attribute flags
83                          ;
84 011574 000001 0000000 DECAT: .WORD 1,AW$ACK      ;Application mode for cursor keys
85 011600 000003 0000000 .WORD 3,AW$132         ;132 column mode
86 011604 000005 0000000 .WORD 5,AW$REV        ;Reverse video mode
87 011610 000010 0000000 .WORD 8,AW$RPT        ;Automatic keypad repeat
88 011614 000031 0000000 .WORD 25,AW$VCR       ;Make cursor visible
89 011620 000000          .WORD 0          ;End of table

```

GENLAF -- Generate terminal sequence to set line attrib

```

1          .SBTTL  GENLAF -- Generate terminal sequence to set line attrib
2          ;-----
3          ; Generate the terminal control sequence needed to set the line attribute.
4          ;
5          ; Inputs:
6          ; RO = Line attribute flags (AL$xxx)
7          ;
8 011622 010546 GENLAF: MOV     R5, -(SP)
9 011624 010005         MOV     RO, R5          ;Get attribute flags
10         ;
11         ; See if double height wanted
12         ;
13 011626 032705 0000000 BIT     #<AL$DHT!AL$DHB>, R5; Double high wanted?
14 011632 001422         BEQ     1$,          ;Br if not
15 011634 004737 012260' CALL    GENESC          ;Send ESC
16 011640         SEND    #'#          ;Send "#"
17 011650 032705 0000000 BIT     #AL$DHT, R5      ;Top or bottom half of char?
18 011654 001405         BEQ     2$,          ;Br if bottom
19 011656         SEND    #'3          ;Send 3
20 011666 000404         BR      1$,          ;
21 011670         2$: SEND    #'4          ;Send 4
22         ;
23         ; See if double width is wanted
24         ;
25 011700 032705 0000000 1$: BIT     #AL$DWD, R5      ;Is double width wanted?
26 011704 001412         BEQ     9$,          ;Br if not
27 011706 004737 012260' CALL    GENESC          ;Send ESC
28 011712         SEND    #'#          ;Send "#"
29 011722         SEND    #'6          ;Send 6
30         ;
31         ; Finished
32         ;
33 011732 012605 9$: MOV     (SP)+, R5
34 011734 000207         RETURN

```

GENSPC -- Generate sequence to move cursor over

```

1          .SBTTL  GENSPC -- Generate sequence to move cursor over
2          ;-----
3          ; Generate spaces or a control sequence to move the cursor right
4          ; from the current cursor position (specified by DW$COL(R2)) to
5          ; a specified column.
6          ;
7          ; Inputs:
8          ; R2 = Pointer to window control block
9          ; R1 = Column number we are to move to
10         ;
11 011736 010346 GENSPC: MOV      R3,-(SP)
12         ;
13         ; Determine how many columns we want to move over
14         ;
15 011740 010103         MOV      R1,R3          ;Get destination column
16 011742 166203 0000006 SUB      DW$COL(R2),R3      ;Subtract current column number
17 011746 003452         BLE      9$           ;Br if don't need to move at all
18         ;
19         ; If we need to move no more than 5 columns, output spaces
20         ;
21 011750 020327 0000005 CMP      R3,#5             ;Need to move more than 5 columns?
22 011754 003006         BGT      2$           ;Br if yes
23 011756 1$: SEND     #40          ;Send a space
24 011766 077305         SOB      R3,1$        ;Loop to send more
25 011770 000441         BR       9$           ;Finished
26         ;
27         ; We need to move more than 5 columns; generate control sequence.
28         ; Determine terminal type.
29         ;
30 011772 032762 0000000 0000006 2$: BIT      #<AW$52!AW$S52>,DW$AW(R2);VT52 terminal?
31 012000 001012         BNE      5$           ;Br if VT52
32         ;
33         ; Generate control sequence for VT100
34         ;
35 012002 004737 012272' CALL     GENCSI           ;Generate CSI header
36 012006 010300         MOV      R3,R0          ;Get # columns we need to move
37 012010 004737 012334' CALL     GENVAL          ;Convert and output that value
38 012014         SEND     #'C           ;Terminate control sequence
39 012024 000423         BR       9$
40         ;
41         ; Generate control sequence for VT52
42         ;
43 012026 004737 012260' 5$: CALL     GENESC          ;Generate escape
44 012032         SEND     #'Y           ;Start of cursor addressing sequence
45 012042 016200 0000006 MOV      DW$LIN(R2),R0     ;Get current line number
46 012046 062700 0000037 ADD      #37,R0          ;Form ascii char for line number
47 012052         SEND     R0           ;Send it
48 012060 010100         MOV      R1,R0          ;Get wanted column number
49 012062 062700 0000037 ADD      #37,R0          ;Form ascii char for column number
50 012066         SEND     R0           ;Send it
51         ;
52         ; Change current column number
53         ;
54 012074 010162 0000006 9$: MOV      R1,DW$COL(R2) ;Say we have moved up to this column
55         ;
56         ; Finished
57         ;

```

58 012100 012603
59 012102 000207

MOV (SP)+, R3
RETURN

GENCSR -- Generate cursor addressing sequence

```

1          .SBTTL  GENCSR -- Generate cursor addressing sequence
2          ;-----
3          ; Generate the appropriate terminal control sequence to move the
4          ; cursor to the current line and column.
5          ;
6          ; Inputs:
7          ; R2 = Pointer to window control block
8          ; DW$LIN(R2) = Current line number
9          ; DW$COL(R2) = Current column number
10         ;
11 012104  GENCSR:
12         ;
13         ; Determine what type of terminal this is
14         ;
15 012104  032762  000000C  000000G          BIT      #<AW$52!AW$552>,DW$AW(R2);Is this a VT52?
16 012112  001035          BNE      5$          ;Br if VT52
17         ;
18         ; Generate sequence for a VT100
19         ;
20 012114  004737  012272'          CALL     GENCSI          ;Generate CSI character
21 012120  016200  000000G          MOV      DW$LIN(R2),RO      ;Get line number
22 012124  032762  000000G  000000G          BIT      #AW$ORS,DW$AW(R2);Is origin relative to scroll region?
23 012132  001406          BEQ      1$          ;Br if not
24 012134  166200  000000G          SUB      DW$SRT(R2),RO      ;Subtract top line of scroll region
25 012140  005200          INC      RO              ;1st line is 1
26 012142  003002          BGT      1$          ;Br if we are within scroll region
27 012144  012700  000001          MOV      #1,RO            ;Force to 1st line of scroll region
28 012150  004737  012334'          1$:     CALL     GENVAL          ;Convert to ascii digit string
29 012154          SEND     #SEMI          ;Send semicolon
30 012164  016200  000000G          MOV      DW$COL(R2),RO      ;Get column number
31 012170  004737  012334'          CALL     GENVAL          ;Convert to ascii digit string
32 012174          SEND     #'H          ;Terminate sequence
33 012204  000424          BR      9$
34         ;
35         ; Generate control sequence for VT52
36         ;
37 012206  004737  012260'          5$:     CALL     GENESC          ;Generate escape
38 012212          SEND     #'Y          ;Start of cursor addressing sequence
39 012222  016200  000000G          MOV      DW$LIN(R2),RO      ;Get current line number
40 012226  062700  000037          ADD      #37,RO            ;Form ascii char for line number
41 012232          SEND     RO              ;Send it
42 012240  016200  000000G          MOV      DW$COL(R2),RO      ;Get current column number
43 012244  062700  000037          ADD      #37,RO            ;Form ascii char for column number
44 012250          SEND     RO              ;Send it
45         ;
46         ; Finished
47         ;
48 012256  000207          9$:     RETURN

```

GENESC -- Generate escape character

```

1          .SBTTL  GENESC -- Generate escape character
2          ;-----
3          ; Send an escape character to the terminal
4          ;
5 012260   GENESC: SEND   #33          ;Send escape to the terminal
6 012270   000207   RETURN
7
8          .SBTTL  GENCSI -- Generate CSI character sequence
9          ;-----
10         ; Send a CSI (ESC [) sequence to the terminal.
11         ;
12 012272   GENCSI:
13         ;
14         ; Send 8-bit CSI character to VT200 terminals
15         ;
16         ;     BIT      #AW$200,DW$AW(R2); Is this a VT200 terminal?
17         ;     BEQ      1$          ;Br if not
18         ;     SEND     #CSICHR     ;Send 8-bit CSI character to VT200
19         ;     BR       9$
20         ;
21         ; Send ESC [ to VT100 terminals
22         ;
23 012272   1$:      SEND     #33          ;Send escape
24 012302   SEND     #'[             ;Send "["
25         ;
26         ; Finished
27         ;
28 012312   000207   9$:      RETURN
29
30         .SBTTL  GENCHR -- Send a character to the terminal
31         ;-----
32         ; Send a single character to the terminal
33         ;
34         ; Inputs:
35         ;   R0 = Character to be sent
36         ;   R2 = Pointer to window control block
37         ;
38 012314   010146   GENCHR: MOV     R1,-(SP)
39 012316   116201   0000006   MOVB   DW$JOB(R2),R1 ;Get # of job we are sending to
40 012322   DCALL   BUFCHR     ;Send the character
41 012330   012601   MOV     (SP)+,R1
42 012332   000207   RETURN

```

GENVAL -- Convert value to digits and send

```

1          .SBTTL  GENVAL -- Convert value to digits and send
2          ;-----
3          ; Convert a binary value to an ascii digit string and send to the
4          ; terminal.
5          ;
6          ; Inputs:
7          ; R0 = Value to be converted and sent
8          ;
9 012334 010446 GENVAL: MOV     R4,-(SP)
10 012336 010546      MOV     R5,-(SP)
11 012340 010005      MOV     R0,R5      ;Get value to be converted
12          ;
13          ; Convert to digits and stack the digits
14          ;
15 012342 005046      CLR     -(SP)      ;Store null on stack to indicate end
16 012344 005004 1$:  CLR     R4          ;Clear high-order for divide
17 012346 071427 000012 DIV     #10,R4      ;Divide R4-R5 by 10.
18 012352 062705 000060 ADD     #'0,R5      ;Convert remainder to ascii digit
19 012356 010546      MOV     R5,-(SP)      ;Stack the character
20 012360 010405      MOV     R4,R5      ;Get quotient
21 012362 001370      BNE     1$          ;Loop if more digits to convert
22          ;
23          ; Now pop the digits and send them
24          ;
25 012364 012600 2$:  MOV     (SP)+,R0      ;Get next char to send
26 012366 001404      BEQ     9$          ;Br if finished
27 012370      SEND     R0          ;Send a digit
28 012376 000772      BR     2$          ;Send rest of number
29          ;
30          ; Finished
31          ;
32 012400 012605 9$:  MOV     (SP)+,R5
33 012402 012604      MOV     (SP)+,R4
34 012404 000207      RETURN

```

EMTWIN -- Dispatch window control EMT's

```

1          .SBTTL  EMTWIN -- Dispatch window control EMT's
2          ;-----
3          ; EMTWIN is entered from EMT processing when a window control EMT
4          ; is executed.  It dispatches control to the correct processing
5          ; routine based on the subfunction code.
6          ;
7          ; Inputs:
8          ; R1 = Job index number
9          ; EMTBLK = EMT argument block
10         ;
11 012406  EMTWIN:
12         ;
13         ; Ignore window control EMT's if this is a detached job
14         ;
15 012406  113700  0000000  MOVB    EMTBLK,RO    ;Get EMT subfunction code
16 012412  020027  0000006  CMP     RO,#6      ;Read-window-data function?
17 012416  001407                BEQ     2$         ;Br if yes -- OK for detached jobs
18 012420  032761  0000000 0000000  BIT     ##DEATCH,LSW(R1) ;Is this a detached job?
19 012426  001403                BEQ     2$         ;Br if not
20 012430  005000                CLR     RO         ;Return error 0 for detached job
21 012432  000137  0000000  JMP     SETERR
22         ;
23         ; Get EMT subfunction code and make sure it is valid
24         ;
25 012436  006300  2$:      ASL     RO         ;Convert subfun code to word table index
26 012440  020027  0000020  CMP     RO,#MAXSFC ;Is the subfunction code valid?
27 012444  103403                BLO     1$         ;Br if yes
28 012446  005000                CLR     RO         ;Return error code 0 if not
29 012450  000137  0000000  JMP     SETERR
30         ;
31         ; Enter processing routine
32         ;
33 012454  000170  012460'  1$:      JMP     @WINVEC(RO) ;Enter processing routine
34         ;
35         ; Branch vector for subfunction codes
36         ;
37 012460  012500'  WINVEC: .WORD  WFNEW    ;0 - Create a new window
38 012462  013170'          .WORD  WFMAP    ;1 - Select a window
39 012464  013236'          .WORD  WFDEL    ;2 - Delete a window
40 012466  013350'          .WORD  WFSPND   ;3 - Suspend window processing
41 012470  013370'          .WORD  WFRSUM   ;4 - Resume window processing
42 012472  013410'          .WORD  WFPRNT   ;5 - Print the specified window
43 012474  013456'          .WORD  WFPREAD  ;6 - Read window data into program buffer
44 012476  013740'          .WORD  WFSTT    ;7 - Set terminal type
45         000020  MAXSFC = .-WINVEC ;Highest branch vector index
46

```

WFNEW -- EMT to create a new window

```

1          .SBTTL  WFNEW  -- EMT to create a new window
2          ;-----
3          ; WINNEW is the EMT used to define a new window.
4          ; The form of the EMT argument block is:
5          ;
6          ;       .BYTE  0,161
7          ;       .BYTE  window_number,perm_flag
8          ;       .BYTE  window_width,max_scroll
9          ;       .WORD  copy_window,copy_job
10         ;       .WORD  0
11         ;
12         ; Inputs:
13         ; R1 = Job index number
14         ; EMTBLK = EMT argument block
15         ;
16 012500  WFNEW:
17         ;
18         ; If a window with this number already exists for this job, delete it.
19         ;
20 012500  113702  0000020  MOV  EMTBLK+2,R2      ;Get specified window number
21 012504  004737  014140'  CALL WINSRC        ;Try to locate window control block
22 012510  103402                BCS  1$           ;Br if that window not currently defined
23 012512  004737  014104'  CALL  WINDEL      ;Delete the window
24         ;
25         ; Try to find a free window control block
26         ;
27 012516  013702  000002'  1$:  MOV  DWBAS,R2      ;Point to 1st window control block
28 012522  105762  0000000  2$:  TSTB DW$JOB(R2)   ;Is this block free?
29 012526  001411                BEQ  5$           ;Br if yes
30 012530  062702  0000000  ADD  #DW$$SZ,R2     ;Point to next window block
31 012534  020237  000004'  CMP  R2,DWEND      ;Checked all blocks?
32 012540  103770                BLO  2$           ;Br if yes
33 012542  012700  000001  MOV  #1,R0         ;Return error 0 if no free blocks
34 012546  000137  0000000  JMP  SETERR
35         ;
36         ; Initialize the window control block
37         ;
38 012552  012700  0000000  5$:  MOV  #DW$$SZ/2,R0  ;Get # words in window block
39 012556  010203                MOV  R2,R3        ;Get pointer to control block
40 012560  005023  3$:  CLR  (R3)+         ;Zero the entire block
41 012562  077002                SOB  R0,3$
42 012564  110162  0000000  MOV  R1,DW$JOB(R2) ;Set our job number
43 012570  113762  0000020 0000000  MOV  EMTBLK+2,DW$ID(R2);Set window ID number
44 012576  012762  0000000 0000000  MOV  #<AW$VCR!AW$RPT>,DW$AW(R2);Initialize window attribute flags
45 012604  113700  0000040  MOV  EMTBLK+4,R0   ;Get # columns per line
46 012610  042700  177400  BIC  #^C<377>,R0  ;Kill sign extension
47 012614  001002                BNE  11$         ;Br if width not zero
48 012616  012700  000120  MOV  #80.,R0      ;Set width to 80
49 012622  020027  000204  11$:  CMP  R0,#132.   ;Compare with max width allowed
50 012626  101402                BLOS 12$        ;Br if ok
51 012630  012700  000204  MOV  #132.,R0    ;Constrain to 132
52 012634  010062  0000000  12$:  MOV  R0,DW$CPL(R2) ;Set number of columns per line
53 012640  012762  000030  0000000  MOV  #24.,DW$LPP(R2);Set number of lines per page
54 012646  113762  0000050 0000000  MOV  EMTBLK+5,DW$MSL(R2);Set max-scrolled-lines parameter
55 012654  012762  000001  0000000  MOV  #1,DW$TLN(R2) ;Say line 1 is at top of buffer
56 012662  012762  000001  0000000  MOV  #1,DW$SRT(R2) ;Say line 1 is top of scrolling region
57 012670  016262  0000000 0000000  MOV  DW$LPP(R2),DW$SRB(R2);scrolling region goes to end of page

```

```

58 ;
59 ; Initialize terminal type
60 ;
61 012676 004737 013774' CALL WINSTT ;Set correct terminal type
62 ;
63 ; Initialize character set mapping for a VT200
64 ;
65 012702 032761 000000C 000000G BIT #<VT2007!VT2008>,LTRMTP(R1);Is terminal a VT200?
66 012710 001411 BEQ 7$ ;Br if not
67 012712 112762 000001 000000G MOVB #1,DW$G2M(R2) ;Map G2 to DEC supplemental chars
68 012720 112762 000001 000000G MOVB #1,DW$G3M(R2) ;Map G3 to DEC supplemental chars
69 012726 112762 000002 000000G MOVB #2,DW$GRM(R2) ;Map GR to G2
70 ;
71 ; Set application keypad mode if Single line editor is in KED mode
72 ;
73 012734 032761 000000G 000000G 7$: BIT ##SLON,LSW7(R1) ;Is single-line editor turned on?
74 012742 001407 BEQ 10$ ;Br if not
75 012744 032761 000000G 000000G BIT ##SLKED,LSW7(R1);Is SL in KED mode?
76 012752 001403 BEQ 10$ ;Br if not
77 012754 052762 000000G 000000G BIS #AW$AKM,DW$AW(R2);Set application keypad mode
78 ;
79 ; See if this window should be permanent
80 ;
81 012762 105737 000003G 10$: TSTB EMTBLK+3 ;Is permanent-window flag set?
82 012766 001403 BEQ 8$ ;Br if not
83 012770 052762 000000G 000000G BIS #AW$PRM,DW$AW(R2);Remember window is permanent
84 ;
85 ; See if we should copy any window attributes from an existing window
86 ;
87 012776 005737 000006G 8$: TST EMTBLK+6 ;Should we copy attributes from another windo?
88 013002 001443 BEQ 13$ ;Br if not
89 013004 010203 MOV R2,R3 ;Save addr of new window control block
90 013006 013702 000006G MOV EMTBLK+6,R2 ;Get window_id and job number
91 013012 010201 MOV R2,R1
92 013014 042702 177400 BIC #^C<377>,R2 ;Clear all but window ID
93 013020 000301 SWAB R1 ;Get job # to low-order byte
94 013022 042701 177400 BIC #^C<377>,R1 ;Clear all but job number
95 013026 006301 ASL R1 ;Get job index number
96 013030 001002 BNE 14$ ;Br if job number specified
97 013032 113701 000000G MOVB CORUSR,R1 ;Assume current job
98 013036 004737 014140' 14$: CALL WINSRC ;Try to find existing window control block
99 013042 103422 BCS 15$ ;Br if could not find one
100 013044 016263 000000G 000000G MOV DW$LPP(R2),DW$LPP(R3) ;Copy # lines per page
101 013052 016263 000000G 000000G MOV DW$CPL(R2),DW$CPL(R3) ;Copy # columns per line
102 013060 116263 000000G 000000G MOVB DW$MSL(R2),DW$MSL(R3) ;Copy max # scroll lines
103 013066 016200 000000G MOV DW$AW(R2),R0 ;Get window attribute flags
104 013072 042700 000000C BIC #^C<AW$132!AW$REV>,R0 ;Leave only ones to be copied
105 013076 042763 000000C 000000G BIC #<AW$132!AW$REV>,DW$AW(R3) ;Clear in new control block
106 013104 050063 000000G BIS R0,DW$AW(R3) ;Transfer the flags
107 013110 010302 15$: MOV R3,R2 ;Get back address of new window control block
108 ;
109 ; Create a named local region for the screen buffer for the window
110 ;
111 013112 004737 014204' 13$: CALL MAKWSB ;Make a window screen buffer
112 013116 103006 BCC 4$ ;Br if we made the region
113 013120 004737 014104' CALL WINDEL ;Delete the window
114 013124 012700 000002 MOV #2,R0 ;Return error code 2

```

```
115 013130 000137 0000000      JMP      SETERR
116                               ;
117                               ; Clear entire screen contents to blanks
118                               ;
119 013134 004737 006210'      4*:     CALL      ERSPAG      ; Clear all positions to spaces
120                               ;
121                               ; Set line 1, column 1 as cursor position
122                               ;
123 013140 012700 000001      MOV      #1,R0      ; Get value 1
124 013144 110062 0000000      MOVB    R0,DW$SLN(R2) ; Init saved line # to 1
125 013150 110062 0000000      MOVB    R0,DW$SCL(R2) ; Init saved column # to 1
126 013154 010062 0000000      MOV      R0,DW$COL(R2) ; Set column = 1
127 013160 004737 006702'      CALL    SETLIN      ; Set line =1
128                               ;
129                               ; Finished
130                               ;
131 013164 000137 0000000      JMP      EMTXIT
```

WFMAP -- EMT to select a window as the current window

```

1          .SBTTL  WFMAP  -- EMT to select a window as the current window
2          ;-----
3          ; Select a window as the current window for the job and refresh
4          ; the display screen from the window contents.
5          ;
6          ; Inputs:
7          ;   R1 = Job index number
8          ;   EMTBLK = EMT argument block
9          ;
10         WFMAP:
11         ;
12         ; If current window number is zero, switch back to no window
13         ;
14         013170  013702  0000020      MOV      EMTBLK+2,R2      ;Get specified window number
15         013174  001003                BNE      2$              ;Br if some window specified
16         013176  005061  0000000      CLR      LWINDO(R1)      ;Say we are not doing windowing
17         013202  000413                BR       9$
18         ;
19         ; Locate the window control block for the specified window
20         ;
21         013204  004737  014140'      2$:      CALL     WINSRC      ;Find window control block
22         013210  103004                BCC      1$              ;Br if found it
23         013212  012700  0000003      MOV      #3,R0          ;Error 3 if not
24         013216  000137  0000000      JMP      SETERR
25         ;
26         ; Set this window as the current window for the job
27         ;
28         013222  010261  0000000      1$:      MOV      R2,LWINDO(R1) ;Say this is current window for job
29         ;
30         ; Refresh the display from selected window
31         ;
32         013226  004737  007064'      CALL     REFRSH        ;Refresh display from window contents
33         ;
34         ; Finished
35         ;
36         013232  000137  0000000      9$:      JMP      EMTXIT

```

WFDEL -- EMT to delete a window

```

1          .SBTTL  WFDEL  -- EMT to delete a window
2          ;-----
3          ; EMT to delete a window.
4          ;
5          ; Inputs:
6          ; R1 = Job index number
7          ;
8 013236   WFDEL:
9          ;
10         ; Try to locate control block for the window
11         ;
12 013236   113702   0000020   MOVB    EMTBLK+2,R2    ;Get specified window number
13 013242   001406   BEQ      3$          ;Br if window number is zero
14 013244   120227   177777   CMPB    R2,#-1       ;Is window number -1?
15 013250   001024   BNE     2$          ;Br if not
16         ;
17         ; Delete all windows for job (temp and permanent)
18         ;
19 013252   004737   014052'   CALL    WINREL      ;Release all windows for the job
20 013256   000432   BR      9$
21         ;
22         ; Window number zero means delete all temporary windows
23         ;
24 013260   013702   000002'   3$:    MOV     DWBAS,R2    ;Point to 1st window control block
25 013264   120162   0000000   5$:    CMPB   R1,DW$JOB(R2) ;Does this window belong to our job?
26 013270   001006   BNE     4$          ;Br if not
27 013272   032762   0000000 0000000   BIT     #AW$PRM,DW$AW(R2);Is this a perm or temp window?
28 013300   001002   BNE     4$          ;Br if permanent window
29 013302   004737   014104'   CALL    WINDEL      ;Delete this window
30 013306   062702   0000000   4$:    ADD     #DW$$SZ,R2    ;Point to next window control block
31 013312   020237   000004'   CMP     R2,DWEND     ;Checked all?
32 013316   103762   BLD     5$          ;Br if not
33 013320   000411   BR      9$
34         ;
35         ; We are deleting a specific window
36         ;
37 013322   004737   014140'   2$:    CALL    WINSRC      ;Try to locate window control block
38 013326   103004   BCC     1$          ;Br if located the window control block
39 013330   012700   000003   MOV     #3,R0        ;Error code 3 if cannot locate window
40 013334   000137   0000000   JMP     SETERR
41         ;
42         ; Delete the window
43         ;
44 013340   004737   014104'   1$:    CALL    WINDEL      ;Delete the window
45         ;
46         ; Finished
47         ;
48 013344   000137   0000000   9$:    JMP     EMTXIT

```

WFSPND -- Suspend window processing

```

1          .SBTTL  WFSPND -- Suspend window processing
2          ;-----
3          ; Suspend window processing.  After executing this emt, window
4          ; processing is suspended.  Characters are passed through to the
5          ; screen without being processed by the window routine.
6          ;
7          ; Inputs:
8          ; R1 = Job index number
9          ;
10         013350 016102 0000000  WFSPND: MOV     LWINDO(R1),R2  ;Get pointer to current window control block
11         013354 001403          BEQ     9$                ;Br if job has no window active now
12         013356 052762 0000000 0000000  BIS     #AW$SPN,DW$AW(R2);Set flag suspending window processing
13         013364 000137 0000000 9$:      JMP     EMTXIT          ;Finished
14
15         .SBTTL  WFRSUM -- Resume window processing
16         ;-----
17         ; Resume window processing.
18         ;
19         ; Inputs:
20         ; R1 = Job index number
21         ;
22         013370 016102 0000000  WFRSUM: MOV     LWINDO(R1),R2  ;Get pointer to current window control block
23         013374 001403          BEQ     9$                ;Br if job has no window active now
24         013376 042762 0000000 0000000  BIC     #AW$SPN,DW$AW(R2);Say window no longer suspended
25         013404 000137 0000000 9$:      JMP     EMTXIT          ;Finished

```

WFPRNT -- Cause contents of a window to be printed

```

1          .SBTTL  WFPRNT -- Cause contents of a window to be printed
2          ;-----
3          ; Cause the contents of a window for the current job to be printed.
4          ;
5          ; Inputs:
6          ;   R1 = Job index number
7          ;
8          ; EMT argument block:
9          ;
10         ;   .BYTE  5,161
11         ;   .BYTE  window_id,0
12         ;
13 013410  WFPRNT:
14         ;
15         ; Locate the window control block for the specified window
16         ;
17 013410  113702  0000020      MOVB   EMTBLK+2,R2      ;Get specified window ID
18 013414  001403              BEQ    3$              ;Zero is invalid
19 013416  004737  014140'     CALL   WINSRC        ;Find window control block
20 013422  103004              BCC   1$              ;Br if found it
21 013424  012700  000003     3$:   MOV   #3,R0      ;Error 3 if invalid window ID
22 013430  000137  0000000     JMP   SETERR
23         ;
24         ; Print this window
25         ;
26 013434  004737  014710'     1$:   CALL  WINPRT      ;Try to print the window
27 013440  103004              BCC   9$              ;Br if successful
28 013442  012700  000004     MOV   #4,R0      ;Error 4 if can't print
29 013446  000137  0000000     JMP   SETERR
30         ;
31         ; Finished
32         ;
33 013452  000137  0000000     9$:   JMP   EMTXIT

```

```

1          .SBTTL  WFREAD -- Copy window information to program buffer
2          ;-----
3          ; Copy window data into buffer in program area.
4          ;
5          ; EMT argument block:
6          ;
7          ;     .BYTE  6,161
8          ;     .BYTE  window_id,job_number
9          ;     .WORD  buffer_address
10         ;     .WORD  buffer_size
11         ;
12 013456  WFREAD:
13         ;
14         ; Make sure specified buffer address and size is ok
15         ;
16 013456  013700  0000040  MOV     EMTBLK+4,R0    ;Get base address of buffer
17 013462  004737  0000000  CALL   VALADW        ;Make sure it's ok
18 013466  063700  0000060  ADD    EMTBLK+6,R0   ;Add specified size
19 013472  004737  0000000  CALL   VALADB        ;Make sure end is ok too
20         ;
21         ; Get the number of the job whose window we want to read
22         ;
23 013476  113701  0000030  MOVB   EMTBLK+3,R1   ;Get specified job number
24 013502  006301  ; ASL    R1            ;Convert to job index number
25 013504  001002  ; BNE   1$           ;Br if job number specified
26 013506  113701  0000000  MOVB   CORUSR,R1    ;Get current job index number
27 013512  120137  0000000  1$:  CMPB  R1,CORUSR   ;Are we reading window for our job?
28 013516  001410  ; BEQ   5$           ;Br if yes
29 013520  032737  0000000  0000000  BIT    #P2#CXT,PRIVC2 ;Do we have GETCXT privilege?
30 013526  001004  ; BNE   5$           ;Br if yes
31 013530  012700  0000001  MOV    #1,R0        ;Error 1 if not
32 013534  000137  0000000  JMP    SETERR
33         ;
34         ; Find the specified window control block
35         ;
36 013540  113702  0000020  5$:  MOVB   EMTBLK+2,R2   ;Get window ID
37 013544  004737  014140'  CALL   WINSRC        ;Search for specified window
38 013550  103004  ; BCC   2$           ;Br if found the window control blk
39 013552  012700  0000003  MOV    #3,R0        ;Invalid window ID
40 013556  000137  0000000  JMP    SETERR
41         ;
42         ; Determine how much data must be copied
43         ;
44 013562  016203  0000000  2$:  MOV    DW$LPP(R2),R3 ;Get # lines on page
45 013566  070362  0000000  MUL   DW#CPL(R2),R3 ;Times # columns per line
46 013572  006303  ; ASL   R3            ;Need two bytes for each char cell
47 013574  066203  0000000  ADD   DW$LPP(R2),R3 ;Add space used by line attrib vector
48 013600  005203  ; INC   R3            ;Round up to next word
49 013602  042703  0000001  BIC   #1,R3
50 013606  010300  ; MOV   R3,R0        ;Get # bytes of window buffer data
51 013610  062700  0000006  ADD   #3*2,R0       ;Add # bytes for parameter words
52 013614  020037  0000060  CMP   R0,EMTBLK+6   ;Is buffer large enough?
53 013620  101404  ; BLOS  3$           ;Br if yes
54 013622  012700  0000004  MOV   #4,R0        ;Error 4 if buffer too small
55 013626  000137  0000000  JMP   SETERR
56         ;
57         ; Copy some window parameter information before actual window buffer

```

```

58 ;
59 013632 013705 0000040 3#: MOV EMTBLK+4,R5 ;Get address of user's buffer
60 013636 016246 0000000 MOV DW$TLN(R2),-(SP);Store top line number
61 013642 106625 MTPD (R5)+
62 013644 016246 0000000 MOV DW$LPP(R2),-(SP);Store # lines per page
63 013650 106625 MTPD (R5)+
64 013652 016246 0000000 MOV DW$CPL(R2),-(SP);Store # columns per line
65 013656 106625 MTPD (R5)+
66 ;
67 ; Copy data from window region to user's buffer
68 ;
69 013660 006203 ASR R3 ;Get # words to copy
70 013662 012704 0000000 MOV #VPAR6,R4 ;Get virt address of window region
71 013666 4#: BUFMAP ;;;Map to window region
72 013710 012400 MOV (R4)+,R0 ;;;Get a word from screen region
73 013712 UNMAP ;Restore mapping
74 013726 010046 MOV R0,-(SP) ;Push word we are transferring
75 013730 106625 MTPD (R5)+ ;Store data into user's buffer
76 013732 077323 SOB R3,4# ;Loop if more data to copy
77 ;
78 ; Finished
79 ;
80 013734 000137 0000000 JMP EMTXIT
  
```

WFSTT -- EMT to set terminal type for windowing

```

1          .SBTTL  WFSTT  -- EMT to set terminal type for windowing
2          ;-----
3          ; Reset the terminal type for all windows being used by this job.
4          ;
5          ; Inputs:
6          ; R1 = Job index number.
7          ;
8 013740   WFSTT:
9          ;
10         ; Begin loop to process all windows belonging to this job
11         ;
12 013740  013702  000002'      MOV     DWBAS,R2      ;Point to 1st window control block
13 013744  120162  0000000     1$:   CMPB   R1,DW$JOB(R2)  ;Does this one belong to this job?
14 013750  001002              BNE     2$          ;Br if not
15 013752  004737  013774'      CALL  WINSTT      ;Reset terminal type for this window
16 013756  062702  0000000     2$:   ADD    #DW$$SZ,R2    ;Point to next window control block
17 013762  020237  000004'      CMP    R2,DWEND   ;Checked all?
18 013766  103766              BLO    1$          ;Loop if not
19         ;
20         ; Finished
21         ;
22 013770  000137  0000000     JMP    EMTXIT

```

WINSTT -- Set terminal type for a window

```

1          .SBTTL  WINSTT -- Set terminal type for a window
2          ;-----
3          ; WINSTT sets up the terminal type in the window control block
4          ; attribute word based on the terminal type specified for the job.
5          ;
6          ; Inputs:
7          ; R2 = Pointer to window control block
8          ;
9 013774  010146  WINSTT: MOV     R1,-(SP)
10 013776  116201  0000000  MOVB    DW#JOB(R2),R1 ;Get job index number
11          ;
12          ; Determine terminal type based on line type
13          ;
14 014002  042762  0000000 0000000  BIC     #<AW$52!AW$200>,DW$AW(R2) ;Say not VT52 and not VT200
15          ;
16          ; See if terminal is a VT52
17          ;
18 014010  032761  0000000 0000000  BIT     #VT52,LTRMTP(R1);Is this a VT52?
19 014016  001404          BEQ     1$ ;Br if not
20 014020  052762  0000000 0000000  BIS     #AW$52,DW$AW(R2);Set VT52 as terminal type
21 014026  000407          BR      9$
22          ;
23          ; See if terminal is a VT200
24          ;
25 014030  032761  0000000 0000000 1$: BIT     #<VT2007!VT2008>,LTRMTP(R1) ;VT200 terminal?
26 014036  001403          BEQ     9$ ;Br if not
27 014040  052762  0000000 0000000  BIS     #AW$200,DW$AW(R2);Set VT200 as terminal type
28          ;
29          ; Finished
30          ;
31 014046  012601  9$: MOV     (SP)+,R1
32 014050  000207          RETURN

```

WINREL --- Release all display windows for a job

```

1          .SBTTL  WINREL --- Release all display windows for a job
2          ;-----
3          ; Release all display windows for the current job.
4          ;
5          ; Inputs:
6          ; R1 = Job index number for job whose windows are to be released.
7          ;
8 014052   WINREL:
9          ;
10         ; Begin loop to search for window control blocks belonging to this
11         ; job.
12         ;
13 014052  013702  000002'      MOV     DWBAS,R2      ;Point to first window control block
14 014056  120162  0000000     1$:    CMPB   R1,DW$JOB(R2)  ;Is this one belong to our job?
15 014062  001002              BNE     2$          ;Br if not
16 014064  004737  014104'      CALL  WINDEL      ;Delete the windoe
17 014070  062702  0000000     2$:    ADD   #DW#$SZ,R2  ;Point to next window control block
18 014074  020237  000004'      CMP   R2,DWEND   ;Checked all?
19 014100  103766              BLO   1$          ;Loop if not
20         ;
21         ; Finished
22         ;
23 014102  000207              RETURN

```

WINDEL -- Delete a window

```

1          .SBTTL  WINDEL -- Delete a window
2          ;-----
3          ; Delete a window and release its screen buffer region.
4          ;
5          ; Inputs:
6          ;   R2 = Pointer to window control block
7          ;
8 014104   WINDEL:
9          ;
10         ; If this is the current window, reset window info for job
11         ;
12 014104   116200   0000000   MOVB    DW#JOB(R2),R0   ;Get # of job that owns this window
13 014110   020260   0000000   CMP     R2,LWINDO(R0)  ;Is this current window for the job?
14 014114   001002           BNE     1$              ;Br if not
15 014116   005060   0000000   CLR    LWINDO(R0)     ;Say job is not doing windowing
16         ;
17         ; Free the region used for the screen buffer
18         ;
19 014122   004737   014514'   1$:    CALL   FREWSB      ;Free the window screen buffer
20         ;
21         ; Free the window control block
22         ;
23 014126   105062   0000000   CLRB   DW#ID(R2)      ;Say block is free
24 014132   105062   0000000   CLRB   DW#JOB(R2)     ;Say no job using block
25         ;
26         ; Finished
27         ;
28 014136   000207           RETURN

```

WINSRC -- Locate control block for a window

```

1          .SBTTL  WINSRC -- Locate control block for a window
2          ;-----
3          ; Locate a window control block for a specified window for the current
4          ; job.
5          ;
6          ; Inputs:
7          ; R1 = Index number of job that owns the window
8          ; R2 = Window number
9          ;
10         ; Outputs:
11         ; C-flag cleared ==> Found window control block
12         ; C-flag set    ==> Cannot find window control block
13         ; R2 = Pointer to window control block if found
14         ;
15 014140  WINSRC:
16         ;
17         ; Search for specified window control block
18         ;
19 014140  010200          MOV     R2,R0          ;Get window ID
20 014142  013702  000002'  MOV     DWBAS,R2        ;Point to first window control block
21 014146  120062  0000000  1$:    CMPB   R0,DW$ID(R2)    ;Does this block have correct ID?
22 014152  001003          BNE     2$                ;Br if not
23 014154  120162  0000000  CMPB   R1,DW$JOB(R2)    ;Is this control block for right job?
24 014160  001407          BEQ     3$                ;Br if yes
25 014162  062702  0000000  2$:    ADD     #DW$$SZ,R2    ;Point to next control block
26 014166  020237  000004'  CMP    R2,DWEND        ;Checked all?
27 014172  103765          BLO    1$                ;Loop if not
28         ;
29         ; Cannot find specified window control block
30         ;
31 014174  000261          SEC                      ;Signal error on return
32 014176  000401          BR     9$
33         ;
34         ; Found the window control block
35         ;
36 014200  000241  3$:    CLC                      ;Signal success on return
37         ;
38         ; Finished
39         ;
40 014202  000207  9$:    RETURN

```

MAKWSB -- Create named region for window screen buffer

```

1          .SBTTL  MAKWSB -- Create named region for window screen buffer
2          ;-----
3          ; Create a named local region large enough to hold the window
4          ; screen buffer.
5          ;
6          ; Inputs:
7          ; R2 = Pointer to window control block
8          ; EMTBLK+2 = Arg block for EMT to create the window
9          ;
10         ; Outputs:
11         ; C-flag cleared ==> Successfully created region
12         ; C-flag set    ==> Unable to create region
13         ;
14 014204 010146 MAKWSB: MOV     R1,-(SP)
15 014206 010346      MOV     R3,-(SP)
16 014210 010446      MOV     R4,-(SP)
17 014212 010546      MOV     R5,-(SP)
18 014214 010605      MOV     SP,R5          ; Save original stack pointer in R5
19         ;
20         ; Calculate number of 64-byte blocks needed for region
21         ;
22 014216 016203 0000006 MOV     DW$LPP(R2),R3  ; Get # lines on page
23 014222 070362 0000006 MUL     DW$CPL(R2),R3  ; Times number of columns
24 014226 006303      ASL     R3              ; Need two bytes per character
25 014230 066203 0000006 ADD     DW$LPP(R2),R3  ; Need byte vector for line attributes
26 014234 062703 0000077 ADD     #63.,R3        ; Bound up to 64-byte boundary
27 014240 072327 177772  ASH     #-6.,R3        ; Get # 64-byte blocks needed
28         ;
29         ; Build a region definition block on the stack
30         ;
31 014244 162706 000012  SUB     #10.,SP        ; Allocate space for region def block
32 014250 010604      MOV     SP,R4          ; Get pointer to start of RDB
33 014252 004737 014404' CALL    MAKRDB         ; Make a region definition block on the stack
34 014256 010364 0000006 MOV     R3,R.GSIZ(R4)  ; Set # 64-byte units needed
35 014262 012764 000000C 0000006 MOV     #<RS.GBL!RS.CGR>,R.GSTS(R4) ; Set status flags
36         ;
37         ; Build EMT argument block on stack
38         ;
39 014270 162706 000004  SUB     #4.,SP        ; Allocate space for EMT arg block
40 014274 010601      MOV     SP,R1          ; Save pointer to EMT arg block
41 014276 010600      MOV     SP,R0          ; Get pointer to EMT arg block area
42 014300 012710 017000  MOV     #<36*400>,(R0) ; Set EMT function code
43 014304 010460 000002  MOV     R4,2(R0)      ; Set address of region def block
44         ;
45         ; Try to create the region
46         ;
47 014310 104375      EMT     375            ; Try to create the region
48 014312 103426      BCS     9$              ; Br if error on region creation
49         ;
50         ; We successfully created the region.
51         ; Set up information in the window control block.
52         ;
53 014314 016403 0000006 MOV     R.GID(R4),R3  ; Get region control block address
54 014320 016362 0000006 0000006 MOV     RC$BLK(R3),DW$RID(R2); Save addr of global RCB
55 014326 016362 0000006 0000006 MOV     RC$BAS(R3),DW$MAP(R2); Save mapping base for region
56         ;
57         ; Now detach from the global region

```

MAKWSB -- Create named region for window screen buffer

```

58 ;
59 014334 005064 0000000 CLR R,GSTS(R4) ;Clear all status flags
60 014340 010100 MOV R1,R0 ;Get pointer to EMT arg block
61 014342 012710 017001 MOV #<<36*400>+1>,(R0);Set .ELRG function code
62 014346 104375 EMT 375 ;Detach from the region
63 ;
64 ; Now go back and set the exclusive-access flag in the global region
65 ; control block and increment its attachment count by one.
66 ;
67 014350 016203 0000000 MOV DW#RID(R2),R3 ;Get pointer to global RCB
68 014354 052763 0000000 0000000 BIS #RC#EXC,RC#FLG(R3);Set exclusive-use flag
69 014362 105263 0000000 INCB RC#CNT(R3) ;Increment attachment count
70 ;
71 ; Successful completion
72 ;
73 014366 000241 CLC ;Signal success on return
74 ;
75 ; Finished -- Carry flag indicates results
76 ;
77 014370 010506 9#: MOV R5,SP ;Reset stack pointer
78 014372 012605 MOV (SP)+,R5
79 014374 012604 MOV (SP)+,R4
80 014376 012603 MOV (SP)+,R3
81 014400 012601 MOV (SP)+,R1
82 014402 000207 RETURN

```

MAKRDB -- Make a region definition block

```

1          .SBTTL  MAKRDB -- Make a region definition block
2          ;-----
3          ; Initialize a region definition block to access a global region
4          ; used as a window buffer.
5          ;
6          ; Inputs:
7          ; R2 = Pointer to window control block
8          ; R4 = Pointer to area where region definition block is to be built
9          ;
10         014404 010146 MAKRDB: MOV     R1,-(SP)
11         014406 010346         MOV     R3,-(SP)
12         ;
13         ; Initially zero some cells in the RDB
14         ;
15         014410 005064 0000000 CLR     R.GID(R4)      ;Zero addr of region control block
16         014414 005064 0000000 CLR     R.GSTS(R4)     ;No status flags
17         014420 005064 0000000 CLR     R.GSIZ(R4)     ;No size specified yet
18         ;
19         ; Construct name for global region.
20         ; The first three characters are "WIN".
21         ; The next two characters are the job number.
22         ; The last character indicates the window ID.
23         ;
24         014424 013764 000010' 0000000 MOV     R5OWIN,R.NAME(R4);Set 1st 3 chars of name to "WIN"
25         014432 116201 0000000 MOVE    DW#JOB(R2),R1   ;Get job index number
26         014436 006201          ASR     R1                   ;Convert to job number
27         014440 005000          CLR     R0                   ;Clear high-order for divide
28         014442 071027 000012   DIV     #10.,R0          ;Split job number into two digits
29         014446 062701 000036   ADD     #36,R1           ;Convert binary value to rad50 digit
30         014452 070127 000050   MUL     #50,R1          ;Shift remainder left 1 rad50 digit position
31         014456 010103          MOV     R1,R3             ;Save shifted low-order digit of job #
32         014460 010001          MOV     R0,R1             ;Get high-order digit of job #
33         014462 062701 000036   ADD     #36,R1           ;Convert binary value to rad50 digit
34         014466 070127 003100   MUL     #3100,R1        ;Shift over 2 rad50 digits
35         014472 060103          ADD     R1,R3             ;Job # is two high-order digits
36         014474 116201 0000000 MOVE    DW#ID(R2),R1    ;Get window number
37         014500 060103          ADD     R1,R3             ;Put window number as 3rd digit of word
38         014502 010364 0000020 MOV     R3,R.NAME+2(R4) ;Set 2nd word of name
39         ;
40         ; Finished
41         ;
42         014506 012603          MOV     (SP)+,R3
43         014510 012601          MOV     (SP)+,R1
44         014512 000207          RETURN

```

FREWSB -- Free memory used by window screen buffer

```

1          .SBTTL  FREWSB -- Free memory used by window screen buffer
2          ;-----
3          ; Free the memory region used for a window screen buffer.
4          ;
5          ; Inputs:
6          ; R2 = Pointer to window control block
7          ;
8 014514 010146 FREWSB: MOV     R1, -(SP)
9 014516 010446      MOV     R4, -(SP)
10 014520 010546      MOV     R5, -(SP)
11 014522 010605      MOV     SP, R5          ; Save initial stack pointer
12          ;
13          ; See if this window has an associated region
14          ;
15 014524 016204 0000000 MOV     DW#RID(R2), R4 ; Does window have an assoc region?
16 014530 001436      BEQ     9$          ; Br if not
17          ;
18          ; Decrement attachment-count in global region RCB and
19          ; reset exclusive-use flag.
20          ;
21 014532 105364 0000000 DECB   RC#CNT(R4)      ; Say one less job using region
22 014536 042764 0000000 0000000 BIC   #RC#EXC, RC#FLG(R4); Clear exclusive-use flag
23          ;
24          ; Build region definition block on the stack
25          ;
26 014544 162706 000012  SUB     #10., SP      ; Reserve room for region def block
27 014550 010604      MOV     SP, R4          ; Get addr of base of region def block
28 014552 004737 014404' CALL   MAKRDB         ; Build the region definition block
29 014556 012764 0000000 0000000 MOV     #RS.GBL, R.GSTS(R4); Set global status flag in RDB
30          ;
31          ; Build EMT argument block on stack to attach to region
32          ;
33 014564 162706 000004  SUB     #4., SP      ; Reserve room for EMT arg block
34 014570 010601      MOV     SP, R1          ; Save pointer to EMT arg block
35 014572 010600      MOV     SP, R0          ; Get pointer to arg block area
36 014574 012710 017000  MOV     #<<36*400>+0>, (R0); Set function code
37 014600 010460 000002  MOV     R4, 2(R0)     ; Set address of region def block
38 014604 104375      EMT     375          ; Try to attach to the region
39 014606 103407      BCS     9$          ; Br if cannot attach to region
40          ;
41          ; Eliminate the region
42          ;
43 014610 012764 0000000 0000000 MOV     #<RS.GBL!RS.EGR>, R.GSTS(R4); Set status flags
44 014616 010100      MOV     R1, R0        ; Point to EMT argument block
45 014620 012710 017001  MOV     #<<36*400>+1>, (R0); Set EMT function code
46 014624 104375      EMT     375          ; Eliminate the region
47          ;
48          ; Finished
49          ;
50 014626 010506 9$: MOV     R5, SP          ; Restore stack pointer
51 014630 012605      MOV     (SP)+, R5
52 014632 012604      MOV     (SP)+, R4
53 014634 012601      MOV     (SP)+, R1
54 014636 000207      RETURN

```

WININI -- TSWIN initialization

```

1
2
3
4
5
6 014640 010546
7
8
9
10 014642 013705 0000000
11 014646 070527 0000000
12 014652 062705 015050'
13 014656 020527 0000000
14 014662 101402
15 014664 012705 0000000
16 014670 010537 000004'
17
18
19
20 014674 005045
21 014676 020537 000002'
22 014702 101374
23
24
25
26 014704 012605
27 014706 000207

```

```

.SBTTL WININI -- TSWIN initialization
-----
; WININI is called during system initialization to initialize the
; display management system.
;
WININI: MOV R5, -(SP)
;
; Allocate space for the window control blocks
;
MOV VMXWIN, R5 ;Get # control blocks wanted
MUL #DW*$SZ, R5 ;Times size of each block
ADD #WINTOP, R5 ;Add base of area
CMP R5, #140000-DW*$SZ ;Would this overflow available area?
BLOS 1$ ;Br if not
MOV #140000-DW*$SZ, R5 ;Constrain to available area
1$: MOV R5, DWEND ;Set pointer to end of control blocks
;
; Zero the entire display control block area
;
2$: CLR -(R5) ;Zero entire area
CMP R5, DWBAS ;Reached start of area?
BHI 2$ ;Loop if not
;
; Finished
;
MOV (SP)+, R5
RETURN

```

WINPRT -- Window print-screen function

```

1          .SBTTL  WINPRT -- Window print-screen function
2          ;-----
3          ; WINPRT is called when a control character is received that means
4          ; that we should perform a print-screen function for the current
5          ; window for the job.
6          ;
7          ; Inputs:
8          ; R2 = Pointer to current window control block for job
9          ;
10         ; Outputs:
11         ; C-flag set on return if unable to print the window.
12         ;
13 014710 010146 WINPRT: MOV     R1,-(SP)
14 014712 010446         MOV     R4,-(SP)
15 014714 010546         MOV     R5,-(SP)
16         ;
17         ; See if "WINPRT" detached job is running now
18         ;
19 014716 012701 0000000 MOV     #LSTSL,R1      ;Get index to last job
20 014722 026137 0000000 000010' 1$:  CMP     LPRG1(R1),R50WIN; Is this the WINPRT program?
21 014730 001004         BNE     2$          ;Br if not
22 014732 026137 0000000 000012'   CMP     LPRG2(R1),R50PRT
23 014740 001404         BEQ     3$          ;Br if yes
24 014742 162701 0000002 2$:      SUB     #2,R1      ;More jobs to check?
25 014746 003365         BGT     1$          ;Loop if yes
26 014750 000432         BR      8$          ;WINPRT program is not running
27         ;
28         ; The WINPRT program is running.
29         ; Schedule a completion routine to tell it to print a window.
30         ;
31 014752 016104 0000000 3$:      MOV     LBRKCQ(R1),R4   ;Get address of its completion Q element
32 014756 001427         BEQ     8$          ;Br if no completion routine pending
33 014760 005737 0000000         TST     NMFREQ      ;Can we get a free queue element?
34 014764 003424         BLE     8$          ;Br if not
35 014766 004737 0000000         CALL   GETRTQ      ;Get a free completion Q element (R1=addr)
36 014772 012700 0000000         MOV     #IOQSIZ/2,R0   ;Get # words in queue element
37 014776 010105         MOV     R1,R5      ;Get pointer to new queue element
38 015000 012425 4$:      MOV     (R4)+,(R5)+   ;Copy original completion Q element
39 015002 077002         SOB     R0,4$
40 015004 116200 0000000         MOVVB  DW#JOB(R2),R0   ;Get # of job whose window to print
41 015010 006200         ASR     R0          ;Convert to job number
42 015012 110061 0000010         MOVVB  R0,CQ#R1+1(R1) ;Set job # in high byte of R1
43 015016 116261 0000000 0000000 MOVVB  DW#ID(R2),CQ#R1(R1); Set window ID in low byte of R1
44 015024 010104         MOV     R1,R4      ;Get addr of compl Q element for QCOMPL
45 015026 004737 0000000         CALL   QCOMPL      ;Queue the completion request for WINPRT
46 015032 000241         CLC          ;Signal success on return
47 015034 000401         BR      9$
48         ;
49         ; Unable to print the window
50         ;
51 015036 000261 8$:      SEC          ;Signal failure on return
52         ;
53         ; Finished
54         ;
55 015040 012605 9$:      MOV     (SP)+,R5
56 015042 012604         MOV     (SP)+,R4
57 015044 012601         MOV     (SP)+,R1

```

58 015046 000207
59
60
61
62
63
64 015050
65
66 000001

RETURN

;

;

; Top of TSWIN code (Window control blocks are allocated from this
; point to the end of the overlay).

;

WINTOP:

;

.END

Errors detected: 0

*** Assembler statistics

Work file reads: 0

Work file writes: 0

Size of work file: 8354 Words (33 Pages)

Size of core pool: 17920 Words (70 Pages)

Operating system: RT-11

Elapsed time: 00:01:45.32

DK: TSWIN, LP: TSWIN=DK: TSWIN, MAC/C/N: SYM

Cross reference table (GREF V05.04)

SS3CHR	1-31						
TC100	12-16	12-84	42-9#				
TCAKM	12-70	38-8#					
TCBS	5-34	14-8#					
TCCADR	12-15	12-43	24-9#				
TCCPRS	12-69	25-30#					
TCCPSV	12-68	25-8#					
TCCR	5-39	16-8#	20-9				
TCDELL	12-48	27-10#					
TCDOWN	12-38	18-10#					
TCESCE	12-50	20-9#					
TCGOAS	12-42	12-55	28-8#				
TCGODS	12-41	12-73	28-18#				
TCGGR	12-56	28-38#					
TCGOUK	12-54	28-28#					
TCG1AS	12-57	12-58	29-8#				
TCG1DS	12-76	29-18#					
TCG1GR	12-59	29-38#					
TCG1UK	29-28#						
TCG2AS	12-60	30-8#					
TCG2DS	12-79	30-10#					
TCG2GR	12-61	30-28#					
TCG3AS	12-62	31-8#					
TCG3DS	12-82	31-10#					
TCG3GR	12-63	31-28#					
TCHT	5-35	15-8#					
TCINSL	12-47	26-11#					
TCIXUP	12-44	12-51	21-9#				
TCLEFT	12-40	23-9#					
TCLERS	12-46	45-9#					
TCLF	5-36	5-37	5-38	12-49	19-8#	20-10	
TCLS1R	12-26	32-48#					
TCLS2	12-27	32-28#					
TCLS2R	12-29	32-58#					
TCLS3	12-28	32-38#					
TCLS3R	12-30	32-68#					
TCN3	12-64	39-10#					
TCN4	12-65	39-18#					
TCN5	12-66	39-26#					
TCN6	12-67	39-38#					
TCNKM	12-86	38-18#					
TCPERS	12-45	46-9#					
TCPRT	11-85	12-21	44-9#				
TCRAA	12-18	33-23#					
TCRDA	12-20	33-51#					
TCREST	12-24	12-25	43-8#				
TCRIT	12-39	22-9#					
TCRTA	33-25	33-53	35-10#				
TCSAA	12-17	33-9#					
TCBSZ	1-30	10-16					
TCSCA	12-22	40-9#					
TCSDA	12-19	33-37#					
TCSEI	5-41	32-13#					
TCSD	5-40	32-8#					
TCSS2	12-52	32-78#					
TCSS3	12-53	32-89#					

TCSSR	12-23	47-9#				
TCSTA	33-11	33-39	34-10#			
TCUP	12-37	17-10#				
TSWIN	1-6#					
VALADB	1-24	89-19				
VALADW	1-24	89-17				
VMXWIN	1-40	98-10				
VPAR6	1-32	61-17	62-19	63-29	89-70	
VT2007	1-40	42-26	43-36	84-65	91-25	
VT2008	1-40	42-26	43-36	84-65	91-25	
VT52	1-40	91-18				
WCPCSI	6-27	7-31#				
WCPESC	6-20	7-9#				
WCSCHK	3-41	6-14#				
WFDEL	83-39	86-8#				
WFMAP	83-38	85-10#				
WFNEW	83-37	84-16#				
WFPRNT	83-42	88-13#				
WFREAD	83-43	89-12#				
WFRSUM	83-41	87-22#				
WFSPND	83-40	87-10#				
WFSTT	83-44	90-8#				
WINCHR	1-17	3-14#				
WINDEL	84-23	84-113	86-29	86-44	92-16	93-8#
WINDSP	1-17	66-9#				
WININI	1-17	98-6#				
WINPRT	1-18	88-26	99-13#			
WINREL	1-17	86-19	92-8#			
WINSF	1-18	64-9#				
WINSFN	51-40	52-8#				
WINSRC	84-21	84-98	85-21	86-37	88-19	89-37 94-15#
WINST	1-18	65-9#				
WINSTT	84-61	90-15	91-9#			
WINTOP	1-47	2-49	98-12	99-64#		
WINVEC	83-33	83-37#	83-45			

BUFMAP	2-26#	4-44	53-15	54-26	55-18	59-22	60-39	61-21	62-23	68-45	89-71	
DISABL	2-6#	4-44	53-15	54-26	55-18	59-22	60-39	61-21	62-23	67-20	68-45	89-71
ENABL	2-10#	4-47	53-18	54-29	55-21	59-25	60-42	61-23	62-25	67-23	68-48	89-73
ESCSEQ	12-5#	12-15	12-16	12-17	12-18	12-19	12-20	12-21	12-22	12-23	12-24	12-25
	12-26	12-27	12-28	12-29	12-30	12-37	12-38	12-39	12-40	12-41	12-42	12-43
	12-44	12-45	12-46	12-47	12-48	12-49	12-50	12-51	12-52	12-53	12-54	12-55
	12-56	12-57	12-58	12-59	12-60	12-61	12-62	12-63	12-64	12-65	12-66	12-67
	12-68	12-69	12-70									
	DCALL	2-16#	52-23	81-40								
SEND	2-39#	68-90	68-91	69-19	69-24	69-25	69-26	69-31	69-33	69-38	69-39	69-43
	69-45	69-46	69-53	69-55	69-56	69-62	69-64	69-66	70-39	70-45	70-46	70-52
	70-53	70-59	70-60	70-66	70-67	70-71	71-35	71-36	71-40	71-41	71-48	72-20
	72-28	72-37	72-41	72-50	73-28	73-31	73-38	73-39	73-40	74-20	74-21	74-22
	74-31	75-35	75-37	76-22	76-23	77-45	77-48	77-59	77-72	78-16	78-19	78-21
	78-28	78-29	79-23	79-38	79-44	79-47	79-50	80-29	80-32	80-38	80-41	80-44
	81-5	81-23	81-24	82-27								
	UNMAP	2-32#	4-47	53-18	54-29	55-21	59-25	60-42	61-23	62-25	68-48	89-73