

2-	1	TSKMON EMT's
3-	1	KMRUN -- Start execution of a SAV file
7-	1	Misc. Kmon EMTs
16-	1	VLSEMT -- EMT to switch between subprocesses
17-	1	Detached job control emt's
18-	1	Shared Run-time control emt's
19-	1	Associate shared run-time system with job
20-	1	Map shared run-time system into user's virtual address
21-	1	Define a run-time region for fast mapping
23-	1	ESPLIT -- Enable user D-space
24-	1	Define a PLAS region for fast mapping
25-	1	CHKRCB -- Check address of Region Control Block
26-	1	Spooling control
27-	1	CL line control EMT's
28-	1	CLASN -- Assign a CL unit to a line
29-	1	CLCLR -- Clear XOFF sent and send XON
29-	18	CLRES -- Reset CL line
30-	1	CLCLOS -- Close channel opened to CL unit
31-	1	CLWAIT -- Wait for CL output to finish
32-	1	Performance monitor emt's
35-	1	CKACJB -- See if access to another job is allowed

```

1          .TITLE  TSEM4   TSX-Plus EMT Overlay
2          .ENABL  LC
3          .ENABL  AMA
4          .DSABL  GBL
5
6          ; Copyright (C) 1976, 1977, 1978, 1979, 1980, 1981, 1982, 1983, 1984, 1985, 1986,
7          ;          1987, 1988, 1989.
8
9          ; S&H Computer Systems, Inc.
10         ; Nashville, Tennessee
11
12         ; This software is furnished under a license for use only
13         ; on a single computer system and may be copied only with
14         ; the inclusion of the above copyright notice. This
15         ; software, or any other copies thereof, may not be provided
16         ; or otherwise made available to any other person except
17         ; for use on such system and to one who agrees to these
18         ; license terms. Title to and ownership of the software
19         ; shall at all times remain with S&H Computer Systems, Inc.
20
21         .CSECT  TSEM4
22 000000 TSEM4: .RAD50  /EM4/          ;Overlay id
23 000000 177776 PS          =          177776 ;Processor Status Word
24
25         ;
26         ; EMI error code return values
27 EC0          = 0
28 EC1          = 1
29 EC2          = 2
30 EC3          = 3
31 EC4          = 4
32 EC5          = 5
33 EC6          = 6
34 EC7          = 7
35 EC8          = 8
36 EC9          = 9
37 EC10         = 10
38
39         ; Macro calls
40
41         .MCALL  .READW, .CLOSE, .CRRG
42
43         ; Global definitions
44
45         .GLOBL  KMNEMT, DETEMT, PMEMT, SPLEMT, SSEMT, KILJOB
46         .GLOBL  CLEMT, CLCLOS, VLSEMT
47
48         ; Global references
49
50         .GLOBL  WC$LEN, WC$NPR, RC$LEN
51         .GLOBL  WC$$SZ, WCBBAS, WC$SIZ, WC$OFF, WC$PAR, WC$TRP, SR$WCB
52         .GLOBL  NUMWCB, RCBBAS, RCBEND, SHRRCB, SHRRCN, RC$FLG, RC$DSP, RC$LCG
53         .GLOBL  MAXSRD, SR$PAR, SR$PDR, SR$PX, SR$FLG, SR. MOR, SR. DSP, DOTRMP
54         .GLOBL  $VBELL, IB$SF2, SF2LEN, GETQ, IB$IJ, SPPRED, $VNOTT, LCXTBL
55         .GLOBL  $NOVLN, $SUCF, $LDFCF, $NOIN, MAXSEC, LSECPT, FSTSL, LSTSL, INITLN
56         .GLOBL  LSW6, CSHALC, CSHINI, SPLDEL, SETDTR, CD$DTR, CLWTIM, $RBRK, LINSWT
57         .GLOBL  $IOMAP, R. GSTS, INTPRI, CURRDB, UPARO, RF$WRT, RT$FLG, LPROG
58         .GLOBL  $INKMN, LSW4, BADEMT, EMTBLK, LOGOFF, SETHAN, REBOOT
59         .GLOBL  KMPCPX, EMSPHL, EMSPNH, QTUKBL, LEMTPC, CLREST, $RDSAV, LSW11

```

```

58 .GLOBL EMTLEV, LJSW, JSWLOC, PRGSIZ, SUTOP, CXTRMN, R$CHN, CLCLER
59 .GLOBL CHNSIZ, R$XCHN, RUNCHN, PRGTOP, CSIARE, DVLBIT, NEWJSW
60 .GLOBL CHAIN, CINFLG, UERSEV, ERRLOC, RUNARG, CINDAT, CPLEMT, RMNBAS
61 .GLOBL VIMAGE, $VIRJOB, LSW9, RMON, LSW2, $SCOPE, TO$SCP, $TAB
62 .GLOBL TO$TAB, $FORM, TO$FF, TO$LC, CXTRMN, R$TTOP, TTOPTS, RMNBAS
63 .GLOBL $SETRN, USRSTK, $RNIOF, $IOMAP, SETMAP, $RNMLK, LQUAN, JSTK
64 .GLOBL UMODE, UPMODE, USTART, $DEBUG, DBGENT, ABORT, SUPRTN, VIDCSR
65 .GLOBL VO$RDB, R. $SIZ, RUNRDB, VO$WDB, VO$WDE, R. $ID, RC$BAS
66 .GLOBL W. NRID, W. NOFF, KPARO, W. SIZE, SETERR, NSPLDV
67 .GLOBL OVRHC, SPOLGO, EMTXIT, $DILUP, LSW, $SUSPN, FORCEX, $DETCH
68 .GLOBL LNPRIM, CL$XLN, CM$BRK, CM$ON, CL$STA, LXCL, CLXICP, LINIR
69 .GLOBL S$SPND, QNSPND, LSTPL, CLXBRK, $CTRLS, LSW3, $CTRLO
70 .GLOBL ENQTL, S$CPU, LOTSPC, LOTSIZ, PO$BYP
71 .GLOBL $DISCN, TRNSTR, PO$DET, PRIVCO, FSTD, LSTD, VALADB, LSUCF
72 .GLOBL DETCBS, GETUCH, CORUSR, LPARNT, URO, RPAR, RPDR, VPLAS
73 .GLOBL MAPPLS, VALADW, RDB, RDBEND, RT$NAM, RT$$SZ, RT$BAS, RT$TOP
74 .GLOBL CUPARO, CUPDRO, UPDRO, CS$OPN, CHNADR, C. CSW, NSPLDV, SPLSHF
75 .GLOBL P2$TRM, PRIVC2, CLTOTL, LSTHL, $HARD, LCLUNT, $DEAD, SPLSFF
76 .GLOBL FSTIOL, LSTIOL, CL$LIX, CL$RQH, CL$WQH, LCLUNT, NEDCHR, SPLSWF
77 .GLOBL LOUTIR, TTINCP, $AUTO, ILSW2, S9600, SETSPD, LINRTS, CLOTIR, CLINCP
78 .GLOBL $SXON, LSW10, CO$DEF, $TAB, CO$TAB, CO$FF, $8BIT, CO$8BT
79 .GLOBL CL$OPT, CL$STA, CL$COL, CL$LEN, CL$LIN, CL$SKP, CL$WID
80 .GLOBL CL$EPN, CL$EPS, CL$EPP, CS$SPL, CS$NMX, CLDEVX, C. DEVQ, C1DEVX
81 .GLOBL CL$ORS, CL$ORA, CM$EFP, $XCHAR, PMCELS, PMUSER, PMRUN, PMBASE, PMTOP
82 .GLOBL PMFLGS, PMCELS, PMNBPC, ENSYS, FP$MOV, VPAR6, PMPAR, KPAR6
83 .GLOBL P2$WRL, LPROJ, P2$GRP, P2$SAM, VSWPFL, DFJMEM
84 .GLOBL $UDSPC, ODTBAS, SR3MMR, USDSPC, IDSFLG
85 .GLOBL SETSTN

```

```

;-----
; Macros to enable and disable interrupts.

```

```

;
; .MACRO DISABL ;DISABLE INTERRUPTS
; BIS #340, @#PS
; ENDM DISABL
;
; .MACRO ENABL ;ENABLE INTERRUPTS
; BIC INTPRI, @#PS
; ENDM ENABL

```

```

; Macro to print an error message when a system crash occurs.

```

```

; Arguments:

```

```

; MSG = Name of error message to print.
; ARG = (Optional) argument value to display with error message.

```

```

; .GLOBL DIEMSG, DIEARG, SYSHLT
; .MACRO DIE MSG, ARG
; MOV MSG, @#DIEMSG
; IF NB, ARG
; MOV ARG, @#DIEARG
; ENDC
; CALL @#SYSHLT
; ENDM DIE

```

```

; Macro definition for calling global routines residing in mapped
; system regions.

```

```
115  
116 . MACRO OCALL ENTADD  
117 . IF B, ENTADD  
118 . ERROR ; OCALL SPECIFIED WITH NO ENTRY ADDRESS  
119 . MEXIT  
120 . ENDC  
121 CALL OVRHC ; CALL THE OVERLAY HANDLER  
122 . WORD ENTADD ; SPECIFY THE ENTRY POINT  
123 . ENDM
```

```

1          .SBTTL  TSKMON EMT's
2          ;-----
3          ; KMNEMT is jumped to when a KMON specific EMT is executed.
4          ; It interprets the sub-function (in 2nd word of arg block)
5          ; and branches off to the appropriate processing routine.
6          ;
7 000002 032761 000000G 000000G KMNEMT: BIT    #$INKMN,LSW4(R1); IS KMON RUNNING NOW?
8 000010 001002                BNE     1$          ;BR IF YES
9 000012 000137 000000G        2$:   JMP     BADEMT    ;ILLEGAL EMT IF KMON NOT RUNNING
10         ;
11         ; Get sub-function code and branch off to processing routine.
12         ;
13 000016 013702 000002G        1$:   MOV     EMTBLK+2,R2    ;GET SUB-FUNCTION CODE
14 000022 020227 000022        CMP     R2,#KMNMAX    ;VALID SUB-FUNCTION CODE?
15 000026 103371                BHIS   2$          ;ERROR IF NOT
16 000030 006302                ASL    R2          ;CONVERT TO WORD TABLE INDEX
17 000032 000172 000036'        JMP     @KMNSUB(R2)    ;ENTER PROCESSING ROUTINE
18
19         ;-----
20         ; Table of KMON subfunctions for EMT code 126.
21         ; (Sub-function code is stored in 2nd word of EMT arg block)
22         ;
23 000036 000102' KMNSUB: .WORD  KMRUN      ; 00 Initiate execution of a SAV file
24 000040 001362'          .WORD  KMSPLG    ; 01 Initiate a spooler
25 000042 000000G          .WORD  LOGOFF   ; 02 Log off the current job
26 000044 000000G          .WORD  SETHAN   ; 03 Update running copy of handler
27 000046 000000G          .WORD  REBOOT   ; 04 Reboot the system
28 000050 001752'          .WORD  KILEMT   ; 05 Force logoff of a job
29 000052 002122'          .WORD  CSHNEW   ; 06 Clean out data cache
30 000054 002140'          .WORD  KMSPDL   ; 07 Delete a spool file
31 000056 001406'          .WORD  KMSPEK   ; 10 Get data from within system
32 000060 001436'          .WORD  KMSPOK   ; 11 Store data into system
33 000062 001466'          .WORD  KMSPRS   ; 12 Suspend or resume a job
34 000064 001540'          .WORD  CLXCON   ; 13 Cross connect TT line to CL unit
35 000066 000000G          .WORD  KMCPGX   ; 14 Copy data from context blk
36 000070 000000G          .WORD  EMSPHL   ; 15 Set HOLD mode for a spooler
37 000072 000000G          .WORD  EMSPNH   ; 16 Set NOHOLD mode for a spooler
38 000074 000000G          .WORD  GTUKBL   ; 17 Access block in user key region
39 000076 001674'          .WORD  STTTLN   ; 20 Start up a terminal line
40 000100 000000G          .WORD  SETSTN   ; 21 Set site name for flag pages (in TSSPL2)
41         000022        KMNMAX = <-KMNSUB>/2
    
```

KMRUN -- Start execution of a SAV file

```

1          .SBTTL  KMRUN  -- Start execution of a SAV file
2          ;-----
3          ; KMRUN (126,0) is the EMT executed by KMON to start execution of
4          ; a SAV file.  On entry user channel # RUNCHN must be open to the SAV file.
5          ; The SAV file is read into memory and control is transferred to it.
6          ;
7 000102 005061 000000G KMRUN: CLR      LEMTPC(R1)      ;CLEAR ADDRESS OF LAST USER-MODE EMT
8 000106 042761 000000G 000000G BIC      #$INKMN,LSW4(R1);SAY WE ARE EXITING FROM KMON
9 000114 012737 177777 000000G   MOV      #-1,EMTLEV      ;SAY NO EMT IS BEING DONE
10         ;
11         ; Set up JSW for job so virtual-image flag will be set before mem alloc
12         ;
13 000122 013746 000000G   MOV      NEWJSW,-(SP)      ;SET NEW JSW
14 000126 011661 000000G   MOV      (SP),LJSW(R1)
15 000132 106637 000000G   MTPD     @#JSWLOC
16         ;
17         ; Set $RDSAV flag to prevent PKSTAT/UPSTAT from saving/restoring the
18         ; JSW and Error byte in locations 44 and 52 of memory. This is necessary
19         ; because SUTOP is going to change mapping to an uninitialized area
20         ; of memory and we don't want to use the contents of memory locations
21         ; until we actually get the SAV image in and set it up.
22         ;
23 000136 052761 000000G 000000G   BIS      #$RDSAV,LSW11(R1);Say we are reading in SAV file
24         ;
25         ; Set top of memory for the sav file we are about to start.
26         ;
27 000144 013700 000000G   MOV      PRGSIZ,RO      ;SET TOP OF MEMORY FOR JOB REGION
28 000150 105737 000000G   TSTB     VSWPFL        ;IS THIS A SWAPPING SYSTEM?
29         ; BNE      39$          ;IF SWAPPING USE JOB SIZE, ELSE
30         ; Changing this to always use PRGSIZ allows RT-11 utilities to
31         ; work correctly in a 64kb DFLMEM no swapping system. They use
32         ; .GVAL offset 266 to determine base of USR (we set this in SUTOP
33         ; to 177774 if DFLMEM is 64kb) then TST -(RO) (which traps because
34         ; we only map PAR7 through the top of simulated RMON), prior to
35         ; doing a .SETTOP. If the program is virtual (doesn't map RMON),
36         ; then PRGSIZ will be bigger than 56kb; if not, then pretend
37         ; that USR base is below RMON. See TSKM2C CMDRUN for PRGSIZ set up.
38 000154 000406   BR      39$          ; Always use PRGSIZ as set up by TSKMON
39 000156 013700 000000G   MOV      DFJMEM,RO     ;RETRIEVE DEFAULT MEMORY SIZE
40 000162 000300   SWAB    RO           ;CONVERT TO ADDRESS ( * 256.)
41 000164 006300   ASL     RO           ; * 512.
42 000166 005300   DEC     RO           ;LEAVE 1 WORD SHORT (ELSE 64.KB = 0)
43 000170 006300   ASL     RO           ; * 1024. = ALLOCATED TOP ADDRESS IN BYTES
44 000172 004737 000000G 39$:   CALL    SUTOP        ;SET TOP OF MEMORY
45         ;
46         ; Transfer the channel information from internal channel RUNCHN
47         ; into user's channel # 17
48         ;
49 000176 013700 000000G   MOV      CXTRMN,RO     ;Get address of job's simulated RMON
50 000202 010003   MOV     RO,R3
51 000204 062703 000000G   ADD     #R#CHN+<17*CHNSIZ>,R3 ;Point to chan blk for channel 17
52 000210 010002   MOV     RO,R2
53 000212 062702 000000G   ADD     #R#XCHN+<<RUNCHN-21>*CHNSIZ>,R2 ;Point to RUNCHN block
54 000216 010200   MOV     R2,RO         ;Save pointer to RUNCHN block
55 000220 012704 000000G   MOV     #CHNSIZ/2,R4   ;Get # words to copy
56 000224 012223 4$:   MOV     (R2)+,(R3)+   ;Copy RUNCHN to channel 17
57 000226 077402   SOB    R4,4$

```

```

58 000230 005010          CLR      (R0)          ; Say RUNCHN is closed
59                      ;
60                      ; Read the SAV file into memory
61                      ;
62 000232 013703 000000G   MOV      PRGTOP,R3      ; GET HIGHEST ADDRESS IN SAV FILE IMAGE
63 000236 000241          CLC
64 000240 006003          RDR      R3              ; GET # WORDS TO READ
65 000242 005203          INC      R3              ; CVT FROM TOP ADDRESS TO # WORDS
66 000244          .READW  #CSIARE,#17,#0,R3,#0
67 000276 103002          BCC     16$           ; Br if ok
68 000300 000137 001000'   JMP     9$           ; Error during read
69                      ;
70                      ; If program is not overlaid, close channel 17.
71                      ;
72 000304 032737 000000G 000000G 16$: BIT     #OVLBIT,NEWJSW ; IS THE PROGRAM OVERLAYED?
73 000312 001003          BNE     3$           ; IF YES THEN LEAVE CHANNEL 17 OPEN
74 000314          .CLOSE  #17          ; CLOSE CHANNEL 17
75                      ;
76                      ; See if we need to allocate extended-memory region for virtual overlays
77                      ;
78 000322 004737 001130'   3$:   CALL   KMRVM          ; See if we need to allocate XM region
79                      ;
80                      ; If a .CHAIN was done, move data from context block to chain data area.
81                      ;
82 000326 013703 000000G   MOV     NEWJSW,R3      ; GET JSW FOR JOB BEING STARTED
83 000332 042737 000000G 000000G   BIC     #CHAIN,NEWJSW ; CLEAR CHAIN FLAG
84 000340 105737 000000G   TSTB   CINFLG         ; WAS A .CHAIN DONE?
85 000344 001422          BEQ     20$          ; BR IF NOT
86 000346 105037 000000G   CLRB   CINFLG         ; SAY CHAIN IS FINISHED
87 000352 052737 000000G 000000G   BIS     #CHAIN,NEWJSW ; SET CHAIN-FLAG
88 000360 032703 000000G   BIT     #CHAIN,R3     ; DOES JOB WANT TO PRESERVE CHAIN DATA AREA?
89 000364 001034          BNE     1$           ; BR IF YES
90 000366 012704 000140   MOV     #<<1000-500>>/2,R4 ; GET # WORDS TO MOVE
91 000372 004737 001100'   CALL   CINMOV         ; Move chain data
92                      ;
93                      ; If a .CHAIN was done, reset the previous user's error cell (52&53).
94                      ;
95 000376 113746 000000G   MOVB   UERSEV,-(SP)   ; GET THE PREVIOUS ERROR SEVERITY LEVEL
96 000402 000316          SWAB   (SP)           ; PUT INTO HIGH BYTE
97 000404 106637 000000G   MTPD   @#ERRLOC      ; RESTORE THE USER ERROR SEVERITY LEVEL
98 000410 000425          BR     6$           ; SKIP THE INSTRUCTIONS TO CLEAR ERRLOC
99                      ;
100                     ; We are not doing a .CHAIN.
101                     ; See if we need to pass run argument string through chain data area.
102                     ;
103 000412 105737 000000G   20$:  TSTB   RUNARG      ; See if we need to pass RUN command line
104 000416 001005          BNE     22$          ; Br if yes
105 000420 012737 000001 000010G   MOV     #1,CINDAT+10 ; Say argument length = 1
106 000426 005037 000012G   CLR     CINDAT+12    ; Say argument string is null
107 000432 032703 000000G   22$:  BIT     #CHAIN,R3   ; Does job want to preserve chain data area?
108 000436 001007          BNE     1$           ; Br if yes
109 000440 013704 000010G   MOV     CINDAT+10,R4 ; Get # bytes in run argument string
110 000444 062704 000013   ADD     #13,R4       ; Get # bytes below 512 and round up
111 000450 006204          ASR     R4           ; Get # words to move
112 000452 004737 001100'   CALL   CINMOV         ; Move run argument to chain data area
113                     ;
114                     ; Initially clear user's error cell (52&53).

```

KMRUN -- Start execution of a SAV file

```

115 ;
116 000456 005046 1$: CLR -(SP) ;INITIALLY ZERO USER'S ERROR CELL
117 000460 106637 000000G MTPD @#ERRLOC ;INITIALLY ZERO USER'S ERROR CELL
118 ;
119 ; Store [EMT 356] instruction in job's low memory area to be used
120 ; to exit from a completion routine.
121 ;
122 000464 012746 104356 6$: MOV #104356, -(SP) ; [EMT 356]
123 000470 006637 000000G MTPD @#CPLEMT ; STORE INTO JOB'S AREA
124 ;
125 ; Set pointer to simulated monitor vector table that is mapped through
126 ; user page 7 (160000-177777).
127 ;
128 000474 012746 000000G MOV #RMNBAS, -(SP) ; VIRTUAL ADDRESS OF MONVEC TABLE
129 000500 032737 000000G 000000G BIT #VIMAGE, NEWJSW ; IS THIS A VIRTUAL JOB?
130 000506 001405 BEQ 14$ ; BR IF NOT
131 000510 052761 000000G 000000G BIS ##VIRJB, LSW9(R1) ; SET VIRTUAL-JOB FLAG FOR THE SYSTEM
132 000516 012716 177776 MOV #177776, (SP) ; SET THIS AS RMON BASE FOR VIRTUAL JOB
133 000522 106637 000000G 14$: MTPD @#RMON ; SET POINTER IN USER'S SPACE
134 ;
135 ; Set EMT vector cell (location 30) in user's area to point to
136 ; cell in simulated RMON vector.
137 ;
138 000526 005000 CLR R0 ; INITIALIZE OPTION WORD VALUE
139 000530 016102 000000G MOV LSW2(R1), R2 ; GET VALUE OF LSW2 FLAGS FOR LINE
140 000534 032702 000000G BIT ##SCOPE, R2 ; IS THIS A SCOPE TYPE TERMINAL?
141 000540 001402 BEQ 10$ ; BR IF NOT
142 000542 052700 000000G BIS #TO$SCP, R0 ; SET SCOPE FLAG
143 000546 032702 000000G 10$: BIT ##TAB, R2 ; HARDWARE TABS?
144 000552 001402 BEQ 11$ ; BR IF NOT
145 000554 052700 000000G BIS #TO$TAB, R0 ; SET TAB FLAG
146 000560 032702 000000G 11$: BIT ##FORM, R2 ; HARDWARE FF?
147 000564 001402 BEQ 12$ ; BR IF NOT
148 000566 052700 000000G BIS #TO$FF, R0 ; SET FORM-FEED FLAG
149 000572 032702 000000G 12$: BIT #TO$LC, R2 ; ALLOW LOWER-CASE INPUT?
150 000576 001402 BEQ 13$ ; BR IF NOT
151 000600 052700 000000G BIS #TO$LC, R0 ; SET LC FLAG
152 000604 013702 000000G 13$: MOV CXTRMN, R2 ; GET ADDRESS OF BASE OF SIMULATED RMON FOR JOB
153 000610 010062 000000G MOV R0, R#TTOP(R2) ; SET TT OPTION WORD VALUE
154 000614 012746 000000C MOV #TTOPTS+RMNBAS+2, -(SP) ; GET ADDRESS OF TT OPTION CELL
155 000620 106637 0000030 MTPD @#30 ; SET IN EMT TRAP VECTOR
156 ;
157 ; See if we need to some special initialization for SETUP program
158 ;
159 000624 032761 000000G 000000G BIT ##SETRN, LSW9(R1) ; Is this the SETUP program being started?
160 000632 001402 BEQ 19$ ; Br if not
161 000634 004737 001024' CALL SETINI ; Initialize for SETUP program
162 ;
163 ; Set up user's SP
164 ;
165 000640 013746 000000G 19$: MOV USRSTK, -(SP) ; STACK POINTER FOR PROGRAM BEING STARTED
166 000644 106606 MTPD SP ; SET AS USER-MODE SP
167 ;
168 ; Set up JSW for job in memory now that SAV image has been read in
169 ;
170 000646 013746 000000G MOV NEWJSW, -(SP) ; SET NEW JSW
171 000652 011661 000000G MOV (SP), LJSW(R1)

```

KMRUN -- Start execution of a SAV file

```

172 000656 106637 000000G          MTPD    @#JSWL0C
173                                ;
174                                ; Now that memory image is set up correctly, clear the flag that says
175                                ; we are reading in the SAV file.
176                                ;
177 000662 042761 000000G 000000G          BIC     #RDSAV,LSW11(R1);Finished reading in SAV file
178                                ;
179                                ; See if we should map PAR 7 for job to I/O page
180                                ;
181 000670 032761 000000G 000000G          BIT     #RNIOP,LSW9(R1);Is I/O page access wanted?
182 000676 001403                                BEQ     17$           ;Br if not
183 000700 052761 000000G 000000G          BIS     #IOMAP,LSW6(R1);Set flag saying to map PAR 7 to I/O page
184                                ;
185                                ; Make sure memory management is set up correctly for the job
186                                ;
187 000706 004737 000000G          17$:   CALL    SETMAP           ;Set up memory mapping for the job
188                                ;
189                                ; See if we need to lock this program in low memory
190                                ;
191 000712 032761 000000G 000000G          BIT     #RNMMLK,LSW9(R1);Should we lock this program in memory?
192 000720 001410                                BEQ     18$           ;Br if not
193 000722 042761 000000G 000000G          BIC     #RNMMLK,LSW9(R1);Clear the flag
194 000730 012700 000000G          MOV     #CSIARE,R0      ;Point to EMT arg block area
195 000734 012710 060007          MOV     #<7+<140*400>>, (R0) ;Set up EMT argument block
196 000740 104375          EMT     375           ;Try to lock job in memory
197                                ;
198                                ; Give job a full time-slice
199                                ;
200 000742 005061 000000G          18$:   CLR     LQUAN(R1)      ;GIVE FULL TIME-SLICE ON STARTUP
201                                ;
202                                ; Push starting PSW and PC onto stack
203                                ;
204 000746 012706 000000G          MOV     #JSTK,SP        ;CLEAN OFF CONTEXT-BLOCK STACK
205 000752 012746 000000G          MOV     #UMODE!UPMODE,-(SP);USER-MODE PS
206 000756 013746 000000G          MOV     USTART,-(SP)    ;STARTING ADDRESS
207                                ;
208                                ; See if we are to start program under the debugger
209                                ;
210 000762 032761 000000G 000000G          BIT     #DEBUG,LSW9(R1);Are we to run program under the debugger?
211 000770 001402                                BEQ     15$           ;Br if not
212 000772 000137 000000G          JMP     DBGENT          ;Enter debugger to start the program
213                                ;
214                                ; Use RTI to enter user's program in user mode.
215                                ;
216 000776 000002          15$:   RTI                    ;ENTER PROGRAM IN USER-MODE
217                                ;
218                                ; Error reading SAV file
219                                ;
220 001000 105037 000000G          9$:    CLRB    CINFLG        ;Say chain is not being done
221 001004                                .CLOSE #17           ;Close the SAV file channel
222 001012 012705 000007          MOV     #EC7,R5        ;Get error code
223 001016 005004          CLR     R4
224 001020 000137 000000G          JMP     ABORT          ;Abort the job

```

KMRUN -- Start execution of a SAV file

```

1 ; -----
2 ; Perform special initialization when starting execution of SETUP program.
3 ; We must do this because SETUP tries to call the GETCSR routine to
4 ; get the CSR address of the video controller when running on the PRO.
5 ;
6 001024 SETINI:
7 ;
8 ; Set up a special RMON pointer for SETUP which will cause offset
9 ; 434 to point to a routine which will return video CSR address.
10 ;
11 001024 012746 1773440 MOV #SUPRTN-434,-(SP);Set fake address for RMON pointer
12 001030 106637 0000000 MTPD @#RMON ;Store RMON pointer into job space
13 001034 012700 0000000 MOV #SUPRTN,RO ;Get location where we store code in job
14 001040 012746 0000020 MOV #SUPRTN+2,-(SP) ;Set address where code will be stored
15 001044 106620 MTPD (RO)+ ;Store into job space
16 ;
17 ; Now store code in job space which will return CSR address for
18 ; video controller on the top of the stack.
19 ;
20 001046 012746 012766 MOV #012766,-(SP) ; [MOV #csr,2(SP)]
21 001052 006620 MTPD (RO)+ ;Store into program space
22 001054 013746 0000000 MOV VIDCSR,-(SP) ;Get CSR address for video controller
23 001060 006620 MTPD (RO)+ ;Store into program space
24 001062 012746 000002 MOV #2,-(SP)
25 001066 006620 MTPD (RO)+ ;Store stack offset for MOV instruction
26 001070 012746 000207 MOV #207,-(SP) ; [RETURN]
27 001074 006620 MTPD (RO)+ ;Store into program space
28 ;
29 ; Finished
30 ;
31 001076 000207 RETURN

```

KMRUN -- Start execution of a SAV file

```

1          ; -----
2          ; Move chain data from job context area to locations starting at 500
3          ; in the memory image of the program being started.
4          ;
5          ; Inputs:
6          ; R4 = Number of words to move.
7          ;
8 001100 010346 CINMOV: MOV      R3, -(SP)
9 001102 010446          MOV      R4, -(SP)
10         ;
11         ; Move the data
12         ;
13 001104 012700 000500          MOV      #500, R0          ;Get address of area to receive data
14 001110 012703 000000G          MOV      #CINDAT, R3      ;Point to chain data area in context block
15 001114 012346 2$:          MOV      (R3)+, -(SP)      ;Move chain data from context block to job
16 001116 106620          MTPD     (R0)+
17 001120 077403          SOB      R4, 2$
18         ;
19         ; Finished
20         ;
21 001122 012604          MOV      (SP)+, R4
22 001124 012603          MOV      (SP)+, R3
23 001126 000207          RETURN

```

KMRUN -- Start execution of a SAV file

```

1
2 ; -----
3 ; KMRVM is called from KMRUN when setting up a job for execution.
4 ; It checks to see if the job requires an extended-memory region for
5 ; virtual overlays, and if so allocates the region and zeroes the
6 ; segment id values in each section of the region.
7 ;
7 001130 010146 KMRVM: MOV R1, -(SP)
8 001132 010246 MOV R2, -(SP)
9 001134 010346 MOV R3, -(SP)
10 001136 010446 MOV R4, -(SP)
11 001140 010546 MOV R5, -(SP)
12 ;
13 ; Determine if this job needs an extended memory region
14 ;
15 001142 106537 000066 MFPD @#66 ;Get pointer to Window Definition Blocks
16 001146 022627 001000 CMP (SP)+, #1000 ;Any windows for job?
17 001152 103471 BLO 9$ ;Br if not -- No XM region needed
18 ;
19 ; Create an extended memory region using the information in the
20 ; Region Definition Block in the job.
21 ;
22 001154 106537 000064 MFPD @#64 ;Get pointer to job's overlay table
23 001160 012601 MOV (SP)+, R1
24 001162 010102 MOV R1, R2 ;Point to region definition block
25 001164 062702 000000G ADD #V0#RDB, R2
26 001170 106562 000000G MFPD R, GSIZ(R2) ;Get # 64-byte blocks to allocate for region
27 001174 012637 000000C MOV (SP)+, RUNRDB+R, GSIZ
28 001200 001456 BEQ 9$ ;Br if no space needed for XM region
29 001202 005037 000000C CLR RUNRDB+R, GSTS ;Clear Region Definition Block status flags
30 001206 CRRG #CSIARE, #RUNRDB ;Create the XM region
31 001226 103451 BCS 10$ ;Br if error while creating the region
32 ;
33 ; Zero the ID numbers in each section of the region.
34 ; This is done to indicate that the code for the section needs to be
35 ; read into the region from disk.
36 ;
37 001230 106561 000000G MFPD V0#WDB(R1) ;Get pointer to first Window Definition Block
38 001234 012602 MOV (SP)+, R2
39 001236 106561 000000G MFPD V0#WDE(R1) ;Get pointer past end of last WDB
40 001242 012603 MOV (SP)+, R3
41 001244 013704 000000C MOV RUNRDB+R, GID, R4 ;Get address of system Region Control Block
42 001250 016400 000000G MOV RC#BAS(R4), R0 ;Get base 64-byte page number of region base
43 001254 010446 1$: MOV R4, -(SP) ;Store pointer to Region Control Block in WDB
44 001256 106662 000000G MTPD W, NRID(R2)
45 001262 010005 MOV R0, R5 ;Get base page number of region
46 001264 106562 000000G MFPD W, NOFF(R2) ;Get offset of window within region
47 001270 062605 ADD (SP)+, R5 ;Get base page # of window
48 001272 DISABL ;: DISABLE
49 001300 013746 000000G MOV @#KPAR0, -(SP) ;: Save mapping for kernel page 0
50 001304 010537 000000G MOV R5, @#KPAR0 ;: Map kernel page 0 to window section
51 001310 005037 000000 CLR @#0 ;: Zero section ID number
52 001314 012637 000000G MOV (SP)+, @#KPAR0 ;: Restore system par 0 mapping
53 001320 ENABL ;: ENABLE
54 001326 062702 000000G ADD #W, SIZE, R2 ;Point to next window definition block
55 001332 020203 CMP R2, R3 ;Have we done all windows?
56 001334 103747 BLO 1$ ;Loop if more windows to do
57 ;

```

```
58 ; Finished
59 ;
60 001336 012605 9#: MOV (SP)+,R5
61 001340 012604 MOV (SP)+,R4
62 001342 012603 MOV (SP)+,R3
63 001344 012602 MOV (SP)+,R2
64 001346 012601 MOV (SP)+,R1
65 001350 000207 RETURN
66 ;
67 ; Error -- Unable to create XM region for job
68 ;
69 001352 012700 177754 10#: MOV #-24,R0 ;Return error code
70 001356 000137 0000000 JMP SETERR
```

```
1          .SBTTL Misc. Kmon EMTs
2          ;-----
3          ; SPOLGO (1) Initiate operation of a spooler.
4          ; Argument word 2 contains the address of the SDCB for the spooled device
5          ; being initiated.
6          ;
7 001362 105737 000000G KMSPLG: TSTB   NSPLDV       ;Are there any spooled devices?
8 001366 001405          BEQ     9$          ;BR IF NOT
9 001370 013700 000004G          MOV     EMTBLK+4,R0    ;GET ADDRESS OF SDCB
10 001374          OCALL  SPOLGO       ;START THE SPOOLER
11 001402 000137 000000G 9$:     JMP     EMTXIT      ;FINISHED
```

```
1 ;-----  
2 ; Get data from within the system.  
3 ;  
4 ; Argument words in EMT block:  
5 ; Word 2: Address of start of data within the kernel.  
6 ; Word 3: Number of bytes of data to transfer.  
7 ; Word 4: Address of buffer within TSKMON where data is to be placed.  
8 ;  
9 001406 013702 0000040 KMSPEK: MOV EMTBLK+4,R2 ;Get address of data wanted  
10 001412 013703 0000060 MOV EMTBLK+6,R3 ;Get # bytes to transfer  
11 001416 013704 0000100 MOV EMTBLK+10,R4 ;Get address of buffer in TSKMON  
12 ;  
13 ; Move data from kernel to TSKMON buffer  
14 ;  
15 001422 006203 ASR R3 ;Get # words to transfer  
16 001424 012246 1$: MOV (R2)+,-(SP) ;Get a word of data onto the stack  
17 001426 106624 MTPD (R4)+ ;Store into TKMON buffer  
18 001430 077303 SOB R3,1$ ;Loop till all words moved  
19 ;  
20 ; Finished  
21 ;  
22 001432 000137 0000000 JMP EMTXIT ;Finished
```

```
1 ;-----  
2 ; Store data into kernel data structure.  
3 ;  
4 ; Argument words in EMT block:  
5 ; Word 2: Address of start of data within the kernel.  
6 ; Word 3: Number of bytes of data to transfer.  
7 ; Word 4: Address of buffer within TSKMON where data is to be fetched.  
8 ;  
9 001436 013702 0000040 KMSPOK: MOV EMTBLK+4,R2 ;Get address of data destination  
10 001442 013703 0000060 MOV EMTBLK+6,R3 ;Get # bytes to transfer  
11 001446 013704 0000100 MOV EMTBLK+10,R4 ;Get address of buffer in TSKMON  
12 ;  
13 ; Move data from TSKMON buffer to kernel  
14 ;  
15 001452 006203 ASR R3 ;Get # words to transfer  
16 001454 106524 1$: MFPD (R4)+ ;Get a word of data from TSKMON buffer  
17 001456 012622 MOV (SP)+,(R2)+ ;Store into kernel space  
18 001460 077303 SOB R3,1$ ;Loop till all words moved  
19 ;  
20 ; Finished  
21 ;  
22 001462 000137 0000000 JMP EMTXIT ;Finished
```

```
1 ;-----  
2 ; Suspend or resume execution of a job.  
3 ;  
4 001466 013701 0000040 KMSPRS: MOV EMTBLK+4,R1 ;Get # of job to suspend or resume  
5 001472 001420 BEQ 9$ ;Zero is invalid  
6 001474 032761 0000000 0000000 BIT ##DILUP,LSW(R1) ;Is job logged on?  
7 001502 001414 BEQ 9$ ;Br if not  
8 001504 105737 0000000 TSTB EMTBLK ;Suspend or resume the job?  
9 001510 001004 BNE 1$ ;Br if resume  
10 ;  
11 ; Suspend execution of the job  
12 ;  
13 001512 052761 0000000 0000000 BIS ##SUSPN,LSW(R1) ;Set suspend-execution flag for job  
14 001520 000405 BR 9$  
15 ;  
16 ; Resume execution of the job  
17 ;  
18 001522 042761 0000000 0000000 1$: BIC ##SUSPN,LSW(R1) ;Clear suspend-job flag  
19 001530 004737 0000000 CALL FORCEX ;Force job to run  
20 ;  
21 ; Finished  
22 ;  
23 001534 000137 0000000 9$: JMP EMTXIT
```

```

1 ; -----
2 ; Cross connect a TT line to a CL unit.
3 ; Word 3 of EMT argument block contains CL unit number.
4 ;
5 001540 CLXCON:
6 ;
7 ; Treat this as a NOP if this is a detached job
8 ;
9 001540 032761 000000G 000000G BIT #DETCH,LSW(R1) ;Is this a detached job?
10 001546 001050 BNE 9$ ;Br if yes
11 ;
12 ; Ensure that pending terminal output is flushed
13 ;
14 001550 026161 000000G 000000G 2$: CMP LOTSPC(R1),LOTSIZ(R1) ;Any output still pending?
15 001556 001405 BEQ 3$ ;Go ahead if not
16 001560 012700 000000G MOV #S$CPU,RO ;Get out of everybody's way while waiting
17 001564 004737 000000G CALL ENQTL ;Give somebody else a chance while waiting
18 001570 000767 BR 2$ ;And check again
19 ;
20 ; Get Desired CL unit
21 ;
22 001572 013705 000004G 3$: MOV EMTBLK+4,R5 ;Get desired CL unit index number
23 ;
24 ; Say CL unit connected to TT line
25 ;
26 001576 016104 000000G MOV LNPRIM(R1),R4 ;Get primary line #
27 001602 010465 000000G MOV R4,CL$XLN(R5) ;Set # of TT line connected to CL
28 001606 042765 000000C 000000G BIC #^C<CM$BRK>,CL$STA(R5) ;Init status flags for CL unit
29 001614 052765 000000G 000000G BIS #CM$ON,CL$STA(R5) ;And say line is in use
30 ;
31 ; Connect TT unit to CL line
32 ;
33 001622 010564 000000G MOV R5,LXCL(R4) ;Connect CL unit to our line
34 001626 012764 000000G 000000G MOV #CLXICP,LINIR(R4) ;Set addr of input char processing routine
35 ;
36 ; Raise DTR on CL unit
37 ;
38 001634 052765 000000G 000000G BIS #CO$DTR,CL$OPT(R5) ;Request DTR up
39 001642 OCALL SETDTR ;Call CL routine to raise DTR
40 ;
41 ; Suspend execution of job until cross connection is broken
42 ;
43 001650 005764 000000G 1$: TST LXCL(R4) ;Are we still cross connected?
44 001654 002405 BLT 9$ ;Br if not
45 001656 012700 000000G MOV #S$SPND,RO ;Get sleep state
46 001662 004737 000000G CALL QNSPND ;Suspend execution of job
47 001666 000770 BR 1$ ;See if connection has been broken
48 ;
49 ; Finished
50 ;
51 001670 000137 000000G 9$: JMP EMTXIT

```

```
1 ;-----  
2 ; Start a terminal line  
3 ;  
4 001674 013701 000004G STTTLN: MOV EMTBLK+4,R1 ;Get index # of line to be started  
5 001700 032761 000000G 000000G BIT ##DILUP,LSW(R1) ;Is line already started?  
6 001706 001017 BNE 9$ ;Br if yes  
7 001710 032761 000000G 000000G BIT ##AUTO,ILSW2(R1);Is line set to autobaud?  
8 001716 001404 BEQ 1$ ;Br if not  
9 001720 012700 000000G MOV #S9600,R0 ;Set speed to 9600 baud  
10 001724 004737 000000G CALL SETSPD ;Set the line speed  
11 001730 005000 1$: CLR R0 ;No secondary start-up command file  
12 001732 OCALL INITLN ;Initialize the line  
13 001740 042761 000000G 000000G BIC ##RBRK,LSW10(R1);Clear break-received flag  
14 001746 000137 000000G 9$: JMP EMTXIT
```

Misc. Kmon EMTs

```

1          ; -----
2          ; Force logoff of a job.
3          ;
4 001752 013702 000004G KILEMT: MOV      EMTBLK+4,R2    ;GET # OF JOB TO KILL
5 001756 004737 006650'   CALL      CKACJB      ;See if we have privilege to kill that job
6 001762 103405           BCS      10$          ;Br if don't have privilege
7 001764 010200           MOV      R2,R0        ;Get # of job to kill
8 001766 004737 002004'   CALL      KILJOB      ;KILL THE JOB
9 001772 000137 000000G   JMP      EMTXIT      ;FINISHED
10 001776 005000          10$:   CLR      R0          ;Return error code 0
11 002000 000137 000000G   JMP      SETERR
12          ; -----
13          ; Subroutine to "kill" (force logoff) of a job.
14          ;
15          ; Inputs:
16          ; R0 = Virtual job index number of job to kill.
17          ;
18          ;
19 002004 010146          KILJOB: MOV      R1,-(SP)
20 002006 010546           MOV      R5,-(SP)
21 002010 010001           MOV      R0,R1        ;Get virtual job index number
22          ;
23          ; See if job is currently logged on
24          ;
25 002012 032761 000000G 000000G   BIT      #$DILUP,LSW(R1) ;IS JOB LOGGED ON NOW?
26 002020 001435           BEQ      9$          ;BR IF NOT
27          ;
28          ; If this line is cross connected with a CL line, break the connection.
29          ;
30          ;
31          ;
32          ;
33          ;
34          ;
35          ;
36          ;
37          ; Clear ctrl-S output suspension and ctrl-O output suppression and
38          ; set flag saying job is being killed.
39          ;
40 002050 016100 000000G 1$:   MOV      LNPRIM(R1),R0 ;GET PRIMARY LINE NUMBER
41 002054 042760 000000G 000000G   BIC      #$CTRLS,LSW3(R0);RESET CTRL-S OUTPUT SUSPENSION
42 002062 042761 000000G 000000G   BIC      #$CTRLD,LSW3(R1);RESET CTRL-O OUTPUT SUSPENSION
43 002070 042761 000000G 000000G   BIC      #$SUSPN,LSW(R1);Clear job-suspended flag
44 002076 052761 000000G 000000G   BIS      #$DISCN,LSW(R1);FORCE LOGOFF
45          ;
46          ; Start output transmission for job
47          ;
48 002104 004777 000000G           CALL      @TRNSTR      ;Start output transmission
49          ;
50          ; Force job to execute
51          ;
52 002110 004737 000000G           CALL      FORCEX        ;FORCE ITS EXECUTION
53          ;
54          ; Finished
55          ;
56 002114 012605          9$:   MOV      (SP)+,R5
57 002116 012601           MOV      (SP)+,R1

```

58 002120 000207

RETURN

```
1 ;-----  
2 ; Clean out data cache.  
3 ;  
4 002122 005737 0000006 CSHNEW: TST CSHALC ; Is data caching genned into system?  
5 002126 001402 BEQ 1$ ; Br if not  
6 002130 004777 0000006 CALL @CSHINI ; Clean out the data cache  
7 002134 000137 0000006 1$: JMP EMTXIT
```

```
1 ;-----  
2 ; Delete a spool file.  
3 ; Form of the EMT:  
4 ; .BYTE 0,126  
5 ; .WORD 7  
6 ; .WORD file_id_number  
7 ;  
8 002140 KMSDDL:  
9 ;  
10 ; See if spooling support is included in this system  
11 ;  
12 002140 105737 0000000 TSTB NSPLDV ;Are there any spooled devices?  
13 002144 001410 BEQ 1$ ;Br if not  
14 ;  
15 ; Get the file id number and delete the file  
16 ;  
17 002146 013703 0000040 MOV EMTBLK+4,R3 ;Get spool file ID number  
18 002152 OCALL SPLDEL ;Try to delete the file  
19 002160 103402 BCS 1$ ;Br if could not find the file  
20 002162 000137 0000000 JMP EMTXIT  
21 ;  
22 ; Specified file could not be found  
23 ;  
24 002166 012700 000001 1$: MOV #EC1,R0  
25 002172 000137 0000000 JMP SETERR
```

VLSEMT -- EMT to switch between subprocesses

```

1          .SBTTL  VLSEMT -- EMT to switch between subprocesses
2          ;-----
3          ; The form of the EMT used to switch between subprocesses is
4          ;
5          ; .BYTE  sub_function,162
6          ; .BYTE  subprocess_number,0
7          ; .BYTE  return_process,initiate_only
8          ; .WORD  pointer_to_start_up_file_string
9          ;
10         ; Where subprocess_number is the relative subprocess number for the
11         ; job (0=primary process).
12         ;
13 002176 005037 000000G VLSEMT: CLR      URO          ;Return 0 in R0 if error
14         ;
15         ; See if job is authorized to use subprocesses
16         ;
17 002202 032761 000000G 000000G BIT      ##NOVLN,LSW2(R1); Is job allowed to use subprocesses?
18 002210 001014 BNE      1$          ;Br if not
19 002212 032761 000000G 000000G BIT      ##DETCH,LSW(R1); Is this a detached job?
20 002220 001010 BNE      1$          ;Br if detached
21 002222 032761 000000C 000000G BIT      <##$SUCF!$LDPCF>,LSW9(R1); Doing logon/logoff processing?
22 002230 001004 BNE      1$          ;Br if yes
23 002232 032761 000000G 000000G BIT      ##NOIN,LSW3(R1); Doing logon/logoff processing?
24 002240 001404 BEQ      2$          ;Br if not
25 002242 012700 000001 1$:      MOV      #EC1,R0          ;Error 1 if not allowed to use subprocesses
26 002246 000137 000000G JMP      SETERR
27         ;
28         ; See if he specified a process number or wants us to find a free one
29         ;
30 002252 113705 000002G 2$:      MOVVB   EMTBLK+2,R5      ;Get specified subprocess number
31 002256 001570 BEQ      4$          ;Br if switching to primary process
32 002260 003015 BGT      12$         ;Br if subprocess number specified
33 002262 012705 000001 MOV      #1,R5      ;Start with subprocess # 1
34 002266 016103 000000G MOV      LNPRIM(R1),R3 ;Get primary line #
35 002272 016303 000000G MOV      LSECPT(R3),R3 ;Point to table of secondary line numbers
36 002276 020527 000000G 13$:   CMP      R5,#MAXSEC ;Are there more subprocesses available to job?
37 002302 101050 BHI      6$          ;Br if not
38 002304 105723 TSTB   (R3)+        ;Is this subprocess free?
39 002306 001423 BEQ      15$         ;Br if free
40 002310 005205 INC      R5          ;Advance subprocess number
41 002312 000771 BR      13$         ;Continue searching for a free subprocess
42         ;
43         ; See if the specified process number is valid
44         ;
45 002314 020527 000000G 12$:   CMP      R5,#MAXSEC ;Is subprocess number too large?
46 002320 101407 BLOS   3$          ;Br if ok
47 002322 012737 000000G 000000G MOV      #MAXSEC,URO ;Return MAXSEC to user in R0
48 002330 012700 000002 MOV      #EC2,R0    ;Error 2 -- Subprocess number too big
49 002334 000137 000000G JMP      SETERR
50         ;
51         ; Switching to a subprocess.
52         ; See if subprocess has been allocated yet.
53         ;
54 002340 016102 000000G 3$:      MOV      LNPRIM(R1),R2 ;Get primary line #
55 002344 016203 000000G MOV      LSECPT(R2),R3 ;Point to table of secondary line numbers
56 002350 060503 ADD      R5,R3      ;Point to entry for selected process
57 002352 105743 TSTB   -(R3)       ;Has this subprocess been allocated yet?

```

VLSEMT -- EMT to switch between subprocesses

```

58 002354 001131          BNE      4$          ;Br if yes
59
60          ; Request to switch to a subprocess which has not been allocated yet.
61
62 002356 123727 000000G 000002 15$:   CMPB     EMTBLK,#2      ;Is it ok to start a new subprocess?
63 002364 001004          BNE      18$          ;Br if yes
64 002366 012700 000006          MOV     #EC6,R0       ;Error 6 -- Subprocess not active
65 002372 000137 000000G          JMP     SETERR
66
67          ; See if we can find a free subprocess.
68
69 002376 012703 000000G 18$:   MOV     #FSTSL,R3     ;Get job # of first subprocess
70 002402 020327 000000G 5$:   CMP     R3,#LSTSL    ;Checked all?
71 002406 101006          BHI     6$           ;Br if yes
72 002410 005763 000000G          TST     LNPRIM(R3)   ;Is this line available?
73 002414 001407          BEQ     7$           ;Br if yes
74 002416 062703 000002          ADD     #2,R3        ;Get index to next subprocess
75 002422 000767          BR     5$           ;Continue search
76
77          ; There are no free subprocesses
78
79 002424 012700 000003 6$:   MOV     #EC3,R0       ;Error 3 -- No free subprocesses
80 002430 000137 000000G          JMP     SETERR
81
82          ; We have found a free subprocess.
83          ; Its index is in R3.
84          ; Validate address of pointer to secondary start-up command file name string.
85
86 002434 013700 000006G 7$:   MOV     EMTBLK+6,R0  ;Get virtual address of name string
87 002440 001402          BEQ     17$          ;Br if no start-up file specified
88 002442 004737 000000G          CALL   VALADB       ;Validate the address
89
90          ; Allocate an I/O queue element to use to pass information to the
91          ; job initiator.
92
93 002446 010146 17$:   MOV     R1,-(SP)     ;Save our job index number
94 002450 010346          MOV     R3,-(SP)
95 002452 004737 000000G          CALL   GETQ        ;Get a free I/O queue element (R1=address)
96 002456 105061 000000G          CLRB   IB$SF2(R1)  ;Assume no secondary start-up command file
97
98          ; See if we need to set up a secondary start-up command file for the
99          ; process that is being initiated.
100
101 002462 013703 000006G          MOV     EMTBLK+6,R3 ;Is there a start-up command file string?
102 002466 001412          BEQ     16$          ;Br if no secondary start-up command file
103 002470 010104          MOV     R1,R4       ;Point to buffer where name will be stored
104 002472 062704 000000G          ADD     #IB$SF2,R4  ;Point to cell in buffer for name
105 002476 012702 177777G          MOV     #SF2LEN-1,R2 ;Get # chars reserved for file name
106 002502 004737 000000G 11$:  CALL   GETUCH       ;Get char from user's buffer
107 002506 110024          MOVB   R0,(R4)+     ;Store into buffer
108 002510 077204          SOB   R2,11$       ;Loop till all of name moved
109 002512 105014          CLRB   (R4)        ;Make sure there is a null at the end
110
111          ; Complete initialization of buffer passing info to job initiator
112
113 002514 010100 16$:   MOV     R1,R0       ;Save pointer to initiation info buffer
114 002516 012603          MOV     (SP)+,R3

```

VLSEMT -- EMT to switch between subprocesses

```

115 002520 012601          MOV      (SP)+,R1      ;Get back current process index
116 002522 105737 000004G  TSTB    EMTBLK+4      ;Return to our process or primary process?
117 002526 001402          BEQ     10$           ;Br if return to primary process
118 002530 110160 000000G  MOVB   R1,IB$IJ(R0)   ;Set our process # as initiating job
119
120          ; At this point, R0=Pointer to buffer with initialization info (IB$xxx).
121          ; Initialize the subprocess.
122
123 002534 010146 10$:    MOV     R1,-(SP)      ;Save original process number
124 002536 010301          MOV     R3,R1         ;Get new process number
125 002540          OCALL  INITLN      ;Initialize the new process
126 002546 103004          BCC    8$           ;Br if initialization ok
127 002550 012700 000004   MOV     #EC4,R0       ;Error 4 -- Insufficient memory for process
128 002554 000137 000000G  JMP     SETERR
129 002560 052761 000000G 000000G 8$:    BIS    #$VBELL,LSW9(R1); Don't ring bell when new subprocess waits
130 002566 105737 000005G  TSTB    EMTBLK+5      ;Are we going to switch terminal control?
131 002572 001404          BEQ     20$           ;Br if yes
132 002574 052761 000000G 000000G  BIS    #$VNOTT,LSW(R1); Say subprocess not connected to terminal
133 002602          OCALL  SPPRED      ;Reduce execution priority of initiated proc
134 002610 012601 20$:    MOV     (SP)+,R1      ;Get back original process number
135
136          ; Make association between subprocess and primary process
137
138 002612 016102 000000G  MOV     LNPRIM(R1),R2  ;Get primary process number
139 002616 010263 000000G  MOV     R2,LPARNT(R3) ;Say primary job is parent of subprocess
140 002622 016204 000000G  MOV     LSECT(R2),R4  ;Point to subprocess # table
141 002626 060504          ADD     R5,R4         ;Point to desired entry
142 002630 110344          MOVB   R3,-(R4)      ;Associate subprocess with primary
143 002632 010263 000000G  MOV     R2,LNPRIM(R3) ;Set primary process for subprocess
144 002636 000410          BR     19$
145
146          ; We are switching to a process that has been initialized.
147
148 002640 123727 000000G 000001 4$:    CMPB   EMTBLK,#1     ;Can we use an existing process?
149 002646 001004          BNE    19$           ;Br if yes
150 002650 012700 000005   MOV     #EC5,R0       ;Error 5 -- Process already exists
151 002654 000137 000000G  JMP     SETERR
152
153          ; Switch terminal connection to the selected process.
154
155 002660 105737 000005G 19$:    TSTB   EMTBLK+5      ;Initiate subprocess only?
156 002664 001006          BNE    9$           ;Br if yes -- Don't switch terminal control
157 002666          OCALL  LINSWT      ;Set up line number prompt
158
159          ; Set flag to suppress bell ringing when this line goes into wait state
160
161 002674 052761 000000G 000000G  BIS    #$VBELL,LSW9(R1); Say not to ring bell when we wait
162
163          ; Return subprocess number to calling program in R0
164
165 002702 010537 000000G 9$:    MOV     R5,URO       ;Return subprocess # in R0
166
167          ; Finished
168
169 002706 000137 000000G  JMP     EMTXIT      ;Finished with EMT

```

```

1          .SBTTL Detached job control emt's
2          ;-----
3          ; This set of emt's is used to control detached jobs.
4          ; The emt function code is 132. The sub-function code is stored in
5          ; byte 0 of the argument block. The valid sub-function codes are:
6          ; 0==>Start a detached job.
7          ; 1==>Check status of a detached job.
8          ; 2==>Kill a detached job.
9          ;
10         DETEMT:
11         ;
12         ; Jump to processing routine based on sub-function code.
13         ;
14         002712 113700 0000000  MOVB   EMTBLK,R0      ;GET SUB-FUNCTION CODE
15         002716 020027 0000003  CMP    R0,#DETHI    ;IS SUB-FUNCTION VALID?
16         002722 103003          BHI   2$            ;BR IF NOT
17         002724 006300          ASL   R0            ;CONVERT TO WORD TABLE INDEX
18         002726 000170 003226'  JMP   @DETVEC(R0)  ;ENTER PROCESSING ROUTINE
19         002732 005000          2$:  CLR   R0        ;Return error code 0
20         002734 000137 0000000  JMP   SETERR
21         ;
22         ; Start a new detached job.
23         ;
24         002740 032737 0000000 0000000 DETG0: BIT    #P0$DET,PRIVCO ;Is this user allowed to access detached jobs?
25         002746 001003          BNE   10$          ;Br if yes
26         002750 005000          CLR   R0           ;Return error code 0 if not
27         002752 000137 0000000  JMP   SETERR
28         ;
29         ; Search for a free detached job line.
30         ;
31         002756 012701 0000000 10$:  MOV   #FSTD,L,R1  ;GET # OF FIRST DETACHED JOB LINE
32         002762 020127 0000000 3$:  CMP   R1,#LSTD,L  ;HAVE WE CHECKED ALL?
33         002766 101043          BHI   DETONE       ;BR IF YES -- NONE FREE
34         002770 032761 0000000 0000000  BIT   #$DILUP,LSW(R1) ;IS THIS LINE FREE?
35         002776 001403          BEQ   2$           ;BR IF YES
36         003000 062701 0000002  ADD   #2,R1        ;GO TRY NEXT
37         003004 000766          BR    3$
38         ; Found a free detached job line.
39         ; Set name of start-up command file.
40         003006 013703 0000002 2$:  MOV   EMTBLK+2,R3  ;GET ADDRESS OF START-UP FILE NAME ARGUMENT
41         003012 010300          MOV   R3,R0        ;VALIDATE THE ADDRESS
42         003014 004737 0000000  CALL  VALADB
43         003020 016102 0000000  MOV   LSUCF(R1),R2 ;GET ADDRESS WHERE WE SHOULD STORE NAME
44         003024 012705 0000000  MOV   #DETCBS,R5   ;GET COUNT OF MAX # CHARS TO MOVE
45         003030 004737 0000000 4$:  CALL  GETUCH       ;GET CHAR FROM USER'S BUFFER
46         003034 110022          MOVB  R0,(R2)+     ;STORE AS START-UP FILE NAME FOR LINE
47         003036 001402          BEQ   6$           ;BR IF MOVED NULL AT END OF NAME
48         003040 077505          SOB  R5,4$        ;LOOP TO MOVE REST OF NAME
49         003042 105012          CLRB (R2)         ;PUT NULL AT END OF NAME
50         ; Start up the line.
51         003044 005000          6$:  CLR   R0        ;No secondary start-up command file
52         003046          OCALL  INITLN     ;INITIALIZE THE LINE
53         003054 103410          BCS  DETONE       ;BR IF INSUFFICIENT MEMORY TO START JOB
54         ; Set number of parent job
55         003056 113761 0000000 0000000  MOVB  CORUSR,LPARNT(R1);Set # of parent job
56         ; Return detached job line number to user in R0.
57         003064 006201          ASR  R1           ;CONVERT TO LINE NUMBER

```



```

1          .SBTTL Shared Run-time control emt's
2          ;-----
3          ; All of the shared run-time control emt's have an emt function
4          ; code of 143. The sub-function code is stored in byte 0 of the
5          ; emt argument block.
6          ;
7          ; Sub-functions:
8          ; 0 ==> Associate or disassociate a run-time system.
9          ; 1 ==> Map part of a run-time system into job's virtual memory area.
10         ; 2 ==> Define shared run-time region for fast mapping.
11         ; 3 ==> Disable fast run-time region mapping (restore TRAP instr.)
12         ; 4 ==> Enable I/D space split
13         ; 5 ==> Disable I/D space split (return to all I-space)
14         ; 6 ==> Define PLAS region for fast mapping
15         ;
16 003234 113700 0000000 SSEMT:  MOVB   EMTBLK,RO      ;Get sub-function code
17 003240 020027 0000007         CMP    RO,#SSEHI    ;Valid sub-function code?
18 003244 103402         BLO    1$          ;Br if OK
19 003246 000137 0000000         JMP    BADEMT     ;Invalid sub-function
20 003252 006300 1$:      ASL    RO          ;Convert sub-function to word index
21 003254 000170 003260'        JMP    @SSEVEC(RO) ;Jump to appropriate routine
22         ;
23         ; Define jump vector table for mapping emts
24         ;
25 003260 003276' SSEVEC: .WORD  SSASOC      ;0 - associate a run-time system
26 003262 003450'         .WORD  SSMAP       ;1 - map to shared run-time system
27 003264 003574'         .WORD  SSREGN      ;2 - define fast map to shared run-time
28 003266 003774'         .WORD  SSNOMP      ;3 - disable fast mapping (restore TRAP use)
29 003270 004132'         .WORD  ESPLIT     ;4 - enable I/D space split
30 003272 004172'         .WORD  DSPLIT     ;5 - restore all I space
31 003274 004220'         .WORD  SSPLAS     ;6 - define fast map to PLAS region
32         ;
33         SSEHI = < -SSEVEC > / 2 ;This and higher subfunctions are invalid
34         ;

```

```

1          .SBTTL Associate shared run-time system with job
2          ;-----
3          ; This emt is used to associate a shared run-time system with a job.
4          ; The form of the emt argument block is:
5          ;
6          ; .BYTE 0,143
7          ; .WORD name-pointer
8          ;
9          ; Where name-pointer is the address of a two word cell containing the
10         ; rad50 name of the run-time system to be associated.
11         ;
12 003276 013700 0000020 SSASOC: MOV EMTBLK+2,R0 ;GET ADDRESS OF NAME CELL
13 003302 001024         BNE 2$ ;BR IF WE ARE ASSOCIATING A RUN-TIME
14         ;
15         ; Name pointer is zero -- Disassociate all run-time systems
16         ;
17 003304 005037 0000000 CLR CURRDB ;NO ASSOCIATED RUN-TIME
18 003310 005002         CLR R2 ;INIT PAR INDEX
19 003312 005062 0000000 1$: CLR RPAR(R2) ;CLEAR PAR VALUE
20 003316 005062 0000000 CLR RPDR(R2) ;CLEAR PDR VALUE
21 003322 062702 0000002 ADD #2,R2 ;ADVANCE TO NEXT SET
22 003326 020227 0000016 CMP R2,#2*7 ;DONE ALL?
23 003332 101767         BLOS 1$ ;BR IF MORE TO CLEAR
24 003334 005737 0000000 TST VPLAS ;Do we have PLAS support?
25 003340 001403         BEQ 7$ ;Br if not
26 003342         DCALL MAPPLS ;Set up info about any PLAS regions
27 003350 004737 0000000 7$: CALL SETMAP ;RELOAD MAP REGISTERS FOR JOB
28 003354 000137 0000000 JMP EMTXIT ;FINISHED
29         ;
30         ; Associate new shared run-time system with job
31         ;
32 003360 004737 0000000 2$: CALL VALADW ;VALIDATE THE ADDRESS
33 003364 106520         MFPD (R0)+ ;GET 1ST WORD OF RUN-TIME NAME
34 003366 012604         MOV (SP)+,R4
35 003370 106520         MFPD (R0)+ ;GET 2ND WORD OF RUN-TIME NAME
36 003372 012605         MOV (SP)+,R5
37         ;
38         ; Search for run-time system descriptor with matching name
39         ;
40 003374 012703 0000000 MOV #RDB,R3 ;POINT TO 1ST RUN-TIME DESCRIPTOR BLOCK
41 003400 020327 0000000 3$: CMP R3,#RDBEND ;CHECKED ALL RUN-TIME DESCRIPTOR BLOCKS?
42 003404 103015         BHIS 6$ ;BR IF YES
43 003406 020463 0000000 CMP R4,RT$NAM(R3) ;COMPARE 1ST WORD OF NAME
44 003412 001003         BNE 5$ ;BR IF MISMATCH
45 003414 020563 0000020 CMP R5,RT$NAM+2(R3) ;COMPARE 2ND WORD OF NAME
46 003420 001403         BEQ 4$ ;BR IF FOUND RIGHT BLOCK
47 003422 062703 0000000 5$: ADD #RT$$SZ,R3 ;POINT TO NEXT RUN-TIME DESCRIPTOR BLOCK
48 003426 000764         BR 3$ ;GO CHECK NEXT ONE
49         ;
50         ; Found run-time descriptor block
51         ; Associate the run-time system with the job
52         ;
53 003430 010337 0000000 4$: MOV R3,CURRDB ;SAY RUN-TIME SYSTEM IS ASSOCIATED WITH JOB
54 003434 000137 0000000 JMP EMTXIT ;FINISHED
55         ;
56         ; Error -- Cannot find named run-time system
57         ; Return error code of 1

```

```
58  
59 003440 012700 000001      ;  
60 003444 000137 000000G    6#:  MOV  #EC1,R0      ;RETURN ERROR CODE 1  
                               JMP  SETERR
```

```

1          .SBTTL  Map shared run-time system into user's virtual address
2          ;-----
3          ; This emt is used to map a portion of a shared run-time system into
4          ; the virtual address region of the job.
5          ; The form of the emt is:
6          ;
7          ;       .BYTE  1,143
8          ;       .WORD  user-par          ;0 to 7
9          ;       .WORD  run-time-offset ;64-byte units
10         ;       .WORD  size             ;64-byte units
11         ;
12 003450  SSMAP:
13         ;
14         ; Call routine to check arguments and bias base address
15         ;
16 003450 004737 004004' CALL  SSSTUP          ;Do common mapping setup
17         ;
18         ; Set up mapping information for each par
19         ;
20 003454 010500 3$:  MOV  R5,R0          ;CALCULATE # 64-BYTE BLOCKS
21 003456 160400      SUB  R4,R0          ; LEFT TO ALLOCATE
22 003460 003443      BLE  6$          ;BR IF FINISHED
23 003462 010462 000000 MOV  R4,RPAR(R2)      ;SET PAR BASE OFFSET VALUE
24 003466 010462 000000 MOV  R4,CUPAR0(R2)   ;SAVE INFORMATION IN JOB CONTEXT BLOCK
25 003472 010462 000000 MOV  R4,UPAR0(R2)   ;SET HARDWARE REGISTER
26 003476 020027 000200 CMP  R0,#200        ;EACH PAR CAN MAP UP TO 200 64-BYTE BLOCKS
27 003502 101402      BLOS 4$          ;BR IF WE CAN MAP ALL THAT'S LEFT
28 003504 012700 000200 MOV  #200,R0        ; ONLY MAP 200 THROUGH THIS PAR
29 003510 060004 4$:  ADD  R0,R4          ;ADVANCE BASE OFFSET NUMBER
30 003512 005300      DEC  R0          ;PDR VALUE IS ACTUAL-1
31 003514 000300      SWAB R0          ;POSITION LENGTH FOR PDR REGISTER
32 003516 052700 000002 BIS  #2,R0          ;SET READ-ALLOWED FLAG FOR PDR
33 003522 132763 000000G 000000G BITB #RF$WRT,RT$FLG(R3); IS WRITE ACCESS TO BE ALLOWED?
34 003530 001402      BEQ  5$          ;BR IF NOT
35 003532 052700 000004 BIS  #4,R0          ;SET WRITE-ALLOWED FLAG FOR PDR
36 003536 042700 100261 5$:  BIC  #100261,R0      ;MAKE SURE UNUSED PDR BITS ARE ZERO
37 003542 010062 000000G MOV  R0,RPDR(R2)     ;THIS IS PDR VALUE FOR PAR RANGE
38 003546 010062 000000G MOV  R0,CUPDR0(R2)   ;SAVE INFORMATION IN JOB CONTEXT BLOCK
39 003552 010062 000000G MOV  R0,UPDR0(R2)   ;SET HARDWARE MAPPING
40 003556 062702 000002 ADD  #2,R2          ;ADVANCE PAR INDEX #
41 003562 020227 000016 CMP  R2,#2*7        ;ONLY DO PAR UP TO # 7
42 003566 101732      BLOS 3$          ;BR IF MORE TO DO
43         ;
44         ; Finished
45         ;
46 003570 000137 000000G 6$:  JMP  EMTXIT          ;FINISHED

```

Define a run-time region for fast mapping

```

1          .SBTTL Define a run-time region for fast mapping
2          ;-----
3          ; Define a run-time region so that it can be quickly mapped using
4          ; the TRAP instruction.
5          ;
6          ; EMT argument list:
7          ; .BYTE 2,143
8          ; .WORD user-par ;PAR to map to region (0 to 7)
9          ; .WORD run-time-offset ;Offset within run-time (64-byte units)
10         ; .WORD size ;# 64-byte units to map
11         ; .WORD region-index ;0 to MAXSRD-1
12         ;
13 003574  SSREGN:
14         ;
15         ; Call routine to check arguments and bias base address
16         ;
17 003574 004737 004004' CALL SSSTUP ;Do common mapping setup
18         ;
19         ; At this point the following registers are set up:
20         ; R2 = PAR index number (2 * PAR).
21         ; R3 = Pointer to current run-time descriptor block.
22         ; R4 = Starting 64-byte physical address of region.
23         ; R5 = Ending 64-byte physical address of region.
24         ;
25         ; Make sure the region-index value is valid.
26         ;
27 003600 160405 SUB R4,R5 ;R5 now has # blocks to be mapped
28 003602 013700 000010G MOV EMTBLK+10,R0 ;Get specified region #
29 003606 020027 000000G 1$: CMP R0,#MAXSRD ;Is the number valid?
30 003612 103404 BLO 11$ ;Br if ok
31 003614 012700 000002 MOV #EC2,R0 ;Return error code 2
32 003620 000137 000000G JMP SETERR
33         ;
34         ; Remember which PAR is set by this region
35         ;
36 003624 110260 000000G 11$: MOVB R2,SR$PX(R0) ;Save PAR index (2*PAR #)
37 003630 105060 000000G CLRB SR$FLG(R0) ;No special mapping flags yet
38         ;
39         ; Set the PAR value in the region descriptor
40         ;
41 003634 006300 ASL R0 ;Get word table index
42 003636 005060 000000G CLR SR$WCB(R0) ;This is a shared run-time region (not PLAS)
43 003642 010460 000000G MOV R4,SR$PAR(R0) ;Set base PAR value for region
44         ;
45         ; Set the PDR value for the region
46         ;
47 003646 010501 MOV R5,R1 ;Get # blocks remaining to map
48 003650 020127 000200 CMP R1,#200 ;Will it all fit thru 1 par?
49 003654 101402 BLOS 2$ ;Br if ok
50 003656 012701 000200 MOV #200,R1 ;If not, decrease to 1 par worth
51 003662 160105 2$: SUB R1,R5 ;This many left to map next time
52 003664 060104 ADD R1,R4 ;Bump up base address for next time
53 003666 005301 DEC R1 ;PDR size is 1 less than wanted
54 003670 000301 SWAB R1 ;Position size for PDR value
55 003672 132763 000000G 000000G BITB #RF$WRT,RT$FLG(R3);Can we write to shared run-time?
56 003700 001402 BEQ 3$ ;Br if not
57 003702 052701 000004 BIS #4,R1 ;Set flag in PDR value saying write ok

```

Define a run-time region for fast mapping

```

58 003706 052701 000002      3#:   BIS      #2,R1      ;Set flag in PDR value saying read ok
59 003712 042701 100261      BIC      #100261,R1   ;Make sure unused bits are clear
60 003716 010160 000000G     MOV      R1,SR#PDR(R0) ;Store PDR value
61 003722 005705      TST      R5          ;Any more left to map?
62 003724 001416      BEQ      5#          ;Br if not
63                          ;
64                          ; More than 8Kb space requested, use more pars
65                          ;
66 003726 062702 000002      ADD      #2,R2        ;Increment to next par index
67 003732 020227 000016      CMP      R2,#2*7     ;Valid PAR index?
68 003736 101006      BHI      37#        ;Br if not
69 003740 006200      ASR      R0          ;Convert trap region index back to #
70 003742 152760 000000G 000000G  BISB    #SR.MDR,SR#FLG(R0) ;Say there are more to map
71 003750 005200      INC      R0          ;Step up to next fast map region #
72 003752 000715      BR      1#          ;Repeat until entire window set up
73                          ;
74                          ; Attempt to map past par 7
75                          ;
76 003754 005000      37#:   CLR      R0          ;Return ECO
77 003756 000137 000000G     JMP      SETERR      ;Return error to user
78                          ;
79                          ; Finished
80                          ;
81 003762 112737 000001 000000G 5#:   MOVB    #1,DOTRMP   ;Enable TRAP to do mapping
82 003770 000137 000000G     JMP      EMTXIT
83                          ;
84                          ;-----
85                          ; Disable fast run-time mapping and return the TRAP instruction to
86                          ; its standard use.
87                          ;
88 003774 105037 000000G     SSNDMP: CLRB    DOTRMP   ;Say mapping not in effect
89 004000 000137 000000G     JMP      EMTXIT

```

Define a run-time region for fast mapping

```

1          ; -----
2          ; Common routine used to process arguments for shared run-time
3          ; mapping EMT's.
4          ;
5          ; Outputs:
6          ; R2 = PAR index number (2 * PAR).
7          ; R3 = Pointer to current run-time descriptor block.
8          ; R4 = Starting 64-byte physical address of region.
9          ; R5 = Ending 64-byte physical address of region.
10         ; URO = Size of area that is being mapped.
11         ;
12 004004  SSSTUP:
13         ;
14         ; Check the specified PAR number
15         ;
16 004004 013702 0000020  MOV     EMTBLK+2,R2    ;Get PAR #
17 004010 020227 0000007  CMP     R2,#7         ;Must be in range 0 to 7
18 004014 101404          BLOS   7#             ;Br if ok
19 004016 012700 177767  MOV     #-11,R0       ;Fatal error if other value
20 004022 000137 0000000  JMP     SETERR
21 004026 006302          7#:    ASL     R2         ;Convert par # to word table index
22         ;
23         ; Get pointer to descriptor for current shared run-time system
24         ;
25 004030 013703 0000000  MOV     CURRDB,R3     ;Get address of associated run-time descriptor
26 004034 001004          BNE    1#             ;Better be one
27 004036 012700 0000001  MOV     #EC1,R0       ;If not then return error code 1
28 004042 000137 0000000  JMP     SETERR
29         ;
30         ; Get physical memory address
31         ;
32 004046 013704 0000040  1#:    MOV     EMTBLK+4,R4 ;Get run-time base offset
33 004052 020463 0000000  CMP     R4,RT$TOP(R3) ;Make sure it is within run-time area
34 004056 103404          BLO   3#             ;Br if ok
35 004060 012700 0000005  MOV     #EC5,R0       ;Return error 5 if too high
36 004064 000137 0000000  JMP     SETERR
37 004070 013705 0000060  3#:    MOV     EMTBLK+6,R5 ;Get size of region to be mapped
38 004074 060405          ADD   R4,R5         ;Get offset above top of region to be mapped
39 004076 066304 0000000  ADD   RT$BAS(R3),R4  ;Bias the offsets
40 004102 066305 0000000  ADD   RT$BAS(R3),R5
41         ;
42         ; Get amt of memory to be mapped
43         ;
44 004106 020563 0000000  CMP     R5,RT$TOP(R3) ;Is top of request above top of run-time?
45 004112 101402          BLOS  2#             ;Br if not
46 004114 016305 0000000  MOV     RT$TOP(R3),R5 ;Don't map beyond top of run-time
47         ;
48         ; Return actual mapped size to user in R0
49         ;
50 004120 010537 0000000  2#:    MOV     R5,URO    ;Return size of mapped region in user's R0
51 004124 160437 0000000  SUB    R4,URO
52         ;
53         ; Finished
54         ;
55 004130 000207          RETURN

```

```

1          .SBTTL  ESPLIT -- Enable user D-space
2          ;-----
3          ; Enable/Disable I and D space split
4          ; When one or more of a job's PARs are mapped away to a shared run-time
5          ; the root memory is not released, but is ordinarily inaccessible. If
6          ; I/D space split is enabled, then the root memory which was mapped
7          ; away by a shared run-time can be accessed as D-space. This is only valid
8          ; on machines which support I and D space (have memory management register
9          ; 3 -- SR3FLG not 0 and have D-space APR's -- IDSFLG not 0).
10         ;
11         ; Enabling D-space is done by setting the LSW11 bit which says the user
12         ; wants to split, then calling SUTOP with the current size, which then
13         ; calls SETMAP and copies the ordinary I-space APRs into the D-space APRs
14         ; and enables user D-space.
15         ;
16         ; The form of the EMT is:
17         ;     .BYTE  4,143
18         ;
19 004132 105737 000000G  ESPLIT: TSTB  IDSFLG      ;Does hardware support I and D space?
20 004136 001411          BEQ  SPLITR      ;If not, br to split error return
21 004140 052761 000000G 000000G  BIS  #$UDSPC,LSW11(R1) ;Set flag to enable D-space mapping
22 004146 013700 000000G  MOV  ODTBAS,RO      ;Point to word beyond normal address limit
23 004152 004737 000000G  CALL SUTOP        ;This will do the real work
24 004156 000137 000000G  JMP  EMTXIT
25         ;
26         ; Error, hardware does not support I and D space
27         ;
28 004162 012700 000000G  SPLITR: MOV  #EC6,RO      ;Signal error code 1
29 004166 000137 000000G  JMP  SETERR
30         ;
31         ;-----
32         ; Disable D-space split, return all mapping to I-space
33         ; This just requires turning off the hardware D-space enable bit,
34         ; the D-space APRs will then be ignored so they don't require cleanup.
35         ;
36         ; The form of the EMT is:
37         ;     .BYTE  5,143
38         ;
39 004172 105737 000000G  DSPLIT: TSTB  IDSFLG      ;Does hardware support I and D space?
40 004176 001771          BEQ  SPLITR      ;Br if not
41 004200 042761 000000G 000000G  BIC  #$UDSPC,LSW11(R1) ;Clear user D-space in use flag
42 004206 042737 000000G 000000G  BIC  #USDSPC,@#SR3MMR ;And disable it in hardware
43 004214 000137 000000G  JMP  EMTXIT

```

Define a PLAS region for fast mapping

```

1          .SBTTL Define a PLAS region for fast mapping
2          ;-----
3          ; Define a PLAS window so it can be quickly mapped using the TRAP
4          ; instruction. The region is not limited to 8Kb. All checking related
5          ; to PAR numbers and mapped length is assumed to have been done
6          ; when creating the window.
7          ;
8          ; EMT argument list:
9          ;   .BYTE 6,143
10         ;   .BYTE W.NID,fmrnum ;PLAS window ID, <0 to MAXSRD-1>
11         ;   .WORD W.NRID      ;R.GID to which window is associated
12         ;
13 004220 113701 0000020 5$PLAS: MOVB EMTBLK+2,R1 ;Get window ID
14 004224 005301          DEC R1 ;Make it 0 indexed
15 004226 020127 0000000  CMP R1,#NUMWCB ;Is window ID in valid range? (1-NUMWCB)
16 004232 103403          BLO 2$ ;Br if OK
17 004234 012700 0000003 1$: MOV #EC3,R0 ;Invalid window ID
18 004240 000421          BR 7$ ;Return with error
19         ;
20         ; Verify that fast map region number is valid
21         ;
22 004242 113700 0000030 2$: MOVB EMTBLK+3,R0 ;Get fast map region number
23 004246 020027 0000000  CMP R0,#MAXSRD ;Is number in valid range?
24 004252 103403          BLO 3$ ;Br if OK
25 004254 012700 0000002 21$: MOV #EC2,R0 ;Invalid fast map region #
26 004260 000411          BR 7$ ;Return with error
27         ;
28         ; Convert window ID into ptr to window control block
29         ;
30 004262 070127 0000000 3$: MUL #WC#$SZ,R1 ;And offset into window control blocks
31 004266 062701 0000000  ADD #WCBBAS,R1 ;Point to specified window control block
32 004272 016105 0000000  MOV WC$SIZ(R1),R5 ;Get # 64-byte blocks to be mapped
33 004276 001004          BNE 4$ ;Br if window is allocated
34 004300 012700 0000001 31$: MOV #EC1,R0 ;Else say window is undefined
35 004304 000137 0000000 7$: JMP SETERR ;Return with error
36         ;
37         ; Now move window control information into fast map cells
38         ;
39 004310 013702 0000040 4$: MOV EMTBLK+4,R2 ;Get ptr to region control block
40 004314 004737 004576'  CALL CHKRCB ;Verify that it is valid
41 004320 103767          BCS 31$ ;Br if invalid
42 004322 032762 0000000 0000000  BIT #RC$LCG,RC$FLG(R2) ;Is this region swappable?
43 004330 001003          BNE 41$ ;Br if not
44 004332 012700 0000004  MOV #EC4,R0 ;Can't fast map swappable regions!
45 004336 000762          BR 7$ ;Go do error
46 004340 005046          41$: CLR -(SP) ;Assume I-space mapping
47 004342 032762 0000000 0000000  BIT #RC$DSP,RC$FLG(R2) ;Should we use D-space instead?
48 004350 001402          BEQ 44$ ;Br if not
49 004352 112716 0000000  MOVB #SR.DSP,(SP) ;If using D-space, init flag byte
50         ;
51         ; Ensure that window won't exceed region bounds and update WCB cells
52         ;
53 004356 016204 0000000 44$: MOV RC$LEN(R2),R4 ;Get size of region
54 004362 166104 0000000  SUB WC$OFF(R1),R4 ;Figure maximum allowed window length
55 004366 020504          CMP R5,R4 ;Would request exceed region?
56 004370 103401          BLO 46$ ;Br if not
57 004372 010405          MOV R4,R5 ;If so, just allow to end of region

```

Define a PLAS region for fast mapping

```

58 004374 010561 000000G      46$:  MOV      R5,WC$LEN(R1)  ;And actual length into window control block
59 004400 010537 000000G      MOV      R5,URO          ;Return actual length to user
60 004404 010504                MOV      R5,R4           ;Copy window length
61 004406 062704 000177      ADD      #177,R4         ;Bound up to full par
62 004412 072427 177771      ASH      #-7,R4          ;Convert #64byte blocks to #8Kb pars
63 004416 110461 000000G      MOVVB   R4,WC$NPR(R1)   ;And set into window control block
64                                ;
65                                ; Loop to update as many PARs as required
66                                ;
67 004422 016204 000000G      MOV      RC$BAS(R2),R4   ;Get base of region
68 004426 066104 000000G      ADD      WC$OFF(R1),R4  ;Add offset to PLAS window
69 004432 116102 000000G      MOVVB   WC$PAR(R1),R2   ;Get PAR index # (2*PAR #)
70                                ; At this point, R0 has the trap #, NOT the trap index
71 004436 110061 000000G      MOVVB   R0,WC$TRP(R1)   ;Set trap # into WCB (for inswap update)
72 004442 020027 000000G      42$:  CMP      R0,#MAXSRD   ;Have we used up all trap #'s?
73 004446 103402                BLO      45$             ;Br if still OK
74 004450 005726                TST      (SP)+           ;Else clean flag word off stack
75 004452 000700                BR       21$             ;And go report error
76 004454 110260 000000G      45$:  MOVVB   R2,SR$PX(R0)  ;Set PAR index into fast map cell
77 004460 111660 000000G      MOVVB   (SP),SR$FLG(R0) ;Init flag byte for this region
78 004464 006300                ASL      R0              ;Convert trap # to word index
79 004466 010160 000000G      MOV      R1,SR$WCB(R0)  ;Set ptr to wcb in fast map cell
80 004472 010460 000000G      MOV      R4,SR$PAR(R0)  ;Set PAR value into fast map cell
81 004476 010503                MOV      R5,R3           ;Get # blocks that still need to be mapped
82 004500 020327 000200      CMP      R3,#200        ;More than we can map with 1 par?
83 004504 101402                BLOS    43$             ;Br if not
84 004506 012703 000200      MOV      #200,R3        ;Map through this full par
85 004512 160305                43$:  SUB      R3,R5         ;Get # blocks left to be mapped
86 004514 060304                ADD      R3,R4           ;Bump PAR value up for next time
87 004516 005303                DEC      R3              ;Convert # blocks to # of last valid block
88 004520 000303                SWAB    R3               ;Move # blocks to high byte
89 004522 052703 000006      BIS      #6,R3          ;Enable read/write access
90 004526 042703 100271      BIC      #100271,R3     ;Clear unused PDR bits, ED is always up
91 004532 010360 000000G      MOV      R3,SR$PDR(R0) ;Set PDR value into fast map cell
92 004536 005705                TST      R5              ;Need to map any more?
93 004540 001410                BEQ     5$               ;Br if not
94 004542 006200                ASR     R0               ;If so, convert back to trap #
95 004544 152760 000000G 000000G  BISB    #SR.MOR,SR$FLG(R0) ;Say there are more regions to map
96 004552 005200                INC     R0               ;Bump up to next trap #
97 004554 062702 000002      ADD     #2,R2           ;Bump par index up to next register
98 004560 000730                BR      42$             ;Loop through as many pars as needed
99                                ;
100                               ; All necessary fast trap cells are set up, enable fast mapping and exit
101                               ;
102 004562 005726                5$:  TST      (SP)+         ;Clean I- D-space flag off stack
103 004564 112737 000001 000000G  MOVVB   #1,DOTRMP       ;Enable fast mapping
104 004572 000137 000000G      JMP     EMTXIT

```

CHKRCB -- Check address of Region Control Block

```

1          .SBTTL  CHKRCB -- Check address of Region Control Block
2          ;-----
3          ;  CHKRCB is called to verify that the address of a region control
4          ;  block is valid.  This routine is a similar to that in TSPLAS.
5          ;
6          ;  Inputs:
7          ;  R2 = Region control block address to be checked
8          ;
9 004576 032702 000001  CHKRCB: BIT    #1,R2      ;Make sure address is even
10 004602 001014          BNE    1$      ;Br if odd
11 004604 020227 000000G  CMP    R2,#RCBBAS  ;Make sure it is within proper region
12 004610 103403          BLO    2$
13 004612 020227 000000G  CMP    R2,#RCBEND
14 004616 103410          BLO    3$
15 004620 020237 000000G  2$:  CMP    R2,SHRRCB  ;See if this is a shared RCB
16 004624 103403          BLO    1$
17 004626 020237 000000G  CMP    R2,SHRRCN
18 004632 101402          BLOS   3$
19          ;
20          ;  Address is invalid
21          ;
22 004634 000261 1$:  SEC
23 004636 000401          BR     9$
24          ;
25          ;  Address is ok
26          ;
27 004640 000241 3$:  CLC
28          ;
29 004642 000207 9$:  RETURN
30

```

```

1          .SBTTL  Spooling control
2          ;-----
3          ; This EMT is used to control the spooling operation.
4          ;
5          ; Form of the EMT argument block:
6          ;   .BYTE   chan,151
7          ;   .WORD   sub-function
8          ;   .WORD   value
9          ;
10         ; Where "chan" is an open channel whose file is to be affected,
11         ; and "sub-function" indicates which function is to be performed.
12         ;
13         004644 013703 000000G SPLEMT: MOV     CHNADR,R3      ;Get address of specified channel
14         004650 032763 000000G 000000G BIT     #CS$OPN,C.CSW(R3);Is the channel open?
15         004656 001004          BNE     1$           ;Br if yes
16         004660 012700 000003  MOV     #EC3,R0      ;Channel not open
17         004664 000137 000000G      JMP     SETERR
18         ;
19         ; Ignore this EMT if the channel is not opened to a spooled device
20         ;
21         004670 032763 000000G 000000G 1$: BIT     #CS$SPL,C.CSW(R3);Is channel opened to a spooled device?
22         004676 001412          BEQ     9$           ;Ignore the EMT if not
23         ;
24         ; Get sub-function code and branch off to processing routine
25         ;
26         004700 013700 000002G      MOV     EMTBLK+2,R0    ;Get EMT sub-function code
27         004704 006300          ASL     R0            ;Convert to word-table index
28         004706 020027 000006      CMP     R0,#MXSFX     ;Is index ok?
29         004712 103402          BLD     2$           ;Br if ok
30         004714 000137 000000G      JMP     BADEMT       ;Invalid sub-function code
31         004720 000170 005020'      2$: JMP     @SPLFNV(R0);Enter processing routine
32         004724 000137 000000G      9$: JMP     EMTXIT
33         ;
34         ; Set Hold/Nohold flag for spool file
35         ;
36         004730 105737 000000G SPSTHL: TSTB   NSPLDV     ;Are there any spooled devices?
37         004734 001405          BEQ     9$           ;Br if not
38         004736 013702 000004G      MOV     EMTBLK+4,R2  ;Get [no]hold flag
39         004742          OCALL   SPLSHF     ;Set hold flag for file
40         004750 000137 000000G      9$: JMP     EMTXIT     ;Finished
41         ;
42         ; Set Hold/Nohold flag for spool file
43         ;
44         004754 105737 000000G SPSTFL: TSTB   NSPLDV     ;Are there any spooled devices?
45         004760 001404          BEQ     9$           ;Br if not
46         004762 013702 000004G      MOV     EMTBLK+4,R2  ;Get [no]flagpage flag
47         004766 000137 000000G      JMP     SPLSFF       ;Set flagpage flag for device
48         004772 000137 000000G      9$: JMP     EMTXIT     ;Finished
49         ;
50         ; Set Hold/Nohold flag for spool file
51         ;
52         004776 105737 000000G SPSTWD: TSTB   NSPLDV     ;Are there any spooled devices?
53         005002 001404          BEQ     9$           ;Br if not
54         005004 013702 000004G      MOV     EMTBLK+4,R2  ;Get wide/narrow flag
55         005010 000137 000000G      JMP     SPLSWF       ;Set wide/narrow flag for device
56         005014 000137 000000G      9$: JMP     EMTXIT     ;Finished
57         ;
    
```

```
58          ; Vector of routine addresses for sub-function codes
59          ;
60 005020 004730' SPLFN: .WORD  SPSTHL      ; 0 -- Set [no]hold flag for file
61 005022 004754'      .WORD  SPSTFL      ; 1 -- Turn on flag pages for device
62 005024 004776'      .WORD  SPSTWD      ; 2 -- Set flag page wide/narrow for device
63          000006      MXSFX =      .-SPLFN  ; # functions
```

```

1          .SBTTL  CL line control EMT's
2          ;-----
3          ;
4          ; Assorted CL EMT's -- some of which duplicate CL spfun services, but
5          ; are also implemented as EMT's to avoid the requirement to have a
6          ; channel open to the CL unit.
7          ;
8          ; The form of the argument block is:
9          ;
10         ; .BYTE    n,155
11         ; .WORD    CL-unit-number          ; 0 to (CLTOTL-1)
12         ; .WORD    time-sharing-line-number ; Only used for CLASN
13         ;
14 005026  CLEMT:
15         ;
16         ; Require TERMINAL privilege to manipulate CL units
17         ;
18 005026  032737  000000G 000000G      BIT    #P2$TRM,PRIVC2 ; Is this user privileged?
19 005034  001003                BNE    12$          ; Br if yes
20 005036  012700  000001      MOV    #EC1,R0      ; Error 1 if user not privileged
21 005042  000436                BR     30$
22         ;
23         ; Check to see if the specified CL unit number is valid
24         ;
25 005044  013702  000002G      12$:   MOV    EMTBLK+2,R2    ; Get specified CL unit number
26 005050  020227  000000G      CMP    R2,#CLTOTL    ; Is this in the proper range?
27 005054  103403                BLD    1$           ; Br if ok
28 005056  012700  000002      MOV    #EC2,R0      ; Error 2
29 005062  000426                BR     30$
30 005064  006302      1$:   ASL    R2           ; Convert CL unit # to table index
31         ;
32         ; Now jump off to the individual processing routines
33         ;
34 005066  113700  000000G      MOVB   EMTBLK,R0    ; Get subfunction code
35 005072  020027  000003      CMP    R0,#CLEMMX   ; Is it valid?
36 005076  103402                BLD    2$           ; Br if OK
37 005100  005000                CLR    R0           ; Else return ECO
38 005102  000416                BR     30$
39         ;
40 005104  006300      2$:   ASL    R0           ; Convert subfunction code to index
41 005106  001416                BEQ    3$           ; Br if we don't need to check for hdw or priv
42 005110  032737  000000G 000000G      BIT    #P0$BYP,PRIVC0 ; Does issuer have BYPASS privilege?
43 005116  001003                BNE    21$         ; Br if yes
44 005120  012700  000010      MOV    #EC8,R0      ; Oh, too bad. Must have BYPASS
45 005124  000405                BR     30$
46 005126  016201  000000G      21$:   MOV    CL$LIX(R2),R1 ; Get index of T-S line CL is connected to
47 005132  001004                BNE    3$           ; Br if it is connected to a line
48 005134  012700  000007      MOV    #EC7,R0      ; Oops, not connected to hardware!
49 005140  000137  000000G      30$:   JMP    SETERR
50         ;
51 005144  000170  005150'      3$:   JMP    @CLCODE(R0) ; Enter the processing routine
52         ;
53 005150  005154'      CLCODE: .WORD    CLASN    ; 0 Assign a CL unit to a line
54 005152  005674'          .WORD    CLCLR    ; 1 Clear XOFF status (=== SPFUN 201)
55 005154  005710'          .WORD    CLRES    ; 2 Reset CL unit (=== SPFUN 265)
56         CLEMMX = <.-CLCODE>/2

```

CLASN -- Assign a CL unit to a line

```

1          .SBTTL          CLASN -- Assign a CL unit to a line
2          ;-----;
3          ; Assign a CL unit to a line.
4          ; The form of the EMT is:
5          ;
6          ;       .BYTE    0,155
7          ;       .WORD    CL_unit_number
8          ;       .WORD    line_number
9          ;
10         CLASN:
11         ;
12         ; Check to see if the specified line number is ok
13         ;
14         005156 013704 000004G      MOV      EMTBLK+4,R4      ;Get specified line number
15         005162 001451              BEQ      5$              ;LINE=0 ==> Free this unit
16         005164 006304              ASL      R4              ;Convert line # to line table index
17         005166 020427 000000G      CMP      R4,#LSTHL      ;Must be a valid hardware line
18         005172 101042              BHI      2$              ;Br if invalid
19         005174 032764 000000G 000000G BIT      ##HARD,LSW3(R4) ;Is this line connected to hardware?
20         005202 001436              BEQ      2$              ;Br if not
21         005204 020264 000000G      CMP      R2,LCLUNT(R4) ;Is this CL unit already assigned to this line
22         005210 001535              BEQ      22$             ;Br if yes -- nothing else needs to be done
23         005212 032764 000000G 000000G BIT      ##DEAD,LSW3(R4) ;Is this line installed?
24         005220 001027              BNE      2$              ;Br if not
25         005222 005764 000000G      TST      LCLUNT(R4)    ;Is this line in use by another CL unit?
26         005226 002404              BLT      4$              ;Br if not
27         005230 012700 000004      MOV      #EC4,R0       ;Error 4 if line already being used by CL
28         005234 000137 000000G      30$:    JMP      SETERR
29         005240 020427 000000G      4$:    CMP      R4,#LSTPL    ;Connecting to a primary time-sharing line?
30         005244 101007              BHI      3$              ;Br if not
31         005246 032764 000000G 000000G BIT      ##DILUP,LSW(R4) ;Is this line in use by time-sharing user?
32         005254 001414              BEQ      5$              ;Br if not
33         005256 012700 000005      MOV      #EC5,R0       ;Error 5 if line is active as a time-sharing
34         005262 000764              BR       30$
35         005264 020427 000000G      3$:    CMP      R4,#FSTIOL ;Are we assigning to a reserved CL line?
36         005270 103403              BLO      2$              ;Br if not
37         005272 020427 000000G      CMP      R4,#LSTIOL    ;Is this a valid CL line?
38         005276 101403              BLOS     5$              ;Br if yes
39         005300 012700 000003      2$:    MOV      #EC3,R0     ;Error 3 if invalid line number
40         005304 000753              BR       30$
41         ;
42         ; The line number is ok.
43         ; Deassign the CL unit from its current line association.
44         ;
45         005306 016203 000000G      5$:    MOV      CL$LIX(R2),R3 ;Get line # currently assoc with this CL unit
46         005312 001471              BEQ      6$              ;Br if line is not currently assigned
47         005314 005762 000000G      TST      CL$XLN(R2)    ;Is CL unit in use for cross connect?
48         005320 001005              BNE      23$            ;Br if yes
49         005322 016200 000000G      MOV      CL$RQH(R2),R0 ;Anything in read queue head
50         005326 056200 000000G      BIS      CL$WQH(R2),R0 ;or write queue head for this CL unit?
51         005332 001403              BEQ      11$            ;Br if not
52         005334 012700 000006      23$:    MOV      #EC6,R0     ;Error 6 if CL unit is currently busy
53         005340 000735              BR       30$
54         005342 004737 006026'      11$:    CALL     CLWAIT        ;Wait for output characters to be sent
55         005346 010205              MOV      R2,R5         ;Get CL unit index to R5
56         005350              DCALL   CLREST        ;Reset CL unit status
57         005356 042762 000000G 000000G BIC      #CD#DTR,CL$(OPT(R2) ;Request DTR down

```

CLASN -- Assign a CL unit to a line

```

58 005364          DCALL  SETDTR          ; Call CL routine to drop DTR
59 005372 012763 177777 000000G      MOV    #-1,LCLUNT(R3) ; Say this line not assoc with a CL unit
60 005400 016300 000000G      MOV    LCXTBL(R3),R0  ; Get pointer to translation table for line
61 005404 001401          BEQ    24$          ; Br if no translation table
62 005406 005010          CLR    (R0)          ; Say no translation in effect
63 005410 020327 000000G      24$:  CMP    R3,#LSTPL      ; Is this a time-sharing line
64 005414 101022          BHI    7$          ; Br if not
65 005416 012763 000000G 000000G    MOV    #NEDCHR,LOUTIR(R3); Set T/S terminal output interrupt rtn
66 005424 012763 000000G 000000G    MOV    #TTINCP,LINIR(R3); Set T/S terminal input interrupt rtn
67 005432 032763 000000G 000000G    BIT    ##AUTO,ILSW2(R3); Is this line suppose to autobaud?
68 005440 001416          BEQ    6$          ; Br if not
69 005442 010301          MOV    R3,R1          ; Get number of line being released
70 005444 012700 000000G      MOV    #S9600,R0     ; Get 9600 baud speed code
71 005450 004737 000000G      CALL   SETSPD        ; Set line speed
72 005454 113701 000000G      MOVB   CORUSR,R1     ; Get back our line index number
73 005460 000406          BR     6$          ;
74 005462 012763 000000G 000000G    7$:  MOV    #LINRTS,LOUTIR(R3); Set dummy routine to do RTS
75 005470 012763 000000G 000000G    MOV    #LINRTS,LINIR(R3);
76          ;
77          ; Associate the specified line with the CL unit
78          ;
79 005476 010462 000000G      6$:  MOV    R4,CL$LIX(R2) ; Set # of line associated with CL unit
80 005502 001002          BNE    21$          ; Br if not freeing this CL unit
81 005504 000137 000000G      22$:  JMP    EMTXIT        ; LINE=0 ==> Free this CL unit
82 005510 010264 000000G      21$:  MOV    R2,LCLUNT(R4) ; Set CL unit in line table
83 005514 012764 000000G 000000G    MOV    #CLOTIR,LOUTIR(R4); Set output interrupt service routine
84 005522 012764 000000G 000000G    MOV    #CLINCP,LINIR(R4); Set terminal input service routine
85 005530 052764 000000G 000000G    BIS    ##SXON,LSW10(R4); Send XON when we start
86          ;
87          ; Set some option flags for this CL unit
88          ;
89 005536 016403 000000G      MOV    LCXTBL(R4),R3 ; Get pointer to translation table for line
90 005542 001401          BEQ    25$          ; Br if no translation table
91 005544 005013          CLR    (R3)          ; Say no translation in effect
92 005546 016403 000000G      25$:  MOV    ILSW2(R4),R3  ; Get option flags for the line
93 005552 012700 000000G      MOV    #CO$DEF,R0   ; Get default CL option flags
94 005556 032703 000000G      BIT    ##TAB,R3     ; Does this device support tabs?
95 005562 001402          BEQ    8$          ; Br if not
96 005564 052700 000000G      BIS    #CO$TAB,R0   ; Set CL tab flag
97 005570 032703 000000G      8$:  BIT    ##FORM,R3    ; Does this device suport form-feeds?
98 005574 001402          BEQ    9$          ; Br if not
99 005576 052700 000000G      BIS    #CO$FF,R0   ; Set CL form feed flag
100 005602 032703 000000G      9$:  BIT    ##8BIT,R3   ; Does this device want 8-bit support?
101 005606 001402          BEQ    10$         ; Br if not
102 005610 052700 000000G      BIS    #CO$8BT,R0  ; Enable 8 bit support
103 005614 010062 000000G      10$:  MOV    R0,CL$OPT(R2) ; Initialize CL options for this device
104          ;
105          ; Initialize status for this CL unit
106          ;
107 005620 005062 000000G      CLR    CL$STA(R2)   ; Init status flags
108 005624 005062 000000G      CLR    CL$COL(R2)   ; Current column number
109 005630 012762 000102 000000G    MOV    #66,CL$LEN(R2); # lines per page
110 005636 005062 000000G      CLR    CL$LIN(R2)   ; Current line number
111 005642 005062 000000G      CLR    CL$SKP(R2)   ; Lines to skip at bottom of page
112 005646 005062 000000G      CLR    CL$WID(R2)   ; Line width
113 005652 005062 000000G      CLR    CL$EPN(R2)   ; No end-of-file form-feeds
114 005656 016200 000000G      MOV    CL$EPS(R2),R0 ; Get pointer to ENDSTRING buffer

```

```
115 005662 105010          CLRB  (R0)          ;No ENDSTRING
116 005664 005062 000000G   CLR   CL$EPP(R2)
117                          ;
118                          ; Finished
119                          ;
120 005670 000137 000000G   20$:  JMP   EMTXIT      ;Finished assigning the CL unit
```

CLCLR -- Clear XOFF sent and send XON

```

1          .SBTTL          CLCLR -- Clear XOFF sent and send XON
2          ;-----
3          ; This routine is the EMT equivalent of CL SPFUN 201
4          ;
5          ; Emt argument block:
6          ;   .BYTE 1,155
7          ;   .WORD CL-unit-number
8          ;
9          ; Inputs:
10         ;   R1   TS line in use as CL unit
11         ;   R2   CL unit index
12         ;
13 005674  CLCLR:
14 005674  010205      MOV     R2,R5          ;Need to get CL unit index into R5
15 005676      OCALL   CLCLER          ;Call TSCLO routine to clear CL unit
16 005704  000137  0000000  JMP     EMTXIT
17
18         .SBTTL          CLRES -- Reset CL line
19         ;-----
20         ; This routine is the EMT equivalent of CL SPFUN 265
21         ;
22         ; EMT argument block:
23         ;   .BYTE 2,155
24         ;   .WORD CL-unit-number
25         ;
26         ; Inputs:
27         ;   R1   TS line in use as CL unit
28         ;   R2   CL unit index
29 005710  CLRES:
30 005710  010205      MOV     R2,R5          ;Need to get CL unit index into R5
31 005712      OCALL   CLREST          ;Call TSCLO routine to reset CL unit
32 005720  000137  0000000  JMP     EMTXIT

```

CLCLOS -- Close channel opened to CL unit

```

1          .SBTTL  CLCLOS -- Close channel opened to CL unit
2          ;-----
3          ; This routine is called to determine if the channel being closed is
4          ; assigned to a CL unit.  If it is, the job is suspended until all output
5          ; to the CL unit has been completed.
6          ;
7 005724 010246 CLCLOS: MOV      R2, -(SP)
8 005726 010546      MOV      R5, -(SP)
9          ;
10         ; Determine if this channel is opened to a CL unit
11         ;
12 005730 013702 000000G      MOV      CHNADR, R2      ;Get address of current channel block
13 005734 016200 000000G      MOV      C.CSW(R2), R0      ;Get channel status word
14 005740 032700 000000G      BIT      #CS$SPL, R0      ;Is this a spooled device?
15 005744 001025      BNE      9$      ;Br if yes -- Don't wait for output to finish
16 005746 116202 000000G      MOVB     C.DEVQ(R2), R2      ;Get unit number
17 005752 042702 177770      BIC      #^C<7>, R2      ;Clear all but unit number
18 005756 042700 000000C      BIC      #^C<CS$NMX>, R0      ;Mask out all but device table index
19 005762 020037 000000G      CMP      R0, CLDEVX      ;Is this a CL device?
20 005766 001405      BEQ      1$      ;Br if yes
21 005770 020037 000000G      CMP      R0, C1DEVX      ;Is this a C1 device?
22 005774 001011      BNE      9$      ;Br if not
23 005776 062702 000010      ADD      #8, R2      ;Bias unit number by 8 for C1
24         ;
25         ; This is a CL device being closed.
26         ; Wait for all output to be completed.
27         ;
28 006002 006302      1$:      ASL      R2      ;Convert to word table index
29 006004 004737 006026'      CALL     CLWAIT      ;Wait for all output to finish
30 006010 010205      MOV      R2, R5      ;Get CL unit index to R5
31 006012      OCALL    CLREST      ;Reset CL unit status
32         ;
33         ; Finished
34         ;
35 006020 012605      9$:      MOV      (SP)+, R5
36 006022 012602      MOV      (SP)+, R2
37 006024 000207      RETURN

```

```

1          .SBTTL CLWAIT -- Wait for CL output to finish
2          ;-----
3          ; This routine is called to check to see if all characters which have
4          ; been queued for transmission on a CL line have actually been transmitted.
5          ; If there are still pending characters the job is suspended for a while
6          ; to give the characters time to be sent.
7          ;
8          ; Inputs:
9          ;   R2 = CL unit index
10         ;
11 006026 010346 CLWAIT: MOV     R3, -(SP)
12         ;
13         ; Set maximum number of times we will wait for output to finish
14         ;
15 006030 012703 000024         MOV     #20, R3           ;Set max iteration count
16         ;
17         ; See if there are any output characters pending for this CL unit
18         ;
19 006034 026262 0000000 0000000 1$:  CMP     CL$ORS(R2), CL$ORA(R2) ;Are there any pending output chars?
20 006042 001013         BNE     2$           ;Br if yes
21 006044 016200 0000000         MOV     CL$LIX(R2), R0       ;Get index # of line CL is connected to
22 006050 001421         BEQ     9$           ;Br if CL unit not connected to line
23 006052 032762 0000000 0000000     BIT     #CM$EFP, CL$STA(R2);Are we doing end-of-file processing?
24 006060 001004         BNE     2$           ;Br if yes
25 006062 032760 0000000 0000000     BIT     #$XCHAR, LSW3(R0); Is output transmission to that line active?
26 006070 001411         BEQ     9$           ;Br if not
27         ;
28         ; There are some pending output characters.
29         ; Suspend job for a little while and then check again.
30         ;
31 006072 012746 0000000     2$:  MOV     #CLWTIM, -(SP)       ;Push pointer to time value cells
32 006076 012746 012000         MOV     #<24*400>, -(SP) ;Push EMT argument code
33 006102 010600         MOV     SP, R0           ;Point to EMT arg block we built on stack
34 006104 104375         EMT     375           ;Do .TWAIT
35 006106 062706 000004         ADD     #4, SP           ;Pop EMT argument block from stack
36         ;
37         ; Go back and check for output pending
38         ;
39 006112 077330         SOB     R3, 1$         ;Go back and check for output pending
40         ;
41         ; There is no output pending or we have wait as long as we are willing
42         ;
43 006114 012603     9$:  MOV     (SP)+, R3
44 006116 000207         RETURN

```

```

1          .SBTTL Performance monitor emt's
2          ;-----
3          ; The following EMT's are used to control the TSX-Plus performance
4          ; monitor system.
5          ;
6          ; The EMT sub-function stored in byte 0 of the argument block controls
7          ; the action of the emt. The valid sub-functions are:
8          ;
9          ; 0 = Initialize the performance monitor system.
10         ; 1 = Start doing performance monitoring.
11         ; 2 = Suspend performance monitoring.
12         ; 3 = Stop performance monitor and return result values.
13         ;
14 006120 113705 000000G PMEMT:  MOVB  EMTBLK,R5      ;GET SUB-FUNCTION CODE FOR EMT
15 006124 120527 000003      CMPB  R5,#3      ;VALID SUB-FUNCTION CODE?
16 006130 101402      BLOS  1$      ;BR IF OK
17 006132 000137 000000G      JMP   BADEMT    ;INVALID EMT CODE
18 006136 006305      1$:  ASL   R5      ;CONVERT TO WORD-TABLE INDEX
19 006140 000175 006144'      JMP   @PMRVEC(R5) ;ENTER PROCESSING ROUTINE
20
21 006144 006154' PMRVEC: .WORD  PMINIT    ;0 -- INITIALIZE
22 006146 006366'      .WORD  PMSTRT    ;1 -- START MONITORING
23 006150 006402'      .WORD  PMSTOP    ;2 -- SUSPEND MONITORING
24 006152 006416'      .WORD  PMEND     ;3 -- END ANALYSIS

```

```

1          ; -----
2          ; Initialize performance monitoring.
3          ;
4          ; Arguments:
5          ; 1. Base address of region being monitored.
6          ; 2. Top address of region being monitored.
7          ; 3. Number of bytes per cell in histogram.
8          ; 4. PF# control flags.
9          ;
10         ; Errors:
11         ; 0 = Performance monitor already in use.
12         ; 1 = Performance monitor not generated in.
13         ;
14 006154 005737 000000G PMINIT: TST      PMCELS      ; WAS PERFORMANCE MONITOR GENNED IN?
15 006160 001004          BNE      5$          ; BR IF YES
16 006162 012700 000001  MOV     #EC1,R0      ; RETURN ERROR CODE 1
17 006166 000137 000000G  JMP     SETERR
18 006172 113702 000000G  5$:    MOVVB  PMUSER,R2    ; IS ANYONE DOING PERFORMANCE MONITORING NOW?
19 006176 001411          BEQ     1$          ; BR IF NOT
20 006200 120237 000000G  CMPB  R2,CORUSR     ; ARE WE THE ONE?
21 006204 001406          BEQ     1$          ; BR IF YES
22 006206 005000          CLR     R0          ; PM IN USE BY SOMEONE ELSE -- RETURN ERROR 0
23 006210 006202          ASR     R2          ; RETURN # OF JOB THAT OWNS PM IN USER'S R0
24 006212 010237 000000G  MOV     R2,UR0
25 006216 000137 000000G  JMP     SETERR
26 006222 113737 000000G 000000G 1$:    MOVVB  CORUSR,PMUSER ; SAY WE ARE USING PM FACILITY
27 006230 005037 000000G  CLR     PMRUN       ; DON'T START MONITORING YET
28         ;
29         ; Save information about region being monitored.
30         ;
31 006234 013705 000002G  MOV     EMTBLK+2,R5  ; GET BASE ADDRESS OF REGION
32 006240 010537 000000G  MOV     R5,PMBASE
33 006244 013703 000004G  MOV     EMTBLK+4,R3  ; GET TOP ADDRESS OF REGION
34 006250 010337 000000G  MOV     R3,PMTOP
35 006254 013737 000010G 000000G  MOV     EMTBLK+10,PMFLGS ; GET CONTROL FLAGS
36 006262 160503          SUB     R5,R3        ; GET # BYTES IN REGION BEING MONITORED
37 006264 000241          CLC
38 006266 006003          ROR     R3          ; CONVERT TO # WORDS
39 006270 005002          CLR     R2          ; SET FOR DIVIDE
40 006272 071237 000000G  DIV     PMCELS,R2    ; DIVIDE BY # CELLS IN PM DATA AREA
41 006276 005703          TST     R3          ; IS REMAINDER ZERO?
42 006300 001401          BEQ     2$          ; BR IF YES
43 006302 005202          INC     R2          ; ROUND UP QUOTIENT IF NOT
44 006304 006302          2$:    ASL     R2          ; GET # BYTES PER PM CELL
45 006306 020237 000006G  CMP     R2,EMTBLK+6  ; COMPARE WITH REQUESTED # BYTES PER CELL
46 006312 103002          BHS    4$          ; USE LARGER VALUE
47 006314 013702 000006G  MOV     EMTBLK+6,R2
48 006320 010237 000000G  4$:    MOV     R2,PMNBPC ; NUMBER OF BYTES PER CELL
49         ;
50         ; Zero performance monitoring count cells.
51         ; (Enter system state so that we are running on interrupt stack and can
52         ; access PM data area through PAR6. )
53         ;
54 006324 012700 006362'  MOV     #6$,R0      ; GO TO 6$ ON EXIT FROM SYSTEM STATE
55 006330 004737 000000G  CALL    ENSYS       ; ENTER SYSTEM STATE
56 006334 000000G  .WORD  FP$MOV       ; Set fork processing priority
57 006336 013700 000000G  MOV     PMCELS,R0   ; GET # CELLS
    
```

```
58 006342 012705 000000G          MOV    #VPAR6,R5          ; ACCESS AREA THROUGH PAR6 REGION
59 006346 013737 000000G 000000G    MOV    PMPAR,@#KPAR6      ; MAP TO PERFORMANCE MONITOR DATA AREA
60 006354 005025          3$:   CLR    (R5)+            ; ZERO DATA VECTOR
61 006356 077002          SOB    R0,3$              ;
62 006360 000207          RETURN                    ; EXIT SYSTEM STATE -- GO TO 6$
63                               ;
64                               ; Finished
65                               ;
66 006362 000137 000000G    6$:   JMP    EMTXIT          ; EXIT FROM EMT
```

```

1          ; -----
2          ; Start monitoring execution.
3          ;
4 006366 004737 006616' PMSTRT: CALL    PMCHKU    ;MAKE SURE WE ARE PM USER
5 006372 005237 000000G      INC      PMRUN      ;START MONITORING
6 006376 000137 000000G      JMP      EMTXIT
7          ; -----
8          ;
9          ; Suspend performance monitoring.
10         ;
11 006402 004737 006616' PMSTOP: CALL    PMCHKU    ;MAKE SURE WE ARE PM USER
12 006406 005037 000000G      CLR      PMRUN      ;SUSPEND PM MONITORING
13 006412 000137 000000G      JMP      EMTXIT
14         ; -----
15         ;
16         ; Return results of performance monitoring.
17         ;
18         ; Arguments:
19         ; 1. Address of vector to receive parameter values.
20         ; 2. Address of area to receive count vector.
21         ; 3. Size of area to receive count vector (# bytes).
22         ;
23         ; Values returned in parameter vector:
24         ; 1. Base address of monitored region.
25         ; 2. Top address of monitored region.
26         ; 3. Number of bytes per count cell.
27         ; 4. PF$ control and status flags.
28         ;
29         ; Errors:
30         ; 0 = This job is not doing a performance monitor.
31         ; 1 = Area for count vector is too small.
32         ;
33 006416 004737 006616' PMEND:  CALL    PMCHKU    ;MAKE SURE WE ARE PM USER
34 006422 005037 000000G      CLR      PMRUN      ;STOP MONITORING
35 006426 005037 000000G      CLR      PMUSER     ;SAY PERFORMANCE MONITOR IS FREE
36         ;
37         ; Return parameter values
38         ;
39 006432 013701 000002G      MOV      EMTBLK+2,R1    ;GET ADDRESS OF USER'S RECEIVING AREA
40 006436 010100              MOV      R1,RO        ;VALIDATE THE ADDRESS
41 006440 004737 000000G      CALL    VALADW
42 006444 013746 000000G      MOV      PMBASE,-(SP) ;RETURN BASE ADDRESS
43 006450 106621              MTPD     (R1)+
44 006452 013746 000000G      MOV      PMTOP,-(SP)  ;RETURN TOP ADDRESS
45 006456 106621              MTPD     (R1)+
46 006460 013746 000000G      MOV      PMNBPC,-(SP) ;NUMBER OF BYTES PER CELL
47 006464 106621              MTPD     (R1)+
48 006466 013746 000000G      MOV      PMFLGS,-(SP) ;STATUS FLAGS
49 006472 106621              MTPD     (R1)+
50         ;
51         ; Return count values.
52         ;
53         ; Enter system state so that we are running on the interrupt stack and
54         ; can map to PM data area through PAR6.
55         ;
56 006474 012700 006576'      MOV      #3$,RO        ;GO TO 3$ ON RETURN FROM SYSTEM STATE
57 006500 004737 000000G      CALL    ENSYS        ;ENTER SYSTEM STATE
    
```

```

58 006504 000000G .WORD FP$MOV ;Fork processing priority
59 006506 013702 000004G MOV EMTBLK+4,R2 ;GET ADDRESS OF USER'S BUFFER
60 006512 010200 MOV R2,R0 ;VALIDATE THE ADDRESS
61 006514 004737 000000G CALL VALADW
62 006520 013703 000006G MOV EMTBLK+6,R3 ;GET # BYTES IN USER'S AREA
63 006524 006203 ASR R3 ;CONVERT TO # WORDS
64 006526 013704 000000G MOV PMBASE,R4 ;GET ADDRESS OF BASE OF MONITORED REGION
65 006532 012705 000000G MOV #VPAR6,R5 ;ACCESS PM DATA AREA THROUGH PAR6 REGION
66 006536 013737 000000G 000000G MOV PMPAR,@#KPAR6 ;SET PAR6 TO MAP TO PM DATA AREA
67 006544 005037 006614' CLR PMOVFR ;SAY USER BUFFER HAS NOT OVERFLOWED
68 006550 012546 1$: MOV (R5)+,-(SP) ;GET COUNT VALUE
69 006552 106622 MTPD (R2)+ ;MOVE TO USER'S AREA
70 006554 063704 000000G ADD PMNBPC,R4 ;ADVANCE ADDRESS COUNTER
71 006560 020437 000000G CMP R4,PMTOP ;RETURNED ALL VALUES?
72 006564 103003 BHIS 2$ ;BR IF YES
73 006566 077310 SOB R3,1$ ;CONTINUE MOVING
74 006570 005237 006614' INC PMOVFR ;SIGNAL OVERFLOW OF USER'S AREA
75 006574 000207 2$: RETURN ;EXIT SYSTEM STATE -- GO TO 3$
76 ;
77 ; Finished
78 ;
79 006576 013700 006614' 3$: MOV PMOVFR,R0 ;GET USER OVERFLOW ERROR FLAG
80 006602 001402 BEQ 4$ ;BRANCH IF NO OVERFLOW
81 006604 000137 000000G JMP SETERR ;ELSE REPORT ERROR TO USER
82 006610 000137 000000G 4$: JMP EMTXIT ;FINISHED
83 006614 000000 PMOVFR: .WORD 0 ;USER BUFFER OVERFLOW ERROR FLAG
84 ;
85 ;-----
86 ; Subroutine to check if the current user is doing a performance monitor.
87 ; If not an error return with code 0 is taken.
88 ;
89 006616 123737 000000G 000000G PMCHKU: CMPB CORUSR,PMUSER ;ARE WE PM USER?
90 006624 001410 BEQ 1$ ;BR IF YES
91 006626 005000 CLR R0 ;RETURN ERROR CODE 0
92 006630 113702 000000G MOVB PMUSER,R2 ;RETURN # OF USER WHO OWNS PM IN R0
93 006634 006202 ASR R2
94 006636 010237 000000G MOV R2,URO
95 006642 000137 000000G JMP SETERR
96 006646 000207 1$: RETURN
    
```

```

1          .SBTTL  CKACJB -- See if access to another job is allowed
2          ;-----
3          ; Determine if the current job is privileged to access another job.
4          ;
5          ; Inputs:
6          ;   R2 = Job index number of job we wish to access.
7          ;
8          ; Outputs:
9          ;   C-flag cleared ==> Access ok
10         ;   C-flag set ==> Access disallowed
11         ;
12 006650 010146  CKACJB: MOV      R1,-(SP)
13         ;
14         ; Always allow access to our own job
15         ;
16 006652 120237 000000G  CMPB    R2,CORUSR      ;Affecting our own job?
17 006656 001437      BEQ     7$              ;Br if yes
18         ;
19         ; If we have WORLD privilege we can access any job
20         ;
21 006660 032737 000000G 000000G  BIT    #P2$WRL,PRIVC2  ;Do we have WORLD privilege?
22 006666 001033      BNE    7$              ;Br if yes
23         ;
24         ; Always allow access to our virtual lines and children jobs.
25         ;
26 006670 113701 000000G      MOVB   CORUSR,R1      ;Get our job index number
27 006674 126162 000000G 000000G  CMPB   LNPRIM(R1),LNPRIM(R2) ;Do we have the same primary line?
28 006702 001425      BEQ     7$              ;Br if yes
29 006704 026201 000000G      CMP    LPARNT(R2),R1   ;Are we parent of this job?
30 006710 001422      BEQ     7$              ;Br if yes
31         ;
32         ; See if project numbers of jobs match
33         ;
34 006712 026162 000000G 000000G  CMP    LPROJ(R1),LPROJ(R2) ;Do project numbers match?
35 006720 001014      BNE    6$              ;Br if not -- We cannot change job
36 006722 032737 000000G 000000G  BIT    #P2$GRP,PRIVC2  ;Do we have GROUP privilege?
37 006730 001012      BNE    7$              ;Br if yes
38         ;
39         ; Project numbers match, check programmer numbers.
40         ;
41 006732 026162 000000G 000000G  CMP    LPROG(R1),LPROG(R2) ;Do programmer numbers match?
42 006740 001004      BNE    6$              ;Br if not
43 006742 032737 000000G 000000G  BIT    #P2$SAM,PRIVC2  ;Do we have SAME privilege?
44 006750 001002      BNE    7$              ;Br if yes
45         ;
46         ; We cannot access the job
47         ;
48 006752 000261 6$:      SEC                      ;Signal failure on return
49 006754 000401      BR     9$
50         ;
51         ; We can access the job
52         ;
53 006756 000241 7$:      CLC                      ;Signal success on return
54         ;
55         ; Finished
56         ;
57 006760 012601 9$:      MOV    (SP)+,R1

```

58 006762 000207
59 000001

RETURN
.END

Errors detected: 0

*** Assembler statistics

Work file reads: 0
Work file writes: 0
Size of work file: 9639 Words (38 Pages)
Size of core pool: 18176 Words (71 Pages)
Operating system: RT-11

Elapsed time: 00:00:43.09
,LP:TSEM4=DK:TSEM4/C/N:SYM

\$BBIT	1-78	28-100						
\$AUTO	1-77	12-7	28-67					
\$CTRL0	1-69	13-42						
\$CTRLS	1-69	13-41						
\$DEAD	1-75	28-23						
\$DEBUG	1-64	3-210						
\$DETCH	1-67	11-9	16-19					
\$DILUP	1-67	10-6	12-5	13-25	17-34	17-70	28-31	
\$DISCN	1-71	13-44						
\$FORM	1-62	3-146	28-97					
\$HARD	1-75	28-19						
\$INKMN	1-56	2-7	3-3					
\$IOMAP	1-55	1-63	3-183					
\$LOFCF	1-53	16-21						
\$NDIN	1-53	16-23						
\$NOVLN	1-53	16-17						
\$RBRK	1-54	12-13						
\$RDSAV	1-57	3-23	3-177					
\$RNIOF	1-63	3-181						
\$RNMLK	1-63	3-191	3-193					
\$SCOPE	1-61	3-140						
\$SETRN	1-63	3-159						
\$SUCF	1-53	16-21						
\$SUSPN	1-67	10-13	10-18	13-43				
\$SXON	1-78	28-85						
\$TAB	1-61	1-78	3-143	28-94				
\$UDSPC	1-84	23-21	23-41					
\$VBELL	1-52	16-129	16-161					
\$VIRJB	1-61	3-131						
\$VNOTT	1-52	16-132						
\$XCHAR	1-81	31-25						
... V1	3-66	3-66	3-74	3-74	3-221	3-221	6-30	
... V2	3-66	3-66	3-66#	3-66#	3-74	3-74#	3-221	3-221#
ABORT	1-64	3-224						
BADEMT	1-56	2-9	18-19	26-30	32-17			
C. CSW	1-74	26-14	26-21	30-13				
C. DEVQ	1-80	30-16						
C1DEVX	1-80	30-21						
CHAIN	1-60	3-83	3-87	3-88	3-107			
CHKRCB	24-40	25-9#						
CHNADR	1-74	26-13	30-12					
CHNSIZ	1-59	3-51	3-53	3-55				
CINDAT	1-60	3-105*	3-106*	3-109	5-14			
CINFLG	1-60	3-84	3-86*	3-220*				
CINMOV	3-91	3-112	5-8#					
CKACJB	13-5	17-88	35-12#					
CL\$COL	1-79	28-108*						
CL\$EPN	1-80	28-113*						
CL\$EPP	1-80	28-116*						
CL\$EPS	1-80	28-114						
CL\$LEN	1-79	28-109*						
CL\$LIN	1-79	28-110*						
CL\$LIX	1-76	27-46	28-45	28-79*	31-21			
CL\$OPT	1-79	11-38*	28-57*	28-103*				
CL\$ORA	1-81	31-19						
CL\$ORS	1-81	31-19						

CL\$RQH	1-76	28-49							
CL\$SKP	1-79	28-111*							
CL\$STA	1-68	1-79	11-28*	11-29*	28-107*	31-23			
CL\$WID	1-79	28-112*							
CL\$WQH	1-76	28-50							
CL\$XLN	1-68	11-27*	28-47						
CLASN	27-53	28-10#							
CLCLER	1-58	29-15							
CLCLOS	1-44	30-7#							
CLCLR	27-54	29-13#							
CLCODE	27-51	27-53#	27-56						
CLDEVX	1-80	30-19							
CLEMMX	27-35	27-56#							
CLEMT	1-44	27-14#							
CLINCP	1-77	28-84							
CLOTIR	1-77	28-83							
CLRES	27-55	29-29#							
CLREST	1-57	28-56	29-31	30-31					
CLTOTL	1-75	27-26							
CLWAIT	28-54	30-29	31-11#						
CLWTIM	1-54	31-31							
CLXBRK	1-69	13-35							
CLXCON	2-34	11-5#							
CLXICP	1-68	11-34							
CM\$BRK	1-68	11-28							
CM\$EFP	1-81	31-23							
CM\$ON	1-68	11-29							
CO\$8BT	1-78	28-102							
CO\$DEF	1-78	28-93							
CO\$DTR	1-54	11-38	28-57						
CO\$FF	1-78	28-99							
CO\$TAB	1-78	28-96							
CORUSR	1-72	17-55	28-72	33-20	33-26	34-89	35-16	35-26	
CPLEMT	1-60	3-123*							
CS\$NMX	1-80	30-18							
CS\$OPN	1-74	26-14							
CS\$SPL	1-80	26-21	30-14						
CSHALC	1-54	14-4							
CSHINI	1-54	14-6							
CSHNEW	2-29	14-4#							
CSIARE	1-59	3-66	3-194	6-30					
CUPARO	1-74	20-24*							
CUPDRO	1-74	20-38*							
CURRDB	1-55	19-17*	19-53*	22-25					
CXTRMN	1-58	1-62	3-49	3-152					
DBGENT	1-64	3-212							
DETCBS	1-72	17-44							
DECHK	17-66#	17-97							
DETEM	1-43	17-10#							
DETERR	17-62#								
DETO	17-24#	17-96							
DETHI	17-15	17-99#							
DETKIL	17-76#	17-98							
DETONE	17-33	17-53	17-61#	17-69	17-71	17-87			
DETEEC	17-18	17-96#	17-99						
DFJMEM	1-83	3-39							

