

COGO-10/20 Installation Guide

Order No. AA-5511A-TK

June 1978

This installation guide is written for the system manager of a DECsystem-10 or a DECSYSTEM-20 computer installation using the TOPS-10 or TOPS-20 Operating System. The procedures for building and installing the COGO program from the distribution medium are described.

To order additional copies of this document, contact the Software Distribution Center, Digital Equipment Corporation, Maynard, Massachusetts 01754

digital equipment corporation • maynard. massachusetts

The information in this document is subject to change without notice and should not be construed as a commitment by Digital Equipment Corporation. Digital Equipment Corporation assumes no responsibility for any errors that may appear in this document.

The software described in this document is furnished under a license and may be used or copied only in accordance with the terms of such license.

Digital Equipment Corporation assumes no responsibility for the use or reliability of its software on equipment that is not supplied by DIGITAL or its affiliated companies.

Copyright © 1978 by Digital Equipment Corporation

The postage-prepaid READER'S COMMENTS form on the last page of this document requests the user's critical evaluation to assist us in preparing future documentation.

The following are trademarks of Digital Equipment Corporation:

DIGITAL	DECsystem-10	MASSBUS
DEC	DEctape	OMNIBUS
PDP	DIBOL	OS/8
DECUS	EDUSYSTEM	PHA
UNIBUS	FLIP CHIP	RSTS
COMPUTER LABS	FOCAL	RSX
COMTEX	INDAC	TYPESET-8
DDT	LAB-8	TYPESET-10
DECCOMM	DECSYSTEM-20	TYPESET-11

CONTENTS

	Page
PREFACE	v
1.0 DISTRIBUTION MEDIUM	1
2.0 INSTALLATION PROCEDURES FOR COGO-10/20	1
3.0 RUNNING THE COGO-10/20 TEST PROBLEM	8
3.1 Test Problem Input	11
3.2 Test Problem Output	12

TABLES

TABLE 1	TOPS-10 Procedures for Installing, Compiling, and Loading COGO	2
2	TOPS-20 Procedures for Installing, Compiling, and Loading COGO under TOPS-20	5
3	COGO Default Values	8
4	Running the Test Problem under TOPS-10	9
5	Running the Test Problem under TOPS-20	10

PREFACE

This document serves as a guide to the system manager of a DECsystem-10 computer installation using the TOPS-10 Operating System or a DECSYSTEM-20 computer installation using the TOPS-20 Operating System. The procedures for building and installing the COGO program from the distribution medium are described. The following documents provide further details of the installation procedure:

<u>Operator's Guide</u>	DEC-10-ODOGA-B-D
<u>Operator's Guide (KL Series)</u>	AA-5104A-TB
<u>Operator's Guide</u>	DEC-20-OTPGA-B-D
<u>REACT Specification</u>	DECsystem-10 Notebook 11
<u>System Manager's Guide</u>	AA-4169C-TM

1.0 DISTRIBUTION MEDIUM

COGO-10/20 is distributed on 9-channel magtape. The DEC order numbers for the TOPS-10 and TOPS-20 versions are as follows:

Operating System	Order Number
TOPS-10	QH095-YD
TOPS-20	QT095-YD

COGO-10/20 is distributed both as a source program including FORTRAN and MACRO subroutines and as an executable file.

Backing up a distribution medium is recommended.

2.0 INSTALLATION PROCEDURES FOR COGO-10/20

Tables 1 through 3 in this section describe installation procedures for COGO-10/20 as follows:

Table	Description
1	TOPS-10 Procedures for Installing, Compiling, and Loading COGO
2	TOPS-20 Procedures for Installing, Compiling, and Loading COGO
3	COGO Default Values

The following assumptions are made for the installation procedure:

1. All user typeins are terminated by pressing RETURN.
2. For TOPS-10, a directory with the project-programmer number [200,200] and the password COGO was created on the system disk before installation; for TOPS-20, a directory with the user name COGO and password COGO was created on the system disk before installation.
3. All distribution files will be copied to [200,200] on the DECSYSTEM-10 or to <COGO> on the DECSYSTEM-20.
4. After copying files, the correct directory has READ/WRITE privilege.
5. The user knows how to use an available text editor.

To recompile the FORTRAN source subprograms, FORTRAN Version 5A or a later version must be used. If any subprogram is recompiled, all subprograms must be recompiled.

Table 1
TOPS-10 Procedures for Installing, Compiling, and Loading COGO

Step	System Typeout	User Typein	Comments
1		CTRL/C	Call the operating system prompt.
2	.	LOGIN 200,200	Type the command LOGIN and the appropriate project-programmer number.
3	PASSWORD	COGO	The password does not appear at the terminal.
4	JOB1 DECsystem-1099 60312B TTY1 1024 22-MAY-78 MON .	MOUNT MTA:COGO/REELID:COGO	Ask the operator to mount the distribution tape.
5	REQUEST QUEUED Waiting ... 2^C's to EXIT COGO Mounted, MTA000: USED		Wait until the tape is mounted. The operator mounted the distribution tape on device MTA0.
6	.	BACKUP	Call the system program BACKUP to transfer COGO files from magtape to disk.
7	/	TAPE COGO:	After the BACKUP prompt /, enter the device on which your tape is mounted.
8	/	REWIND	Make certain that the tape is at the beginning.
9	/	DENSITY 1600	Set the tape density to 1600 bits per inch (bpi).

Table 1 (Cont.)
TOPS-10 Procedures for Installing, Compiling, and Loading COGO

Step	System Typeout	User Typein	Comments
10	/	RESTORE *.*=ALL: *.*[*,*]	Use the RESTORE command to search the tape and copy the specified files to disk.
11	. . . "DONE /	UNLOAD	After the RESTORE command is done, rewind the magtape to its physical beginning for dismount.
12	/	EXIT	Leave BACKUP, and return to the TOPS-10 command level.
13	.	DISMOUNT COGO/RELEASE	Tell the operator to dismount the distribution tape, and release the tape handler.
14	COGO DISMOUNTED	(no user response)	
15	.	SOS COGO.FOR	To substitute for the default values given in Table 3, use the text editor SOS to make the required changes in the main program of COGO.

Table 1 (Cont.)
TOPS-10 Procedures for Installing, Compiling, and Loading COGO

Step	System Typeout	User Typein	Comments
16	.	COMPILE @COGCOM	Relocatable (REL) binary files for COGO are provided on the distribution tape, but to recompile, use the COMPILE command with the indirect file COGCOM.
	(messages)		Ignore all messages that are not prefixed with the percent sign %.
17	.	R LINK	Call the LINK program.
18	*	@COGLNK	Use the indirect file COGLNK to take the REL files and generate an EXE file.
19	.		COGO-10 is now installed.

Table 2
TOPS-20 Procedures for Installing, Compiling, and Loading COGO

Step	System Typeout	User Typein	Comments
1		CTRL/C	Call the operating system prompt.
2	@	LOGIN COGO COGO PROJ.TASK	Type the command LOGIN followed by the appropriate user name, password, and account string. The password does not appear on the terminal. TOPS-20 recognition input can be used by pressing the ESCape key after LOGIN, after the user name, and after the password to call the guide words (USER NAME), (PASSWORD), and (ACCOUNT), respectively.
3	@	TMOUNT TAPE:COGO	Ask the operator to mount the distribution tape.
4	[OPERATOR NOTIFIED] [MTA0: ASSIGNED]	(no user response)	The operator mounted the distribution tape on device MTA0.
5	@	DUMPER	Call the DUMPER program to transfer the COGO files from the distribution tape to the disk.
6	DUMPER>	TAPE MTA0:	Specify the device on which the tape is mounted.

Table 2 (Cont.)
TOPS-20 Procedures for Installing, Compiling, and Loading COGO

Step	System Typeout	User Typein	Comments
7	DUMPER>	REWIND	Make certain that the tape is at the beginning.
8	DUMPER>	DENSITY 1600	Set the tape density to 1600 bits per inch (bpi).
9	DUMPER>	RESTORE <*>.* <COGO>	Use the RESTORE command to search the tape and copy the specified files to disk.
10	END OF SAVESET	(no user response)	DUMPER has finished restoring the files.
11	DUMPER>	EXIT	Leave DUMPER, and return to the TOPS-20 command level.
12	@	UNLOAD MTA0:	Rewind the magtape to its physical beginning for dismount.
13	@	DEASSIGN MTA0:	Release the tape handler.
14	@	COMPILE @COGCOM	Relocatable (REL) binary files for COGO are provided on the distribution tape, but to recompile, use the COMPILE command with the indirect file COGCOM.

Table 2 (Cont.)
TOPS-20 Procedures for Installing, Compiling, and Loading COGO

Step	System Typeout	User Typein	Comments
	(messages)		Ignore all messages, unless the messages are prefixed by %.
15	@ *	LINK @COGLNK	Call the LINK program and the indirect file COGLNK to take the REL files and generate an executable (EXE) program file.
16	@	SAVE COGO	Save the executable COGO program.
17	@		COGO-20 is now installed.

Table 3
COGO Default Values

Description	FORTTRAN Name	Default Value
Logical unit numbers		
Primary card reader	IVCD	02
Printer (if no printer, set MTPR to 01)	MTPR	03
Card punch	MTCD	20
Positive direction of horizontal axis	ISGH	R
R for right		
L for left		
Positive direction of vertical axis	ISGV	U
U for up		
D for down		
Coordinate pair sequence	ISEQ	VH
HV = Horizontal first, then vertical		
VH = Vertical first, then horizontal		
Zero azimuth direction	IZZ	U
R for right		
L for left		
U for up		
D for down		
Direction of 90 degree azimuth	IZ90	R
R for right		
L for left		
U for up		
D for down		
Azimuth symbols		
0 degrees	MZ	N
90 degrees	M90	E
180 degrees	M180	S
270 degrees	M270	W

COGO is now ready to run. To check the installation procedures, run the test problem.

3.0 RUNNING THE COGO-10/20 TEST PROBLEM

To run the test problem, follow the instructions in Table 4 for TOPS-10 and in Table 5 for TOPS-20.

Table 4
Running the Test Problem under TOPS-10

Step	System Typeout	User Typein	Comments
1		CTRL/C	Call the operating system prompt.
2	.	LOGIN 200,200	
3	PASSWORD:	COGO	
4	.	RUN COGO	
5	SPECIFY INPUT DEVICE/FILENAME>	TEST.DAT	
6	SPECIFY OUTPUT DEVICE/FILENAME>	TTY:	

Table 5
Running the Test Problem under TOPS-20

Step	System Typeout	User Typein	Comments
1		CTRL/C	Call the operating system prompt.
2	@	LOGIN COGO COGO PROJ.TASK	
3	@	RUN COGO	
4	SPECIFY INPUT DEVICE/FILENAME>	TEST.DAT	
5	SPECIFY OUTPUT DEVICE/FILENAME>	TTY:	

3.1 Test Problem Input

```
S O J * EXAMPLES FROM SELLS COGO VERSION 3 MANUAL
*   EXAMPLE OF LOCATE AZIMUTH AND LOCATE BEARING
DELETE COORDINATES 1-100
STORE 40 10000 20000
LOCATE AZIMUTH 40 41 45-00-00 100.
      41 42 S 45-00-00E 100
      42 43 A 41 40 100
LOCATE BEARING 43 44 4 45-00-00 100
      40 50 N45 0 0E 200
      50 51 A41 43 D41 43
DISTANCE 51 42
**   EXAMPLE OF EXTEND ARC COMMAND
DELETE COORDINATES 1-100
STORE 1 200 600
50 1200 600
EXTEND ARC 50 1 200 1570.8
50 1 201 -785.4
**   EXAMPLES OF LOCATE ANGLE, DEFLECTION AND LINE
STORE 3 8000 5000
      4 7700 5000
LOCATE ANGLE 3 4 8 90 0 0 250
      4 8 9 90 0 0 300
      8 9 10 G4 8 9 250
LOCATE DEFLECTION 4 3 12 045-00-00.0 100.00
      4 3 13 -045-00-00.0 100.00
      4 3 22 60-0-0 200
      4 3 23 -G 4 3 22 D 3 22
LOCATE LINE 3 4 5 500
      3 4 6 -500
**   EXAMPLE OF POINTS INTERSECT, AZIMUTH INTERSECT, AND
*   BEARING INTERSECT
DELETE COORDINATES 1-100
STORE 1 5000 5000
      2 5000 4500
AZIMUTH INTERSECT 3 1 10 1 30.1 2-30.
BEARING INTERSECT 4 1 N 20 W 2 N60 E
POINTS INTERSECT 5 2 1 3 4
*   EXAMPLE OF POINTS AZIMUTH INTERSECT AND
*   POINTS BEARING INTERSECT
POINTS AZIMUTH INTERSECT 6 1 3 2 45.
POINTS BEARING INTERSECT 7 1 3 3 S45W -400
*   EXAMPLE OF ARC LINE AZIMUTH, ARC LINE BEARING,
*   ARC LINE POINTS, AND ARC ARC INTERSECT
STORE 10 0 0
      11 900 900
ARC LINE AZIMUTH 15 10 1500 11 -90. 11
ARC LINE BEARING 16 10 1500 10 N15E 11
ARC LINE POINTS 17 11 1000. 10 16 10
ARC ARC INTERSECT 18 10 D 10 15 11 500 15
**   EXAMPLE OF TANGENT COMMAND
DELETE COORDINATES 1-100
STORE 1 200 100
      2 200 300
TANGENT 9 1 -50 10 2 -25
      7 1 -50 6 2 25
      5 1 50 8 2 -25
      3 1 50 4 2 25
```

```

**    EXAMPLE OF TANGENT OFFSET COMMAND
DELETE COORDINATES 1-10
STORE 2 100 100
      3 500 600
      1 400 150
TANGENT OFFSET 10 1 2 3
**    EXAMPLE OF FIT CURVE COMMAND
DELETE COORDINATES 1-100
STORE 1 200 200
      2 400 200
      3 500 400
FIT CURVE 1 2 3 5 6 7 100.
DIVIDE LINE 1 5 2 8
*    FIT CURVE WITH RADIUS UNKNOWN
FIT CURVE 8 2 3 8 9 10
*    EXAMPLE OF DIVIDE LINE AND DIVIDE ARC COMMANDS
STORE 15 0 0
      20 1000 0
      30 0 1000
DIVIDE LINE 15 20 3
DIVIDE ARC 20 30 15 4
*    EXAMPLE OF PARALLEL LINE
STORE 31 200 200
      32 400 100
PARALLEL LINE 31 32 150. 33 34
PARALLEL LINE 31 32 -100. 35 36
PARALLEL LINE 34 36 100. 37 38
**    EXAMPLE OF PARALLEL FIGURE COMMAND
DELETE COORDINATES 1-100
STORE 11 982.8517 1140.9693
STORE 14 907.4955 1177.3215
STORE 23 1000.0000 1000.0000
STORE 24 1044.3302 1023.1214
STORE 25 980.3919 1181.7215
STORE 26 942.9598 1195.8224
STORE 27 1027.1821 1164.0954
STORE FIGURE 1 (23 14 C26L 25 C27R 11 24)
PARALLEL FIGURE 1 10. 30
PARALLEL FIGURE 1 -20. 35
STORE FIGURE 2 (30 31 C26L 32 C27R 33 34)
STORE FIGURE 3 (35 36 C26L 37 C27R 38 39)
E O R
@

```

3.2 Test Problem Output

```

COGO OPENING FILE: COGTAB.TMP FOR TABLE
*    EXAMPLE OF LOCATE AZIMUTH AND LOCATE BEARING
DELETE COORDINATES 1-100
STORE 40 10000 20000
      40
LOCATE AZIMUTH 40 41 45-00-00 100.
      41      10070.7107      20070.7107

      41 42 S 45-00-00E 100
      42      10000.0000      20141.4214

      42 43 A 41 40 100
      43      9929.2893      20070.7107

```


LOCATE BEARING 43 44 4 45-00-00 100
 44 10000.0000 20000.0000

40 50 N45 0 0E 200
 50 10141.4214 20141.4214

50 51 A41 43 D41 43
 51 10000.0000 20141.4214

DISTANCE 51 42
 FROM 51 TO 42 0.0000 FT.

** EXAMPLE OF EXTEND ARC COMMAND
 DELETE COORDINATES 1-100
 STORE 1 200 600
 1
 50 1200 600
 50
 EXTEND ARC 50 1 200 1570.8
 200 199.9963 1600.0000

50 1 201 -785.4
 201 907.1055 -107.1081

** EXAMPLES OF LOCATE ANGLE, DEFLECTION AND LINE
 STORE 3 8000 5000

3
 4 7700 5000
 4
 LOCATE ANGLE 3 4 8 90 0 0 250
 8 7700.0000 5250.0000

4 8 9 90 0 0 300
 9 8000.0000 5250.0000

8 9 10 64 8 9 250
 10 8000.0000 5000.0000

LOCATE DEFLECTION 4 3 12 045-00-00.0 100.00
 12 8070.7107 5070.7107

4 3 13 -045-00-00.0 100.00
 13 8070.7107 4929.2893

4 3 22 60-0-0 200
 22 8100.0000 5173.2051

4 3 23 -6 4 3 22 D 3 22
 23 7900.0000 5173.2051

LOCATE LINE 3 4 5 500
 5 7500.0000 5000.0000

3 4 6 -500
 6 8500.0000 5000.0000

```

**      EXAMPLE OF POINTS INTERSECT, AZIMUTH INTERSECT, AND
* BEARING INTERSECT
DELETE COORDINATES 1-100
STORE 1 5000 5000
      1
      2 5000 4500
      2
AZIMUTH INTERSECT 3 1 10 1 30.1 2 30.
      3      6248.2124      5220.6558

BEARING INTERSECT 4 1 N 20 W 2 N60 E
      4      5238.5472      4913.1759

POINTS INTERSECT 5 2 1 3 4
      5      5000.0000      4840.5296

*      EXAMPLE OF POINTS AZIMUTH INTERSECT AND
* POINTS BEARING INTERSECT
POINTS AZIMUTH INTERSECT 6 1 3 2 45.
      6      5607.3691      5107.3691

POINTS BEARING INTERSECT 7 1 3 3 S45W -400
      7      5754.7833      4727.2267

*      EXAMPLE OF ARC LINE AZIMUTH, ARC LINE BEARING,
* ARC LINE POINTS, AND ARC ARC INTERSECT
STORE 10 0 0
      10
      11 900 900
      11
ARC LINE AZIMUTH 15 10 1500 11 -90. 11
      15      900.0000      1200.0000

ARC LINE BEARING 16 10 1500 10 N15E 11
      16      1448.8887      388.2286

ARC LINE POINTS 17 11 1000. 10 16 10
      17      319.6325      85.6453

ARC ARC INTERSECT 18 10 D 10 15 11 500 15
      18      668.1270      1342.9841

**      EXAMPLE OF TANGENT COMMAND
DELETE COORDINATES 1-100
STORE 1 200 100
      1
      2 200 300
      2
TANGENT 9 1 -50 10 2 -25
      9      249.6078      106.2500

      10      224.8039      303.1250

                        FROM 9 TO 10      97-10-50.7      198.4313

7 1 -50 6 2 25
      7      246.3512      118.7500

      6      176.8244      290.6250

                        FROM 7 TO 6      112- 1-27.5      185.4050

```

```

5 1 50 8 2 -25
  5      153.6488      118.7500

      8      223.1756      290.6250

                        FROM      5      TO      8      67-58-32.5      185.4050

3 1 50 4 2 25
  3      150.3922      106.2500

      4      175.1961      303.1250

                        FROM      3      TO      4      82-49- 9.3      198.4313

**  EXAMPLE OF TANGENT OFFSET COMMAND
DELETE COORDINATES 1-10
STORE 2 100 100
  2
  3 500 600
  3
  1 400 150
  1
TANGENT OFFSET 10 1 2 3
  10      241.4634      276.8293

                        FROM      2      TO      10      226.4520 FT.

                        FROM      10      TO      1      203.0259 FT. LEFT

**  EXAMPLE OF FIT CURVE COMMAND
DELETE COORDINATES 1-100
STORE 1 200 200
  1
  2 400 200
  2
  3 500 400
  3
FIT CURVE 1 2 3 5 6 7 100.
  5      338.1966      200.0000

      6      338.1966      300.0000

      7      427.6393      255.2786

DIVIDE LINE 1 5 2 8
  8      269.0983      200.0000

*  FIT CURVE WITH RADIUS UNKNOWN
FIT CURVE 8 2 3 8 9 10
  8      269.0983      200.0000

      9      269.0983      411.8034

     10      458.5410      317.0820

*  EXAMPLE OF DIVIDE LINE AND DIVIDE ARC COMMANDS
STORE 15 0 0
  15
  20 1000 0
  20
  30 0 1000
  30

```

DIVIDE LINE 15 20 3		
16	333.3333	-0.0000
17	666.6667	-0.0000

DIVIDE ARC 20 30 15 4		
21	923.8795	382.6834
22	707.1068	707.1068
23	382.6834	923.8795

* EXAMPLE OF PARALLEL LINE
STORE 31 200 200

31		
32	400 100	
PARALLEL LINE 31 32 150. 33 34		
33	267.0820	334.1641
34	467.0820	234.1641

PARALLEL LINE 31 32 -100. 35 36		
35	155.2786	110.5573
36	355.2786	10.5573

PARALLEL LINE		
	34 36 100. 37 38	
37	556.5248	189.4427
38	444.7214	-34.1641

** EXAMPLE OF PARALLEL FIGURE COMMAND
DELETE COORDINATES 1-100

STORE 11	982.8517	1140.9693
11		
STORE 14	907.4955	1177.3215
14		
STORE 23	1000.0000	1000.0000
23		
STORE 24	1044.3302	1023.1214
24		
STORE 25	980.3919	1181.7215
25		
STORE 26	942.9598	1195.8224
26		
STORE 27	1027.1821	1164.0954
27		
STORE FIGURE 1 (23 14 C26L 25 C27R 11 24)		

1		
PARALLEL FIGURE 1 10. 30		
30	991.1339	995.3748
31	898.6294	1172.6963
32	989.7499	1178.1963
33	991.7178	1145.5945
34	1053.1963	1027.7466

```

PARALLEL FIGURE 1 -20. 35
  35      1017.7322      1009.2505
  36      925.2277      1186.5720
  37      961.6758      1188.7720
  38      965.1195      1131.7189
  39      1026.5980      1013.8710

STORE FIGURE 2 (30 31 C26L 32 C27R 33 34)
                2
STORE FIGURE 3 (35 36 C26L 37 C27R 38 39)
                3
END OF RUN
@

```

READER'S COMMENTS

NOTE: This form is for document comments only. DIGITAL will use comments submitted on this form at the company's discretion. If you require a written reply and are eligible to receive one under Software Performance Report (SPR) service, submit your comments on an SPR form.

Did you find this manual understandable, usable, and well-organized? Please make suggestions for improvement.

Did you find errors in this manual? If so, specify the error and the page number.

Please indicate the type of reader that you most nearly represent.

- ☐ Assembly language programmer
- ☐ Higher-level language programmer
- ☐ Occasional programmer (experienced)
- ☐ User with little programming experience
- ☐ Student programmer
- ☐ Other (please specify)_____

Name_____ Date_____

Organization_____

Street_____

City_____ State_____ Zip Code_____

or

Please cut along this line.

----- **Fold Here** -----

Do Not Tear - Fold Here and Staple

**FIRST CLASS
PERMIT NO. 152
MARLBOROUGH, MA
01752**

[REDACTED]

Postage will be paid by:

digital

Software Documentation
200 Forest Street MR1-2/E37
Marlborough, Massachusetts 01752